

Maintenance

This service is used to define and maintain the parameters and definitions that are required by Adabas System Coordinator.

- Maintenance Menu
- Maintain Client Runtime Controls
- Maintain Daemon Groups

Maintenance Menu

▶ To display the Maintenance menu

- Select service 1 from the main menu.

Note:

The Current LFILE 152 Settings window may appear before the Maintenance menu. See the section System Settings for more information.

```

17:36:58      ***** A D A B A S   SYSTEM COORDINATOR 8.2.2 *****      2011-12-03
                - Maintenance -                                          C11000M1
Run-mode: Pulsing (node 2650)

                Code      Service
                ----      -
                1         Client Runtime Controls
                2         Daemon Group Parameters
                .         Exit
                ----      -
Code....: _

Command ==>

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help           Exit                                     Menu

```

From this menu, you can	Service	Cmd
maintain client runtime controls	1	1.1
maintain daemon group parameter values	2	1.2

Maintain Client Runtime Controls

This function is used to define/maintain runtime controls for jobs that use Adabas System Coordinator services and any of the client-based products that depend on Adabas System Coordinator: Adabas Fastpath, Adabas Transaction Manager and Adabas Vista.

Runtime controls determine the operational behaviour of these products in a given job. You can adjust this behaviour on a case-by-case basis by specifying overrides to tailor operation for a particular transaction code (TP systems), stepname (batch jobs) or login id. You can also define a special type of API runtime control, for completely dynamic reconfiguration.

Note:

See section Parameters for a complete description of all runtime controls.

Note:

Runtime controls are shared between all installed optional products, and can be defined by any of the administration applications (SYSCOR, SYSAVI, SYSAFP, SYSATM). You can administer the runtime controls of any product from any application.

- List Runtime Controls
- Add a Runtime Control
- Maintain Runtime Controls

List Runtime Controls

To display a list of existing definitions

1. Select service 1 from the Maintenance menu or enter the command 1 . 1 on the command line.

```

18:08:21      ***** A D A B A S   SYSTEM COORDINATOR 8.2.2 *****      2011-12-03
                - Client Runtime Controls (COR) -                          U11300M1
Run-mode: Pulsing (node 2650)                               Reposition to Type: _____
                                                         Name: _____

                Client Controls
C Type          Name          AFP  AVI  ATM  COR          Comments
- CICS (DTR)    CICCLUST    Y    Y    Y    Y           Overrides,Info
- Batch        CORP*****  Y    Y    Y    Y
-              *DEFAULT    Y    Y    Y    Y
-              CORQ0100    Y    Y    Y    Y
-              CORQ0200  Off   Y    Y    Y
- COM-LETE     DAEFCODE    Y    Y    Y    Y
- TSO          *DEFAULT    Y    Y    Y    Y

Mark with Jobs,Modify,Purge,Rename,Copy,Overrides,Information,History
End of List
Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help          Exit  Refr                               Add  Prods Menu

```

2. The list shows the service or job type, the name and for which products controls are defined. The Comments column shows whether overrides or site information are defined for this service/job.
3. The name identifies the service or job to which these controls apply. A service is a collection of jobs which form a single DTR cluster, for example CICSplex, CICS/MRO with Dynamic Transaction Routing, IMS TM or UTM. For jobs, the name may be a wildcard or you can specify a set of default controls for jobs of that type.
4. Taking the above example:
 - any batch job with a name beginning CORP will use the controls defined for CORP*****
 - job CORQ0100 will use its own controls (but it will use the Adabas Transaction Manager controls defined for *DEFAULT, because there are none defined for CORQ0100)
 - job CORQ0200 will use its own controls and Adabas Fastpath is disabled for this job
 - any other batch job will use the controls defined for *DEFAULT
5. If you wish to display or modify controls or overrides for one of the other products, press PF11 until the required product appears in the screen title and message line:

```

18:10:27      ***** A D A B A S   SYSTEM COORDINATOR 8.2.2 *****      2011-12-03
                - Client Runtime Controls (AFP) -                          U11300M1
Run-mode: Pulsing (node 2650)                                Reposition to Type: _____
                                                         Name: _____

                Client Controls
C Type          Name          AFP  AVI  ATM  COR          Comments
- CICS (DTR)    CICCLUST    Y    Y    Y    Y          Overrides,Info
- Batch        CORP****    Y    Y    Y    Y
-              *DEFAULT    Y    Y    Y    Y
-              CORQ0100    Y    Y    Y    Y
-              CORQ0200    Off  Y    Y    Y
- COM-LETE     DAEFCODE    Y    Y    Y    Y
- TSO          *DEFAULT    Y    Y    Y    Y

Mark with Jobs,Modify,Purge,Rename,Copy,Overrides,Information,History
Now maintaining Adabas Fastpath runtime controls
Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help          Exit  Refr                                Add  Prods Menu

```

6. If there is more than a screen of definitions, use PF7 and PF8 to scroll up and down, m and PF7 and m and PF8 to go to the top or bottom of the list, or use the Reposition field to position anywhere within the list.

Add a Runtime Control

To add a new definition

1. Press PF10 from the Client Runtime Controls list.

The following window will appear:

```

18:16:44      ***** A D A B A S   SYSTEM COORDINATOR 8.2.2 *****      2011-12-03
                - Add Client Runtime Control -                          U11310M1
Run-mode: Pulsing (node 2650)

Select (mark one) :

                _ Batch
                _ COM-LETE
                _ CICS (DTR - Dynamic transaction routing)
                _ CICS (Standard)
                _ IMS (DTR)
                _ UTM (DTR)
                _ TSO
                _ CMS
                _ TIAM
                _ more choices for type or

                _ API controlled - type 1
                _ API controlled - type 2

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help           Exit                                           Menu

```

2. Select a job type for the job from the list provided.

Each different job type has different characteristics and it is therefore important to select the correct type.

Note:

Select the job type "CICS (Standard)" if CICS/MRO is to be used without dynamic transaction routing or for other CICS environments. Select the job type "CICS (DTR – Dynamic Transaction Routing)" if CICS/MRO is to be used with dynamic transaction routing.

If you mark the selection "more choices for type", another selection window will appear with additional job types. If you need to use any of these, contact Software AG for advice.

If you mark either of the API controlled types, you can define a set of runtime controls which can be activated dynamically by API. You must enable API overrides for any job where you want to use this API definition and name it in the job's list of permissible APIs.

Note:

Dynamically activated API runtime controls are not yet available.

3. After selecting a job type, press Enter. In the following example, the job type "CICS (DTR – Dynamic Transaction Routing)" was selected which results in the following screen being displayed:

```

18:17:29      ***** A D A B A S   SYSTEM COORDINATOR 8.2.2 *****      2011-12-03
                - Add Client Runtime Control -                          U11310M4
Run-mode: Pulsing (node 2650)

                Type: CICS (DTR)
                Name: _____

This is a complex type of runtime which is capable of running in basic mode
and in DTR mode.

You must define a System Coordinator group (and its daemons) with PRODUCT=DTR
AND the daemon(s) in that group must be executing in order to achieve DTR
capability, otherwise it is ignored.

The name specified above is a unique name for the runtime controls for the
DTR service (it is not a jobname). You must also use the 'Expand' line
command to enter the list of all jobs in the service.

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
                Help           Exit           Add                               Menu

```

4. Enter the service name (which may not contain * wildcards, in this example CICSPROD was entered) and press PF5 to continue:

```

10:49:46      ***** A D A B A S   SYSTEM COORDINATOR 8.2.2 *****      2012-03-13
                - System Coordinator Runtime Controls -                  U11310M5
Run-mode: Pulsing (node 2650)
Type: CICS (DTR)   Name: CICSPROD
Operation: Normal autodetect: X Enable without products: _ Disable all: _
API runtime overrides....: N (Y/N)   Threadsafe operation...: Y (Y/N)
Use additional exits.....: N (Y/N)
Maximum idle time (sec)..: 3600_____ Non-terminal idle time.: _____
Generate RSP009/79 (Y/N)..: Y (until 0_____ seconds elapse)
Messages - Local.....: Console Y and/or DDMSG file _
                Or - Daemon routing: _
Latency - Local (Y/N)....: N

Latency - Daemon (Y/N)...: Y
                to disk.....: N
Activity pulse every.....: _____ commands or _____ seconds
Group name.....: _____

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
                Help           Exit           Add                               Menu

```

5. The screen is pre-filled with default values for this control type. Please refer to the Parameters section for a description of each parameter. DTR jobs require a System Coordinator Group name. Enter that now or press PF5 which will set the group name, if only one group is defined, or give you a list of defined groups to choose from, if more than one group is defined.

```

10:50:27      ***** A D A B A S   SYSTEM COORDINATOR 8.2.2 *****      2012-03-13
                - System Coordinator Runtime Controls -                      U11310M5
Run-mode: Pulsing (node 2650)
Type: CICS (DTR)   Name: CICSPROD
  Operation: Normal autodetect: X Enable without products: _ Disable all: _
  API runtime overrides....: N (Y/N)   Threadsafe operation...: Y (Y/N)
  Use additional exits.....: N (Y/N)
  Maximum idle time (sec)..: 3600_____ Non-terminal idle time.: _____
  Generate RSP009/79 (Y/N)..: Y (until 0_____ seconds elapse)
  Messages - Local.....: Console Y and/or DDMSG file _
    Or - Daemon routing: _
  Latency - Local (Y/N)....: N

  Latency - Daemon (Y/N)...: Y
    to disk.....: N
  Activity pulse every.....: _____ commands or _____ seconds
  Group name.....: DEMO82__

Fields Modified - Use PF5 to Update or PF3 to Exit
Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help           Exit           Add                                     Menu

```

6. Press PF5 again to add the control.

```

10:51:20      ***** A D A B A S   SYSTEM COORDINATOR 8.2.2 *****      2012-03-13
                - System Coordinator Runtime Controls -                      U11310M5
Run-mode: Pulsing (node 2650)
Type: CICS (DTR)   Name: CICSPROD
  Operation: Normal autodetect: X Enable without products: _ Disable all: _
  API runtime overrides....: N (Y/N)   Threadsafe operation...: Y (Y/N)
  Use additional exits.....: N (Y/N)
  Maximum idle time (sec)..: 3600_____ Non-terminal idle time.: _____
  Generate RSP009/79 (Y/N)..: Y (until 0_____ seconds elapse)
  Messages - Local.....: Console Y and/or DDMSG file _
    Or - Daemon routing: _
  Latency - Local (Y/N)....: N

  Latency - Daemon (Y/N)...: Y
    to disk.....: N
  Activity pulse every.....: _____ commands or _____ seconds
  Group name.....: DEMO82__

Parameter ADDED
Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help           Exit           Upd                                     More API                               Menu

```

You can now:

- Modify the values and press PF5 to update them

- Press PF3 to return to the list
- Press PF12 to return to the main menu
- Press PF10 to define permissible API controls (these will only be honoured if you also set API runtime overrides to Y). Enter the names of up to 64 API controls, which must already be defined, and press PF5

```

18:21:32      ***** A D A B A S   SYSTEM COORDINATOR 8.2.2 *****      2011-12-03
                - System Coordinator Runtime Controls -                      U11310M6
Run-mode: Pulsing (node 2650)
Type: CICS (DTR)
Name: CICSPROD

The following API runtime overrides are allowed:

_____
_____
_____
_____
_____
_____
_____
_____

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help      Exit      Upd                               Menu
    
```

- Press PF9 to define additional options and select option 1 to define command retry requirements, option 2 to define debug settings or option 3 to define unified trace settings:

```

+-----+
| 18:23:28      Runtime Controls      2011-12-03 |
|              - Additional -         U1SCJAM1 |
|                                             |
|      Code      Service                |
|      ----      - - - - -              |
|          1      Command Retry          |
|          2      Debug Settings          |
|          3      Unified Trace Settings  |
|          .      Exit                    |
|      ----      - - - - -              |
| Code.....: _ |
|                                             |
| Command ==> |
|   PF1 Help   PF3 Exit   PF12 Menu      |
|                                             |
+-----+
    
```


- Use unified trace settings to define trace requirements for this client job:
 1. Size of in-memory trace buffer.
 2. Trace collection; local trace file is only available for batch-type jobs and forward to the daemon trace file is only available for jobs defined to use a daemon
 3. Adabas response code and sub-code that cause trace data to be written and whether or not generic errors trigger tracing
 4. Whether or not to trigger a debug event on response code trace activation

```

18:25:48      ***** A D A B A S   SYSTEM COORDINATOR 8.2.2 *****      2011-12-03
                - Unified Trace Settings -                               U1SCTRM1

Trace size (KB): 0_ (no tracing = 0; maximum = 32)

Trace collection (mark one)
  No collection.....: X
  In memory only.....: _
  Local trace file.....:
  Forward to the daemon trace file.....: _

Dynamic options
  Limited debug trace:
    Response code trace activation....: 0__
    Sub-code.....: 0____
    Generic error response codes (Y/N): N
    Debug event activation (Y/N).....: N

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help           Exit           Upd

```

7. Here is an example of adding controls for a batch job. Press PF10 from the list, mark Batch and press Enter to continue:

```

18:33:14      ***** A D A B A S   SYSTEM COORDINATOR 8.2.2 *****      2011-12-03
                - Add Client Runtime Control -                          U11310M1
Run-mode: Pulsing (node 2650)

Select (mark one) :

                x Batch
                _ COM-LETE
                _ CICS (DTR - Dynamic transaction routing)
                _ CICS (Standard)
                _ IMS (DTR)
                _ UTM (DTR)
                _ TSO
                _ CMS
                _ TIAM
                _ more choices for type or

                _ API controlled - type 1
                _ API controlled - type 2

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help           Exit                                           Menu

```

8. Enter the jobname and press PF5:

```

18:35:06      ***** A D A B A S   SYSTEM COORDINATOR 8.2.2 *****      2011-12-03
                - Add Client Runtime Control -                          U11310M3
Run-mode: Pulsing (node 2650)

      Type: Batch
      Name: natbat__ (* for default controls for this type)

This is a standard type of runtime.

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help           Exit           Add                                           Menu

```

9. A job name may contain one or more asterisks (*) to indicate a wild card. For example, the runtime control with the name CICS**PR will be found by any job with the value "CICS" in positions 1-4 and the value "PR" in positions 7-8, no matter what the characters are in positions 5-6. If an asterisk (*) is the last character in a job name, the remainder of positions in the name through the eighth are padded with asterisks. A single asterisk indicates that is the default definition for this job type.

10. Controls are always matched on type. The order of search within type is
 1. Match on exact job name.
 2. Match on wild card definitions.
 3. Use the default for the job type, if one has been defined.

Note:

The number of wild card job names defined for a job type has a direct effect on the number of Adabas commands needed to establish the runtime controls at initialization. This is particularly relevant to batch jobs that process relatively few Adabas commands.

11. Different control types have different settings and different default values. Make any required changes and press PF5 to add the definition. You can then define API overrides and additional options or return to the list, as described in 6.

```

10:52:32      ***** A D A B A S   SYSTEM COORDINATOR 8.2.2 *****      2012-03-13
              - System Coordinator Runtime Controls -                      U11310M5
Run-mode: Pulsing (node 2650)
Type: Batch      Name: NATBAT__
  Operation: Normal autodetect: X Enable without products: _ Disable all: _
  API runtime overrides....: N (Y/N)
  Use additional exits....: N (Y/N)
  Maximum idle time (sec)..: _____

  Messages - Local.....: Console Y and/or DDMSG file _
              Or - Daemon routing: _
  Latency - Local (Y/N)....: Y

  Latency - Daemon (Y/N)...: N
              to disk.....: N
  Activity pulse every....: _____ commands or _____ seconds
  Group name.....: _____

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help           Exit           Add                               Menu

```

Maintain Runtime Controls

To maintain a job parameter


- Select it by entering one of the following options in column C on the Client Runtime Controls list:

j	list jobs
m	modify
p	purge
r	rename
c	copy
o	overrides
i	site information

Modify provides screens in which you can make modifications to the job parameters. See section Parameters for information on each parameter. For purge, rename, and copy, you are prompted to confirm the action to be taken.

- Modify Runtime Control
- List jobs in Runtime Control
- Purge a Runtime Control
- Rename a Runtime Control
- Copy a Runtime Control
- Maintain Site Information
- Maintain Client Runtime Control Overrides
- Dynamic Client Runtime Configuration for Experts

Modify Runtime Control

 **To modify a runtime control:**

1. Select it from the list by marking column C with an "m".

```

16:03:05      ***** A D A B A S   SYSTEM COORDINATOR 8.2.2 *****      2012-03-12
                - System Coordinator Runtime Controls -                      U11310M5
Run-mode: Pulsing (node 2650)
Type: COM-LETE      Name: DAEFCODE
Operation: Normal autodetect: X Enable without products: _ Disable all: _
API runtime overrides....: N (Y/N)
Use additional exits....: N (Y/N)
Maximum idle time (sec)..: 3600_____ Non-terminal idle time.: _____
Generate RSP009/79 (Y/N): Y (until 0_____ seconds elapse)
Messages - Local.....: Console _ and/or DDMSG file _
      Or - Daemon routing: _
Latency - Local (Y/N)....: Y

Latency - Daemon (Y/N)...: N
      to disk.....: N
Activity pulse every.....: _____ commands or _____ seconds
Group name.....: _____

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help           Exit           Upd           More API           Menu
    
```

2. Make any necessary modifications.
3. Use PF9 to modify additional options.
4. Use PF10 to modify the list of permissible API overrides.
5. Press PF5 to confirm your changes or PF3 to exit.

List jobs in Runtime Control

To list jobs in a runtime control:

1. Select it from the list by marking column C with a "j".

```

15:25:27      ***** A D A B A S   FASTPATH SERVICES 8.2.2 *****      2012-03-08
                - Client Runtime Service Members -                          U11390M1

      Job type: IMS (DTR)
      Service name: BLA01
                C Name                               Comments
                _ IMSJOB1

Mark with Purge,Rename,History
Top of List
Command ==>

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help           Exit  Refr                               Add           Menu

```

2. List jobs is only relevant for DTR definitions. It allows you to define which jobs comprise that DTR service. Use PF10 to add a job. You can subsequently purge or rename it by marking it with P or R. All jobs defined for a DTR service will use the runtime controls specified on that service.

Purge a Runtime Control

To purge a runtime control

1. Select it from the list by marking column C with a "p".

```

+-----+
! 11:41:08 Purge 2006-07-21 !
! Runtime Control U11340M1 !
! !
! Type: Batch !
! Name: CORQ0200 !
! !
! - All !
! - Transaction Mgr. !
! - Fastpath !
! - Vista !
! !
! Mark Product(s) to purge or All !
! (Overrides will also be purged) !
! Command ==> !
! PF1 Help PF3 Exit PF5 Purge !
! !
+-----+

```

2. Mark which products' runtime controls you wish to purge or All to purge the entire control.
3. Press PF5 to confirm

Rename a Runtime Control

To rename a runtime control

1. Select it from the list by marking column C with a "r".

```

+-----+
! 11:43:19 Rename 2006-07-21 !
! Runtime Control U11350M1 !
! !
! Type: Batch !
! Name: CORQ0200 !
! New Name: _____ !
! Press PF5 to confirm rename !
! !
! Command ==> !
! PF1 Help PF3 Exit PF5 Rename !
! !
+-----+

```

2. Specify the new name, which must not already exist.
3. Press PF5 to confirm

Copy a Runtime Control

▶ To copy a runtime control

1. Select it from the list by marking column C with a “c”.

```

+-----+
! 11:44:20      Copy      2006-07-21 !
!           Runtime Control U11360M1 !
!                                           !
!      Type: Batch                       !
!      Name: CORP****                    !
!                                           !
!      _ All                             !
!      _ Transaction Mgr.                !
!      _ Fastpath                        !
!      _ Vista                           !
!                                           !
!      Mark Product(s) to copy or All    !
!                                           !
!      Copy to .....: _____        !
!      Copy Overrides: N (Y/N - All)     !
!      Command ==>                       !
!      PF1 Help   PF3 Exit   PF5 Copy    !
!                                           !
+-----+

```

2. Mark which products' runtime controls you wish to copy.
3. Specify the job name to which these runtime controls will be copied, which must not already exist.
4. If you select All, you may also copy any defined overrides by entering Y against Copy Overrides.
5. Press PF5 to confirm

Maintain Site Information

▶ To maintain site information

1. Select it from the list by marking column C with a “i”.


```

11:45:28      ***** A D A B A S      SYSTEM COORDINATOR 8.2.2 *****      2006-07-21
                - Client Runtime Controls Site Information -      U11370M1

Run-mode: Local
Type: CICS (DTR)
Name: CICCLUST

Site Information
-----

DYPR=FNAT=(60099,205) PROFILE=CICSPROD_____
_____
_____

You may define up to 256 bytes of alphanumeric data (site information), which
is stored with this runtime control definition and may be retrieved at runtime
using the documented API.

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help           Exit           Upd                   Purge                   Menu
    
```

2. Modify the site information as required and press PF5 to save your changes, or press PF9 to purge the site information.

Maintain Client Runtime Control Overrides

 **To list runtime control overrides**

1. Select it from the Runtime Control maintenance list by marking column C with an 'o'.

```

18:45:25      ***** A D A B A S      SYSTEM COORDINATOR 8.2.2 *****      2011-12-03
                - Client Runtime Controls Override Summary (COR) -      U11380M1
Run-mode: Pulsing (node 2650)                      Reposition to Type: _____
Type: CICS (DTR)   Name: CICCLUST                      Name: _____

                Overrides
C Type          Name          AFP  AVI  ATM  COR          Comments
_ Transaction   N426                      Y          Y

Mark with Modify,Purge,Rename,Copy,Information
End of List
Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help           Exit  Refr                   Add  Prods Menu
    
```

2. This screen lists the runtime control overrides that have been defined for each product.
3. To add a new override, press PF10, mark the type of override you want to add and provide a name:

```

11:50:36      ***** A D A B A S   SYSTEM COORDINATOR 8.2.2 *****      2006-07-21
                - Add Client Runtime Control Override -                      U11381M1

Run-mode: Local
Type: CICS (DTR)   Name: CICCLUST

Select the override type ....: _ Login id
(mark one)                x Transaction

and specify the override name: natp_____

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help           Exit           Add                               Menu

```

4. Press PF5 to add an empty override, which you can then modify as required:

```

18:47:13      ***** A D A B A S   SYSTEM COORDINATOR 8.2.2 *****      2011-12-03
                - Client Runtime Controls Override Summary (COR) -          U11380M1
Run-mode: Pulsing (node 2650)                      Reposition to Type: _____
Type: CICS (DTR)   Name: CICCLUST                      Name: _____

                Overrides
C Type          Name          AFP  AVI  ATM  COR          Comments
_ Transaction   NATP
-              N426                Y          Y

Mark with Modify,Purge,Rename,Copy,Information

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help           Exit Refr                               Add Prods Menu

```

5. Enter one of the following options in the C column to select an entry:

m	modify
p	purge
r	rename
c	copy
i	site information

6. These options are the same as the ones available for maintaining client runtime controls except that they maintain the override controls rather than the base level controls.
7. Use PF11 to select the product for which you want to define or modify an override.

Dynamic Client Runtime Configuration for Experts

You can dynamically change some runtime controls for your current session. To do this, enter CORENV and use PF11 to select the required product as in the following example.

Note:

Some dynamic changes may take some time to take effect depending upon the product/setting in question.

```

18:49:59      ***** A D A B A S   SYSTEM COORDINATOR 8.2.2 *****      2011-12-03
                - Main Menu -                                          C1MAINM1
Run-mode: Pulsing (node 2650)

                Code      Service
                ----      -
                0      System Settings
                1      Maintenance
                2      Current Activity Displays
                3      Special Services
                4      About System Coordinator
                .      Exit
                ----      -
Code...: _

You can easily switch around the tools for Fastpath, Vista etc by use of
PF11, or use the codes COR, AFP, AVI, AAF, ATM as commands - anytime.

Command ==> corenv
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help           Exit                                           Prods Vers
    
```

Which shows you the current System Coordinator runtime controls in effect for your session.

```

16:09:27          ***** CURRENT SESSION CONTROLS *****          2012-03-12
                - System Coordinator Session Controls -          CORENVM1

API runtime overrides....: N          Threadsafe operation...: Y
Use additional exits.....: N
Maximum idle time (sec)..: 3600          Non-terminal idle time.:
Generate RSP009/79 (Y/N)..: Y (until 0          seconds elapse)
Cleanup at start.....: N (Y/N)
Messages - Local.....: Console Y and/or DDMSG file _
          Or - Daemon routing: _
Latency - Local (Y/N)....: Y
          TSQ prefix.....: WORK
Latency - Daemon (Y/N)...: N
          to disk.....: N
Activity pulse every.....: 100          commands or 30          seconds
Group name.....: WORKSHOP

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
          Help          Exit          Upd  Reset          More          Prods

```

Maintain Daemon Groups

This section describes how to add/maintain daemon groups.

Adabas System Coordinator daemon groups are used to manage clustered (multiregion or IBM Sysplex) applications.

The daemon group defines the types of applications to be managed and the node numbers of the daemons that will manage those applications. One daemon must be active on each operating system image that hosts the application. Any application job can then be defined to this group using the Client Runtime Controls function of SYSCOR, SYSAVI, SYSAFP, or SYSATM Online Services.

- Main Menu
- Adding a Daemon Group Definition
- Maintaining a Daemon Group Definition
- Maintain a Daemon Group Daemon Definition

Main Menu

To invoke the daemon group maintenance menu

1. Select service 2 from the Maintenance menu or enter the command 1 . 2 on a command line.

```

09:25:46      ***** A D A B A S   SYSTEM COORDINATOR 8.2.2 *****      2011-12-04
                        System Coordinator Groups                          C11200M1
Run-mode: Pulsing (node 2650)

C Group Name   Type      SVC ID   Daemons
- DEMO82      Multi     254      2
- TSTGROUP    Single    253      1

Mark with M(odify),P(urge),R(ename),L(ist)

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help           Exit  Refr                               Add           Menu
    
```

2. Enter one of the following options in the C column:

m	Modify group definition
p	Purge group definition
r	Rename group definition
l	List daemons in group

3. Use PF10 to add a new group definition

Adding a Daemon Group Definition

To add a new daemon group definition

1. Press PF10 on the System Coordinator Group menu. The following screen will appear:

```

+-----+
| 09:27:38                Add                2011-12-04 |
|                System Coordinator Group    C11210M1 |
|
|      Group Name: _____   SVC ID: _____ |
|
| System Type:  _ Standard single-system image... |
| (Mark one)   _ There is only one daemon in the group. |
|              _ Standard multi-system images - XCF... |
|              _ This enables multiple XCF group daemons. |
|              _ Standard multi-system images - Net-Work... |
|              _ This enables multiple Net-Work group daemons. |
|
| Group-wide latency service: |
|   Full crash recovery disk file (Y/N): N |
|
| Command ==> |
|   PF1 Help   PF3 Exit   PF5 Add   PF9 More |
+-----+

```

2. In the field Group Name, enter the name for the group.

The group name is used to control communication between Adabas System Coordinator daemon peers in an operating system cluster. For example, the daemons communicate using an XCF group with this name in an IBM parallel sysplex. This name must be specified in the job definition for Adabas options such as Adabas Fastpath or Adabas Vista.

3. In the field SVC ID, define the router (SVC) number that is used for communicating with the group (not applicable to BS2000 or z/VM systems).

This must be the same in all parts of a cluster.

4. In the fields System Type, specify whether the group is to coordinate:

- A single system image.
- Multiple system images. This is used to support coordinator daemons running Adabas Fastpath buffers or Adabas Transaction Manager across multiple system images and also to support dynamic transaction routing across multiple system images.
- Multiple system images using Entire Net-Work for communication between images. This is used to support coordinator daemons running Adabas Fastpath buffers or Adabas Transaction Manager across multiple system images and also to support dynamic transaction routing across multiple system images. You are recommended only to use Entire Net-Work if XCF is not available.

5. In the field Full crash recovery disk file, select whether or not latent sessions for client jobs managed by this daemon group are to be written to disk file. This feature allows client sessions to resume processing after a client job or daemon failure.

- If you are running under BS2000, specify the global common memory pool using the additional parameters that appear in the Add System Coordinator Group Member window.

Specify a name, virtual start address, and size for the pool.

The pool you specify is used for allocation of all shared user memory for clustered applications defined to this System Coordinator group.

- Press PF5 to add the group definition.
- Press PF9 to see more Daemon Group definition fields and the following screen will appear:

```

+-----+
| 16:04:19      Additional Group Parameters      2012-03-08      |
|              System Coordinator Groups        C11210M2      |
|                                                    |
| Messages - daemon..... Console: Y and/or DDMSG file: _    |
| Messages - databases... Console: Y and/or DDMSG file: _    |
|                                                    |
| Command ==>                                           |
|              PF3 Quit          PF5 Upd          |
+-----+
    
```

- In the "Runtime messages – databases" fields select either one or both options for the destination of messages output by the Adabas System Coordinator component in the database and the other products that use its services.

Messages, by default, are written to the console. Messages issued by databases that are within the same daemon group may either be directed instead (or in addition) to a file (DDMSG) by selecting the Local file option. The DDMSG output must be introduced to the databases execution control script and the file must be correctly in place for the messages to appear. In some operating systems it will automatically appear to list output.

- The settings from the "More" screen can be confirmed by using PF10. The daemon group will not be created until PF5 is pressed on the first screen.
- Press PF5 to confirm any changes made on this screen, or PF3 to return to the main group screen.

Maintaining a Daemon Group Definition

After adding the group, you can change any of its attributes, by entering ‘m’ against it:

```

+-----+
| 10:55:35          Modify          2011-12-04 |
|          System Coordinator Group      C11230M1 |
|                                     |
|          Group Name: DEMO82          SVC ID: 254__ |
|                                     |
| System Type: _ Standard single-system image... |
| (Mark one)   There is only one daemon in the group. |
|       X     Standard multi-system images - XCF... |
|             This enables multiple XCF group daemons. |
|       _     Standard multi-system images - Net-Work... |
|             This enables multiple Net-Work group daemons. |
|                                     |
| Group wide latency service: |
|   Full crash recovery disk file (Y/N): N |
|                                     |
| Command ==> |
|   PF1 Help          PF3 Exit          PF5 Upd          PF9 More |
+-----+

```

Make any changes required and press PF5 to confirm them. Press PF9 to see further parameters:

```

+-----+
| 16:10:00          Additional Group Parameters      2012-03-08 |
|          System Coordinator Groups      C11210M2 |
|                                     |
| Messages - daemon..... Console: Y and/or DDMSG file: _ |
| Messages - databases... Console: Y and/or DDMSG file: _ |
|                                     |
| Command ==> |
|           PF3 Quit          PF5 Upd |
+-----+

```

Make any changes required then enter PF5 to confirm these changes or PF3 to return to the first screen.


```
+-----+
| 16:10:00      Additional Group Parameters      2012-03-08      |
|              System Coordinator Groups      C11210M2      |
|                                                     |
| Messages - daemon..... Console: Y and/or DDMSG file: _  |
| Messages - databases... Console: Y and/or DDMSG file: _  |
|                                                     |
| Command ==>                                         |
|              PF3 Quit          PF5 Upd            |
+-----+
```

You can also purge or rename the group. You must use purge and rename with care as you may invalidate other definitions (client runtime controls and Adabas Fastpath buffer definitions) that refer to the group being purged or renamed.

To purge, enter 'p' against the group to be purged:

```
+-----+
| 11:25:01      Purge          2011-09-01      |
|              System Coordinator Group      C11240M1      |
|                                                     |
|              Group Name: TESTMULT          |
|              SVC ID: 253                    |
|                                                     |
|              PF5 to Confirm Purge          |
|                                                     |
| Command ==>                                         |
|              PF1 Help      PF3 Exit      PF5 Purge      |
+-----+
```

and press PF5 to confirm.

To rename, enter 'r' against the group to be renamed:

- modify a daemon entry by entering 'm' in the C column adjacent to the entry to be modified.
2. If you are adding a new group, you must add at least one daemon.

For each daemon, specify the following:

- **Daemon Job Name:** The name of the job or started task that will run the Adabas System Coordinator daemon (SYSCO).
- **Node ID:** The Adabas Node ID (target) used to identify the daemon to the network.

Note:

You may not define Node ID 255, because 255 is reserved for use by Natural.

3. Entering m against a daemon presents this modification screen:

```

17:07:44      ***** A D A B A S   SYSTEM COORDINATOR 8.2.2 *****      2012-03-12
              - Adabas System Coordinator Daemon Parameters -          C11261M1
Run-mode: Pulsing (node 17004)
Group: RPEGRP1   Daemon: AFP17004   SVC: 254   Node: 17004   System: Multi
Recovery
  Continuous Operation (Y/N).....: Y
Daemon latency/pulse services
  Shared memory area size (k).....: 1800_____   Minimum (k): 0_____
    Dataspace name (if used)..: #WRKSP1_
  Daemon memory area size (k).....: 0_____   Minimum (k): 0_____

Unified trace settings
  Trace size (k).....: 32   (no tracing = 0; maximum = 32)
  Use trace file (Y/N).....: N   Wraparound file when full (Y/N)..: N
  Note:   Activation must be performed manually in daemon/database 'tasks'.
  Note:   This same configuration is shared by any databases too.

Command ==>

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help           Exit           Upd                               Menu

```

Here you can modify latency/activity services:

- Whether to use shared memory, maximum and minimum sizes and whether to use a dataspace and unified trace settings for this daemon and (currently) the databases it knows about.
- Trace buffer size, whether to write to a trace file and whether to wraparound the trace file when it fills. Make any required changes and press PF5 to confirm them or PF3 to return to the daemon list.