

Adabas Online System

User's Guide

Version 8.6.1

September 2025

This document applies to Adabas Online System Version 8.6.1 and all subsequent releases.

Specifications contained herein are subject to change and these changes will be reported in subsequent release notes or new editions.

Copyright © 2025 Software GmbH, Darmstadt, Germany and/or its subsidiaries and/or its affiliates and/or their licensors.

The name Software AG and all Software GmbH product names are either trademarks or registered trademarks of Software GmbH and/or its subsidiaries and/or its affiliates and/or their licensors. Other company and product names mentioned herein may be trademarks of their respective owners.

Detailed information on trademarks and patents owned by Software GmbH and/or its subsidiaries is located at <https://softwareag.com/licenses>.

Use of this software is subject to adherence to Software GmbH's licensing conditions and terms. These terms are part of the product documentation, located at <https://softwareag.com/licenses> and/or in the root installation directory of the licensed product(s).

This software may include portions of third-party products. For third-party copyright notices, license terms, additional rights or restrictions, please refer to "License Texts, Copyright Notices and Disclaimers of Third-Party Products". For certain specific third-party license restrictions, please refer to section E of the Legal Notices available under "License Terms and Conditions for Use of Software GmbH Products / Copyright and Trademark Notices of Software GmbH Products". These documents are part of the product documentation, located at <https://softwareag.com/licenses> and/or in the root installation directory of the licensed product(s).

Use, reproduction, transfer, publication or disclosure is prohibited except as specifically provided for in your License Agreement with Software GmbH.

Document ID: AOS-USER-861-20250929

Table of Contents

Using Adabas Online System (AOS)	v
1 Conventions	1
2 About this Documentation	3
Document Conventions	4
Online Information and Support	4
Data Protection	5
3 Getting Started	7
Accessing AOS	8
The Main Menu	9
Adabas Online System Demo Version	13
4 Monitoring Adabas Sessions	23
Displaying Cluster Members	25
Maintaining User Profiles	28
Displaying or Modifying Parameters	33
Displaying Installed Products	44
Displaying the Event Log Buffer	45
Displaying Queues	47
Refreshing Interval Statistics	52
Obtaining Current Snapshot Statistics	53
Maintaining TCP/IP URLs	59
Monitoring Interval Utilization	60
Replicator Management	81
Displaying Session Utilization	81
Monitoring Cluster Usage	91
Displaying Maintenance Levels	99
5 Maintaining Checkpoints	101
Listing Checkpoints	102
Deleting Checkpoints	104
6 Maintaining Files	107
Defining or Modifying the FDT	109
Releasing a Descriptor	120
Deleting an Adabas File	122
Defining a New File	123
Logically Deleting or Undeleting a Descriptor	125
Modifying File Parameters	127
Reordering a File Online	131
Refreshing a File to Empty Status	133
Allocating or Deallocating File Space	134
Maintaining Expanded Files	135
7 Maintaining Databases	139
Adding a New Associator or Data Storage Extent	141
Increasing or Decreasing Associator or Data Storage Data Set Size	142
Displaying and Resetting DIB Block Entries	143

Recovering Unused Space	143
Uncoupling Adabas Files	143
8 Performing System Operator Command Functions	145
Allocating/Deallocating CLOG and PLOG Data Sets	147
Reactivating Command Logging	150
Extended Error Recovery Functions	150
Forcing Dual/Multiple CLOG/PLOG Switch	157
Locking / Unlocking Files	158
CLOG/PLOG Dataset Status	160
Resetting Online Dump Status	164
Stopping Users	164
Termination Commands	168
Managing Online Utilities	169
Maintaining the User Table	170
9 Reviewing the Database Report	173
Displaying Files with Critical Number of Extents	175
Displaying Field Definition Table (FDT)	175
Displaying Files	178
Displaying General Database Layout	185
Displaying Volume Serial Numbers for Database	187
Displaying ASSO/DATA/WORK Block (RABN)	188
Displaying Unused Storage	190
Displaying Used Storage	191
10 Calculating Space Requirements	193
Estimating Associator Space	195
Estimating Sizes for Directory and Data Structures in a Cluster Environment	197
Estimating Data Storage Space	201
Estimating Space for the DD/FILEA Sequential Data Set	202
Estimating Sort Data Set Space	203
Estimating TEMP Data Set Space	207
Estimating Work Data Set Space	211
11 Troubleshooting Options	213
Displaying Database Status Information	214
Displaying Active Targets	215
Forcing a Database Abend	216
Stopping a Utility	216
Index	217

Using Adabas Online System (AOS)

This document describes how to use the Basic Services of Adabas Online System (AOS), including each of its Basic Services menus and screens.

This document is provided for Adabas system administrators using the Adabas Online System to maintain their Adabas databases and files.

<i>Getting Started</i>	Describes how to access Adabas Online System, the main menu, and describes the Adabas Online System Demo version.
<i>Monitoring Adabas Sessions</i>	Describes how to use AOS to perform session monitoring functions, including how to display nucleus parameters, session statistics, buffer sizes for queues and areas, and maintenance levels.
<i>Maintaining Checkpoints</i>	Describes how to list and delete checkpoint information using AOS.
<i>Maintaining Files</i>	Describes how to perform file maintenance using AOS. File maintenance allows you to maintain Adabas fields and files, including allocating file space and changing file parameters. It also allows you to control ISN/storage block reuse.
<i>Maintaining Databases</i>	Describes how to use AOS to control Adabas database (ASSO/DATA) file and space allocation, DIB blocks, and to recover space unused by abended utilities.
<i>Performing System Operator Command Functions</i>	Describes how to use AOS to perform various system operator command functions.
<i>Reviewing the Database Report</i>	Describes how to use AOS to review the database report, corresponding to selected functions of the report produced by the ADAREP utility.
<i>Calculating Space Requirements</i>	Describes how to use AOS to calculate the space requirements for your Adabas database.
<i>Troubleshooting Options</i>	Describes how to locate and use AOS troubleshooting options for your Adabas database.

1 Conventions

Throughout this document, the terms "Adabas Online System" and "AOS" are used interchangeably.

A product version is identified by the first two digits of the versioning number. Software AG distinguishes between major and minor versions according to the amount of functionality or technology added to the product. All other digits indicate correction levels.

In the product documentation, the notations *vrs*, *vr*, or simply *v* are often used as placeholders for the current product version, for example, in data set or module names.

Placeholder	Meaning	Definition
<i>v</i>	version	Major Version The first digit of the product version number indicates major architecture and functionality implementation or enhancement that adds value to the product.
<i>r</i>	release	Minor Version The second digit of the version number indicates new or enhanced functionality that adds value to the product.
<i>s</i>	system maintenance level	Correction Level Correction levels contain error corrections only, without new functionality, including documentation of all modifications and repairs. In case it is necessary to include functional changes into a correction level, an exception handling process ensures that corresponding quality assurance activities are triggered. These functional changes are documented. The main goal is to avoid impacts when you install such a correction level. The third number of an Adabas version denotes the system maintenance level. On certain platforms supported by Adabas, additional levels may exist, such as update package, patch level, service pack and hot fix.

2 About this Documentation

- Document Conventions 4
- Online Information and Support 4
- Data Protection 5

Document Conventions

Convention	Description
Bold	Identifies elements on a screen.
Monospace font	Identifies service names and locations in the format <code>folder.subfolder.service</code> , APIs, Java classes, methods, properties.
<i>Italic</i>	Identifies: Variables for which you must supply values specific to your own situation or environment. New terms the first time they occur in the text. References to other documentation sources.
Monospace font	Identifies: Text you must type in. Messages displayed by the system. Program code.
{ }	Indicates a set of choices from which you must choose one. Type only the information inside the curly braces. Do not type the { } symbols.
	Separates two mutually exclusive choices in a syntax line. Type one of these choices. Do not type the symbol.
[]	Indicates one or more options. Type only the information inside the square brackets. Do not type the [] symbols.
...	Indicates that you can type multiple options of the same type. Type only the information. Do not type the ellipsis (...).

Online Information and Support

Product Documentation

You can find the product documentation on our documentation website at <https://documentation.softwareag.com>.

Product Training

You can find helpful product training material on our Learning Portal at <https://learn.software-ag.com>.

Tech Community

You can collaborate with Software GmbH experts on our Tech Community website at <https://tech-community.softwareag.com>. From here you can, for example:

- Browse through our vast knowledge base.
- Ask questions and find answers in our discussion forums.
- Get the latest Software GmbH news and announcements.
- Explore our communities.
- Go to our public GitHub and Docker repositories at <https://github.com/softwareag> and <https://hub.docker.com/publishers/softwareag> and discover additional Software GmbH resources.

Product Support

Support for Software GmbH products is provided to licensed customers via our Empower Portal at <https://empower.softwareag.com>. Many services on this portal require that you have an account. If you do not yet have one, you can request it at <https://empower.softwareag.com/register>. Once you have an account, you can, for example:

- Download products, updates and fixes.
- Search the Knowledge Center for technical information and tips.
- Subscribe to early warnings and critical alerts.
- Open and update support incidents.
- Add product feature requests.

Data Protection

Software AG products provide functionality with respect to processing of personal data according to the EU General Data Protection Regulation (GDPR). Where applicable, appropriate steps are documented in the respective administration documentation.

3 Getting Started

- Accessing AOS 8
- The Main Menu 9
- Adabas Online System Demo Version 13

This chapter introduces the AOS screen system and usage conventions.

Accessing AOS

➤ **To access the Adabas Online System (AOS) screens:**

- 1 In ISPF, invoke a Natural session.
- 2 On the command line of the Natural session **Main Menu**, enter:

```
LOGON SYSAOS
```

You are connected to Adabas Online System.

- 3 On the command line of the Natural session **Main Menu**, enter:

```
MENU
```

The Adabas Online System **Main Menu** appears.

```
14:02:28          ***** A D A B A S  BASIC  SERVICES *****          2014-04-30
Cluster          -  Main Menu  -          PMAIN02

          Code  Basic Services          Code  Other Services
-----  -
          A    Session monitoring        1    Adabas Cache Facility
          C    Checkpoint maintenance    2    Delta Save Facility
          F    File maintenance          3    Trigger Maintenance
          M    Database maintenance      4    AOS Security
          O    Session opercoms          5    Transaction Manager
          R    Database report            6    Adabas Statistics
          S    Space calculation          7    Vista
          ?    Help                       8    Fastpath
          .    Exit                       9    SAF Security
-----  -

Code ..... _
Database ... 1955      (WIS1955)

Command ==>
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit
```

The Main Menu

From the main menu, you can access Basic Services or any Other Service that is installed on your system. Such services are highlighted on the menu.

```

13:09:58          ***** A D A B A S  BASIC  SERVICES *****          2014-04-30
Cluster          -  Main Menu  -          PMAIN02

                Code  Basic Services                Code  Other Services
                ----  - - - - -                    ----  - - - - -
                A    Session monitoring              1    Adabas Cache Facility
                C    Checkpoint maintenance          2    Delta Save Facility
                F    File maintenance                3    Trigger Maintenance
                M    Database maintenance            4    AOS Security
                O    Session opercoms                5    Transaction Manager
                R    Database report                  6    Adabas Statistics
                S    Space calculation                7    Vista
                ?    Help                             8    Fastpath
                .    Exit                             9    SAF Security
                ----  - - - - -                    ----  - - - - -

Code ..... _
Database ... 1955   (WIS1955)

Command ==>
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit

```

The Adabas Online System Main Menu allows you to perform DBA tasks within Basic Services, selectable by menu option:

Option	Task	Read
A	Session monitoring functions display nucleus parameters, session statistics, buffer sizes for queues and areas, and maintenance levels	Monitoring Adabas Sessions
C	Checkpoint maintenance lists and deletes checkpoint information.	Maintaining Checkpoints
F	File maintenance controls Adabas fields (increase or add a field, release a descriptor) and files (define a new file; delete a file; refresh, rename, or renumber a file; allocate file space; change file parameters). It also controls ISN / storage block reuse.	Maintaining Files
M	Database maintenance controls Adabas database (ASSO/DATA) file and space allocation, DIB blocks, and lets you recover space unused by ABENDED utilities.	Maintaining Databases
O	Session opercoms control extended error recovery, lock/unlock of files, stop user(s), session termination, and management of online utilities	Performing System Operator Command Functions

Option	Task	Read
R	Database report displays tables of "critical" extents, a file's FDT, general and specific file information, VOLSER, and general database information.	Reviewing the Database Report
S	Space calculation provides an aid to calculating database ASSO, DATA, sort, temp, and WORK space.	Calculating Space Requirements

This section provides more details about using the Main Menu and some general information about AOS screens:

- [Specifying the Basic Services Database](#)
- [Using Program Function \(PF\) Keys](#)
- [Invoking Basic Services Functions](#)
- [Getting Help](#)
- [Basic Services Messages](#)

Specifying the Basic Services Database

The database on which Basic Services is installed becomes the default database for Basic Services functions. However, you can specify the database of any active Adabas nucleus session. Subsequent Basic Services functions refer to that database until you specify another database or exit Basic Services.

If you specify a database that is also an Event Replicator Server, the main menu identifies the database as an Event Replicator Server by displaying "Replicator" in the upper left corner of the screen, as shown below. This is the only screen on which this identification explicitly occurs, but the Basic Services functions available and the information displayed for Event Replicator Server databases vary slightly from those provided regular Adabas databases.

```

13:09:58          ***** A D A B A S BASIC SERVICES *****          2014-04-30
Cluster          - Main Menu -          PMAIN02

          Code  Basic Services          Code  Other Services
          ----  - - - - -          ----  - - - - -
          A    Session monitoring          1    Adabas Cache Facility
          C    Checkpoint maintenance      2    Delta Save Facility
          F    File maintenance            3    Trigger Maintenance
          M    Database maintenance         4    AOS Security
          O    Session opercoms             5    Transaction Manager
          R    Database report              6    Adabas Statistics
          S    Space calculation            7    Vista
          ?    Help                        8    Fastpath
          .    Exit                        9    SAF Security
          ----  - - - - -          ----  - - - - -

Code ..... _
Database ... 1955      (WIS1955)

Command ==>
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit

```

Using Program Function (PF) Keys

Available PF keys and their functions are listed at the bottom of each Basic Services screen. The following program function (PF) keys may appear on Basic Services screens:

Function Key	Description
PF1	Get help
PF3	Exit to previous screen
PF7	Page backward through a series of screens.
PF8	Page forward through a series of screens.
PF12	Return to the Adabas Online System main menu

Invoking Basic Services Functions

You can invoke AOS Basic Service functions by selecting a menu option or, for most functions, by entering a command directly on the command line.

- [Selecting a Menu Option](#)

- [Entering Commands Directly](#)

Selecting a Menu Option

➤ **To invoke function using a menu option:**

- Enter the option code in the `Code` field.

Selecting a Main Menu function displays a menu of choices for that function.

Entering Commands Directly

Most Basic Services functions can be invoked using direct commands from the command line. The only exceptions are Adabas Online System security functions.

Each direct command corresponds to a function on a Basic Services menu. You can issue a direct command for a function on a different menu from the one currently displayed. You do not have to leave the current menu to perform a function that is not displayed.

More information about the direct commands is included in the *Basic Services Direct Commands*, where the direct command equivalent to each menu function is described.

Getting Help

Two direct commands that can be issued from any Basic Services menu are `?` and `help`.

- The `?` option (you can also use `PF1`; see the section [Program Functions Keys](#)) displays a brief comment about the current menu.
- `help` provides concise information about the individual Basic Services functions.

Basic Services Messages

Basic Services issues a message confirming each completed function. If an error occurs, a message appears containing a reference number and describing the error.

Before analyzing an error:

1. Try reviewing the Help information (option `?` or `PF1`) for the last step you performed to see if any requirements were overlooked.
2. Retry the operation.

Response code 22 is returned if the Adabas session is terminated and restarted while Basic Services is active. In this case, AOS should be stopped and restarted.

Adabas Online System Demo Version

The Adabas Online System (AOS) Demo version is a version of AOS with limited functionality, as described in this section. The items on each AOS menu that are not provided with the AOS Demo version have asterisks for their menu option codes. In general, you are only allowed to view information in the Demo version; to maintain parameters and settings, you must have the full version of AOS installed.

For example, on the following screen, the **Main Menu. Space calculation** as well as **Trigger Maintenance** options are not available.

```

12:59:18          ***** A D A B A S  BASIC  SERVICES *****          2014-04-30
Cluster          -  Main Menu  -          PMAIN02

          Code  Basic Services          Code  Other Services
          ----  -
          A    Session monitoring       1    Adabas Cache Facility
          C    Checkpoint maintenance   2    Delta Save Facility
          F    File maintenance         *    Trigger Maintenance
          M    Database maintenance     4    AOS Security
          O    Session opercoms         5    Transaction Manager
          R    Database report           6    Adabas Statistics
          *    Space calculation         7    Vista
          ?    Help                     8    Fastpath
          .    Exit                     9    SAF Security
          ----  -

Code ..... _
Database ... 1955   (WIS1955)

Command ==>
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit

```

The rest of this section describes which AOS options are available in the Demo version and which are not.

Selecting **A** from the **Main Menu** displays the **Session Monitoring** menu. You can only select **Display parameters**, **Display installed products**, **Display queues**, **Display interval utilization**, and **Display maintenance levels** on this menu.

```

13:00:14          ***** A D A B A S BASIC SERVICES *****          2014-04-30
                   - Session Monitoring -                               PAC0012

Code  Service                                         Code  Service
-----
*    Display cluster members                         *    Current snapshot statistics
*    Maintain user profiles                          *    Maintain TCP/IP URL
D    Display parameters                               U    Display interval utilization
I    Display installed products                      *    Replicator Management
*    Display event log buffer                       *    Display session utilization
*    Modify parameters                               *    Cluster usage
Q    Display queues                                  Z    Display maintenance levels
*    Refresh interval statistics
?    Help
-----
Code ..... _
Database ID .. 1955      (WIS1955)                NucID .. 1021

Command ==>
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help      NextNuc  Exit                               Menu          ↵
    
```

Selecting **Q** on the **Session Monitoring** menu causes the **Queue Displays** menu to appear. You can only select **Display Hold Queue** on the **Queue Displays** menu.

```

13:12:58          ***** A D A B A S BASIC SERVICES *****          2014-04-30
                   - Queue Displays -                               PACQ002

Code  Service
-----
*    Display User Queue Elements
*    Display Command Queue
H    Display Hold Queue
?    Help
.    Exit
-----

Code ..... _
Max No. Elements ... 100
Last Activity ..... 0      (elapsed time in seconds)
Selection Criteria
  ET-ID (User-ID) .. _____ User Type ... ____
  Job Name ..... _____
  Terminal ID ..... _____
Database ID ..... 1955      (WIS1955)                NucID .. 1021

Command ==>
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help      Exit      Clear UID                               Menu          ↵
    
```



Note: The **ETI-ID (User-ID)** field on this screen can be used to select a specific ETID or security user ID (SECUID), as appropriate for your site.

Selecting **U** on the **Session Monitoring** menu causes the **Interval Utilization** menu to appear. You can only select **System status** and **Thread usage** on the **Interval Utilization** menu.

```

13:14:17          ***** A D A B A S  BASIC  SERVICES *****          2014-04-30
                    - Interval Utilization -                          PACU002

Code  Service                Code  Service
-----
*    Command usage          S    System status
*    File usage             T    Thread usage
*    High watermarks (pools/queues)
*    Workpool (LWP) usage   *    I/Os by Volser
*    Nucleus File Status   *    WORK status
*    PLOG status           *    Display PPT
?    Help
.    Exit
-----

Code ..... _
File Number .. 0
Database ID .. 1955   (WIS1955)           NucID .. 1021

Command ==>
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help      NextNuc   Exit                               Menu      ←

```

Selecting **C** on the **Main Menu** causes the **Checkpoint Maintenance** menu to appear. You can only select **List checkpoints** on the **Checkpoint Maintenance** menu.

```

13:15:43          ***** A D A B A S  BASIC  SERVICES *****          2014-04-30
                  -  Checkpoint Maintenance  -                          PCP0002

                                Code   Service
                                ----   -
                                C     List checkpoints
                                *     Delete checkpoints
                                ?     Help
                                .     Exit
                                ----   -

Code ..... _
Date(YYYY-MM-DD) . 0000-00-00
Ext. CP-list ..... N
Checkpoint Name .. ALL
Database ID ..... 1955   (WIS1955)

Command ==>
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help                Exit                                Menu                ↵
    
```

Selecting **F** on the **Main Menu** causes the **File Maintenance** menu to appear. You can only select **Define/modify FDT** on the **File Maintenance** menu.

```

13:16:33          ***** A D A B A S  BASIC  SERVICES *****          2014-04-30
                  -  File Maintenance  -                              PFL0004

Code  Service                                Code  Service
-----
C     Define/modify FDT                       *     Modify file parameters
*     Release descriptor                       *     Reorder file online
*     Delete existing file                     *     Refresh file to empty status
*     Define new file                           *     Allocate/deallocate file space
*     Logically delete/undel descriptor        *     Maintain expanded files
?     Help                                     .     Exit
-----

Code ..... _
File No ..... 0      Descriptor Name .. __
Database ID .. 1955   (WIS1955)

Command ==>
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help                Exit                                Menu                ↵
    
```

Selecting **C** on the **File Maintenance Menu** causes the **FDT/SDT Definition / Modification** menu to appear. You can only select **Define new FDT** on the **FDT/SDT Definition / Modification** menu.

```

13:17:59          ***** A D A B A S  BASIC  SERVICES *****          2014-04-30
          - FDT/SDT Definition / Modification -          PFLC004

Code  Service                Code  Service
-----
*    Add new field(s)        *    Online invert
*    Change field parameters *    Define/add SDT
D    Define new FDT          *    Release UQ from descriptor
*    Delete field from FDT   ?    Help
*    Undelete field from FDT .    Exit
-----

Code ..... _
File No. ....
Field Name ... _
File Password.
Database ID .. 1955  (WIS1955)

Command ==>
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help      Def. File Exit                               Menu      ←

```

Selecting **M** on the **Main Menu** causes the **Database Maintenance** menu to appear. In the Demo version, this menu only shows the options available when there is a licensed product installed; no options are available in Demo mode.

```

13:19:36          ***** A D A B A S  BASIC  SERVICES *****          2014-04-30
                  - Database Maintenance -                             PDM0002

                Code      Service
                -----
                *          Add new dataset to ASSO/DATA
                *          Increase/decrease ASSO/DATA
                *          List/reset DIB block entries
                *          Recover unused space
                *          Uncouple two ADABAS files
                ?          Help
                .          Exit
                -----

Code ..... _
File No. .... 0
Coupled File .. 0
Database ID ... 1955   (WIS1955)

Command ==>
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit                                     Menu          ↵
    
```

Selecting **O** on the **Main Menu** causes the **Session Opercoms** menu to appear. You can only select **Extended Error Recovery, Lock or unlock files, Stop user(s)** and **Termination Commands** on the **Session Opercoms** menu.

```

13:26:33          ***** A D A B A S  BASIC  SERVICES *****          2014-04-30
                  - Session Opercoms -                               PACI002

Code  Service                Code  Service
-----
*     Allocate/Deallocate CLOG/PLOG      S     Stop user(s)
*     Issue reactivate CLOG command      T     Termination Commands
E     Extended Error Recovery            *     Manage Online Utilities
*     Force CLOG or PLOG switch          *     User Table Maintenance
L     Lock or unlock files               *     Replicator Management
*     Reset ONLINE-DUMP-Status          *     Cluster operator commands
.     Exit                               ?     Help
-----

Code ..... _
Userid(ETID) ... _____
CLOG/PLOG Ind .. _      Global.. _
Database ID .... 1955   (WIS1955)          NucID .. 1021

Command ==>
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit                                     Menu          ↵
    
```

Selecting **E** on the **Session Opercoms** causes the **Extended Error Recovery** menu to appear. You can only select **Add/Delete PIN modules** and **Display/modify PIN routines** on the **Extended Error Recovery** menu.

```

13:27:46          ***** A D A B A S  BASIC  SERVICES *****          2014-04-30
                                     -  Extended Error Recovery  -          PACIE02

      Code      Service
      ----      -
      *          Display message buffer
      *          Display/modify environment
      *          Display/modify Exit routines
      M          Add/Delete PIN modules
      P          Display/modify PIN routines
      *          Refresh threshold and alert exits
      *          SNAP a nucleus dump
      ?          Help
      .          Exit
      ----      -

Code ..... _
Start Address .. _____ End Address ... _____
Database ID .... 1955      (WIS1955)          NUCID .. 1021

Command ==>
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit          Menu          ↵

```

Selecting **L** on the **Session Opercoms** causes the **Lock/Unlock Files** menu to appear. You can only select **Display locked files** on the **Lock/Unlock Files** menu.

```

13:28:34          ***** A D A B A S  BASIC  SERVICES *****          2014-04-30
                  - Lock / Unlock Files -                               PACIL02

Code   Service
-----
D      Display locked files
*      Lock file for all users
*      Advance lock file
*      Lock file except for UTI/EXF users
*      Unlock file from general lock
*      Release an advance lock
*      Unlock file from UTI/EXF lock
?      Help
.      Exit
-----

Code ..... _
File Number ..
UTI/EXF Ind .. U
Database ID .. 1955   (WIS1955)

Command ==>
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help       Exit                               Menu       ↵
    
```

Selecting **S** on the **Session Opercoms** causes the **Stop Users** menu to appear. In the Demo version, this menu only shows the options available when there is a licensed product installed; no options are available in Demo mode.

```

13:59:40          ***** A D A B A S  BASIC  SERVICES *****          2014-04-30
                  - Stop Users -                                       PACIS02

Code   Service
-----
*      Stop users using file
*      Stop inactive users
*      Stop users by jobname
*      Stop a selected user
?      Help
.      Exit
-----

Code ..... _
File Number ..... _____
Last Activity .... _____ (elapsed time in seconds)
Job Name ..... _____
Purge UQE(s) ..... N
Selected Userid ..
Database ID ..... 1955   (WIS1955)          NUCID .. 1021

Command ==>
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help       Disp UQ   Exit       Clear UID                               Menu       ↵
    
```

Selecting **T** on the **Session Opercoms** causes the **Session Termination** menu to appear. You can only select **Normal session termination** on the **Session Termination** menu.

```

14:00:25          ***** A D A B A S  BASIC  SERVICES *****          2014-04-30
                                     - Session Termination -          PACT002

          Code      Service
          ----      -
          A         Normal session termination (ADAEND)
          *         Cancel session immediately (CANCEL)
          *         Stop session                      (HALT)
          ?         Help
          .         Exit
          ----      -

Code ..... _
Database ID .. 1955  (WIS1955)                      NUCID .. 1021
                                           Global.. _

Current nr. of users in User Queue ... 1
Nr. of users with open transactions .. 0
Nr. of active nucs in Plex cluster ... 1

Command ==>
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help                Exit                                Menu                ↵

```

Selecting **R** from the **Main Menu** displays the **Database Report** menu. You can only select **Display file(s)** and **General database layout** on this menu.

```
14:01:13          ***** A D A B A S  BASIC  SERVICES *****          2014-04-30
                  - Database Report -                               PDR0002

Code      Service
-----
*         List files with crit. no. of extents
*         Display field description table (FDT)
F         Display file(s)
G         General database layout
*         List VOLSER distribution of database
*         Display ASSO/DATA block (RABN)
*         Display unused storage
*         Display used storage (DSPACE)
?         Help
.         Exit
-----

Code ..... _
File No ..... 0_____ Password ..
Database ID .. 1955 (WIS1955)          VOLSER .. _____

Command ==>
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit          Menu          ↵
```



Note: Option F will display system files only.

4 Monitoring Adabas Sessions

▪ Displaying Cluster Members	25
▪ Maintaining User Profiles	28
▪ Displaying or Modifying Parameters	33
▪ Displaying Installed Products	44
▪ Displaying the Event Log Buffer	45
▪ Displaying Queues	47
▪ Refreshing Interval Statistics	52
▪ Obtaining Current Snapshot Statistics	53
▪ Maintaining TCP/IP URLs	59
▪ Monitoring Interval Utilization	60
▪ Replicator Management	81
▪ Displaying Session Utilization	81
▪ Monitoring Cluster Usage	91
▪ Displaying Maintenance Levels	99

The Adabas session monitoring functions allow you to control and manage major Adabas resources. These functions are most useful when analyzing system performance or seeking the cause of performance problems. Session monitoring functions can be accessed from the **Session Monitoring** menu:

```

15:19:52          ***** A D A B A S  BASIC  SERVICES *****          2014-06-30
                   -  Session Monitoring  -                               PAC0012

Code   Service
-----
A      Display cluster members
C      Maintain user profiles
D      Display parameters
I      Display installed products
L      Display event log buffer
P      Modify parameters
Q      Display queues
R      Refresh interval statistics
?      Help
-----
Code   Service
-----
S      Current snapshot statistics
T      Maintain TCP/IP URL
U      Display interval utilization
V      Replicator Management
W      Display session utilization
X      Cluster usage
Z      Display maintenance levels
.      Exit
-----

Code ..... _
Database ID .. 1955      (WIS1955)
NucID .. 1021

MENU04 : 'Session Utilization'  function interrupted
Command ==>
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help      NextNuc  Exit

```

 **Note:** In cluster environments, the PF2 key allows you to scroll sequentially through nucleus IDs in the cluster using the NextNucid command. In addition, the current nucleus ID is shown in a NucID field on this screen. When the highest nucleus in a cluster is reached, PF2 causes AOS to cycle back to the beginning and changes the nucleus ID to the lowest nucleus ID in the cluster. Once the nucleus ID is changed, it remains in use for all Adabas Online System screens until it is changed again.

Using the session monitoring environment you can monitor the Adabas nuclei in a multiprocessing environment. When you enter the DBID of a cluster database on the **Session Monitoring** menu, subsequent screens include a field to specify the ID of the nucleus (NUCID) in the cluster you want to monitor:

- If you do not set the nucleus ID, AOS defaults to the local nucleus.
- If you set the nucleus ID to zero for a cluster database, the selected function is performed for *all* active nuclei in the cluster.

Using the AOS session monitoring environment, you can perform the following functions, accessible by menu option:

Option	Function
A	<i>Displaying Cluster Members</i>
C	<i>Maintaining User Profiles</i>
D / P	<i>Displaying or Modifying Parameters</i>
I	<i>Displaying Installed Products</i>
L	<i>Displaying the Event Log Buffer</i>
Q	<i>Displaying Queues</i>
R	<i>Refreshing Interval Statistics</i>
S	<i>Obtaining Current Snapshot Statistics</i>
T	<i>Maintaining TCP/IP URLs</i>
U	<i>Monitoring Interval Utilization</i>
V	<i>Replicator Management</i>
W	<i>Displaying Session Utilization</i>
X	<i>Monitoring Cluster Usage</i>
Z	<i>Displaying Maintenance Levels</i>

Displaying Cluster Members

Selecting option **A** from the **Session Monitoring** menu to display cluster members produces the following screen:

```

21:23:16          ***** A D A B A S  BASIC  SERVICES *****          2014-05-01
DBID 1955          - Display Cluster Members -          PACA002

Total number of active(WORK not empty) nuclei in the cluster ... 5

I Sel I NucID | Image ID I Jobname I Status I Available Plex Services I
-----|-----|-----|-----|-----|-----|-----|-----|
I  _  I  1    I DAEMVS I ADANUC01 I Active I All I
I  _  I  2    I DAEMVS I ADANUC02 I Inactive I List,Cache I
I  _  I  3    I DDZMVS I ADANUC03 I Active I All I
I  _  I  4    I DDZMVS I ADANUC04 I Active I All I
I  _  I 1021  | ZHST    | USAXXXRP | Active  | All I
I      I      |      |      |      |      |      I
I      I      |      |      |      |      |      I
I      I      |      |      |      |      |      I
I      I      |      |      |      |      |      I
I      I      |      |      |      |      |      I
I      I      |      |      |      |      |      I
I      I      |      |      |      |      |      I

Command ==>
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help      PPT      Exit      Refresh  --      -      +      Menu      ↵
    
```

The screen displays a list of nuclei participating in the cluster and information about the current status of each nucleus.

➤ **To select a nucleus for additional processing:**

- Enter "S" in the Sel column opposite that nucleus.

➤ **To display additional information about a nucleus:**

- Enter "D" in the Sel column opposite that nucleus.

For an Adabas cluster nucleus that has a nonzero nucleus ID, its entry in the parallel participant table (PPT) is displayed in a screen similar to the following:

```
21:23:16          ***** A D A B A S  BASIC  SERVICES *****          2014-05-01
DBID 1955          - Display PPT Entry -          MACA012

NucID ... 1021    Active Nucleus, PLOG(s) not copied, CLOG(s) not copied

Name      Dataset Status          DataSet Name
-----
WORK1
PLOGR1
PLOGR2
CLOGR1
CLOGR2
RD.USAXXX.DB1955.WORKR1
RD.USAXXX.DB1955.PLOGR1
RD.USAXXX.DB1955.PLOGR2
RD.USAXXX.DB1955.CLOGR1
RD.USAXXX.DB1955.CLOGR2

Press 'ENTER', PF3 or PF12 to continue
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit          Menu          ↵
↵
```

➤ **To display the PPT for this DBID:**

- Press PF2. The Display PPT screen appears.

```

16:42:08          ***** A D A B A S  BASIC  SERVICES *****          2014-05-05
DBID 1955          - Display PPT -          MACA022

NucID .. 1021      Active Nucleus, PLOG(s) not copied, CLOG(s) not copied
Image .. ZHST      All Sysplex Services Active

          Label Name          Dataset Name
          -----          -
          WORK1              RD.USAWIS.DB1955.WORKR1
          PLOGR1             RD.USAWIS.DB1955.PLOGR1
          PLOGR2             RD.USAWIS.DB1955.PLOGR2
          CLOGR1             RD.USAWIS.DB1955.CLOGR1
          CLOGR2             RD.USAWIS.DB1955.CLOGR2

PF1----- PF3----- PF4----- PF6----- PF7----- PF8----- PF9----- PF12-----
Help      Exit      Refresh      PrevPPT          NextPPT      Menu      ↵
    
```

Maintaining User Profiles

Adabas allows you to retain user-related information from session to session in a user profile table that includes

- ET records;
- user priority;
- user-specific timeout (TNxx, TT, and TLSCMD);
- ISN buffering (NSISN, NSISNHQ);
- command ID (NQCID) values that differ from the established ADARUN values; and
- owner ID information for multicient files.

Selecting `Maintain user profiles` (option **C**) on the **Session Monitoring** menu displays the following **Maintain User Profiles** menu:

```

15:46:52          ***** A D A B A S  BASIC  SERVICES *****          2014-05-01
                   -  Maintain User Profiles  -                          PACIC02

                   Code      Service
                   ----      -
                   L        List/modify user profile(s)
                   M        Mass function
                   X        Delete ETID-ranges
                   ?        Help
                   .        Exit
                   ----      -

Code ..... _
Start UID .... _____
Database ID .. 1957   (WIS1957)

Command ==>
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help                Exit                               Menu                ↵

```

From the **Maintain User Profiles** menu, you can:

- list and modify a user profile table (option **L**);
- copy a user profile to one or more other users (option **M**); and
- remove one or more ETIDs from the Adabas checkpoint file thereby deleting both profile and ET data (option **X**).

If necessary, you can supply a starting user ID. If the `Start UID` field is left empty, Basic Services displays entries starting from the beginning of the user profile table. You can use range notation for the starting value. For example, if you enter `JA*` in the `Start UID` field, the display begins with user IDs that start with the letters "JA".

If necessary, you can change the database by specifying the database ID in the `Database ID` field..

➤ To list and modify the user profile table

- Enter **L** in the `Code` field.

The List/Modify User Profiles screen displays the user profile table:


```

15:48:06          ***** A D A B A S  BASIC  SERVICES *****          2014-05-01
DBID 1957          -  Maintain User Profiles  -          PACICM2

Set the user profiles of the userids entered below to the same as
userid .. USER1____

Userid   Userid   Userid   Userid   Userid   Userid   Userid
-----  -----  -----  -----  -----  -----  -----
XYZ1     XYZ2

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help                Exit                                Menu

```

On the resulting screen, you can type in the user ID of the profile to be copied, and the names of the users whose profiles are to be taken from that user ID.

In the example, users XYZ1 and XYZ2 inherit all values from user USER1 and effectively define a group.

» To delete a range of user IDs

- 1 Enter **X** in the Code field.
- 2 Specify a complete or partial user ID or an asterisk (all user IDs) in the Start UID field.

A window opens asking whether you want to delete all user IDs or select the user IDs to be deleted:

```

15:49:04          ***** A D A B A S BASIC SERVICES *****          2014-05-01
                   - Maintain User Profiles -                          PACIC02

Code      Service
-----
L      List/modify user profile(s)
M      Mass function
X      Delete ETID-ranges
?      Help
.      Exit
-----
Code .....x
Start UID .... ba*
Database ID .. 105      (RD-105)

+-----+
| 'Y' - Select ETIDs for |
|   Deletion             |
| 'N' - Delete ETIDs with NO |
|   Selection            |
| Y <==== Select Option |
| PF1=Help   PF3=Exit   |
+-----+

Command ==>
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help              Exit              Menu
  
```

 **Caution:** Be careful about answering N (No) to the prompt. You could inadvertently delete IDs that you want to keep.

- 3 If you enter N (No) in the window's Select Option field, Basic Services deletes all user IDs in the specified range without any confirmation.

If you answer Y (Yes, the default), the Mass Delete of ET-IDs screen is displayed so that specific user IDs may be marked for retention:

```

15:50:26          ***** A D A B A S BASIC SERVICES *****          2014-05-01
DBID 1955          - Mass Delete of ET-IDs -                          PACICD2

Delete all ET-IDs starting with Userid = BA*
All entries marked 'K' (Keep) will N O T be deleted.

Userid      Userid      Userid      Userid      Userid      Userid      Userid
-----
BABRAB      BABRAN      BACANT      BADBEE      BADFUE      BADKED      BADKHK
BADNTU      BADTCS      BADWAT      BAFCKA      BAFJVS      BAGDTS      BAGJAR
BAGJKI      BAGJVN      BAGKIT      BAGLAW      BAGNET      BAGPCT      BAGPCP
BAGPCR      BAGPST      BAGSIR      BAGSWI      BAGTUF      BAGTON      BAGZAP
BAHNAK      BAJLOB      BAJPJS      BAKLIM      BAKSAT      BAMCID      BAMLIP
BAML0T      BAMPCS      BAPEHN      BAPLAB      BARHEN      BARHER      BASHEP
BASMOR      BASWAN      BASWIG
  
```

As indicated in the message on the screen, you need to mark with "k" those user IDs that you want to *keep*. Unmarked user IDs will be deleted when you press `ENTER`.



Note: When a user ID is deleted, both the user profile and any ET data for the user are deleted.

You can leave the screen without deleting any user IDs by using the `EXIT` key `PF3`.

Displaying or Modifying Parameters

➤ To view Adabas nucleus (ADARUN) parameters:

- Select option **D** on the **Session Monitoring** menu and press `Enter`.

The equivalent direct command is

```
DISPLAY PARAMETERS
```

A series of Display Parameters screens appear. You can scroll through the screens using the `PF7` (scroll backward) and `PF8` (scroll forward) keys. The information on these screens and the number of screens that appear varies depending on the type database you have selected.

ADARUN Parameter Reference, in the *Adabas Online Systems (AOS) Reference Guide*

The following screens might display for an Adabas database in an Adabas cluster:

Monitoring Adabas Sessions

```

19:15:21          ***** A D A B A S BASIC SERVICES *****          2017-09-25
DBID 1955          - Display Parameters -          PACPD32
NucID 1021

----- Pools -----
Sort Area          (LS).. 19968
Int. User Buffer   (LU).. 400000
Buffer Pool       (LBP).. 283392
Format Pool       (LFP).. 150000
ISN List Table    (LI).. 360000
Seq. Cmd. Table   (LQ).. 20000
Work Pool         (LWP).. 1500000
Attached Buffer    (NAB).. 100
Security Pool     (LCP).. 10000
UQ-DE Pool       (LDEUQP).. 50000
Err. Recovery (MSGBUF).. 36

----- Queues -----
Command Queue     (NC) .. 20
Hold Queue        (NH) .. 1200
User Queue        (NU) .. 200

----- Time Windows -----
Transaction Time  (TT) .. 4858
Max Transaction Time (MXTT) .. 3600
Nonactivity ACC-User (TNA) .. 4858
Nonactivity ET-User (TNAE) .. 4858
Nonactivity EXU-User (TNAX) .. 4858
Max Nonactivity Time(MXTNA) .. 3600
Time Limit Sx-Cmds (TLSCMD) .. 300
Max Time for Sx-Cmds(MXTSX) .. 3600
Command Time      (CT) .. 3858
SYNS60 Interval  (INTNAS) .. 3600

Page 1 of 7
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help      NextNuc   Exit      ABC List  Modify    +          Menu

```

```

15:28:41          ***** A D A B A S BASIC SERVICES *****          2018-04-04
DBID 1955          - Display Parameters -          PACPD22
NucID 1021

----- Miscellaneous -----
Read only         (READONLY).. NO
UTI only          (UTIONLY).. NO
OPEN required     (OPENRQ).. NO
Ignore DIB Entry (IGNDIB).. NO
Local nucleus     (LOCAL) .. NO
Number of Threads (NT) .. 25
Non DE Search     (NONDES) .. YES
Log AOS/DBS Upd. (AOSLOG).. NO
Batch Support     (BATCH) .. NO
Data Protection Area(LP).. 1000
Ignore Wrk Prt4 (IGNDTP) .. NO
WORK-Part-4 Area (LDTP) .. 0
WORK-Part-2 Area (LWKP2) .. 160
SVC               (SVC) .. 249

----- Miscellaneous -----
LARGEPAGE ..... NO
V64BIT ..... NO
SRLOG ..... Upd
LOGWARN ..... 0
SECUID ..... ALLOW
INDEXCROSSCHECK ..... YES
Print on refresh(REFSTPRT).. YES
Number plog buffers ..... 1
Number work1 buffers ..... 1
Event log buffer size ..... 1024
Auto-restart buffers (ARN).. 9
zIIP processors (ZIIP) .... YES

Page 2 of 7
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help      NextNuc   Exit      ABC List  Modify    -          +          Menu      ←

```

```

19:15:21          ***** A D A B A S BASIC SERVICES *****          2017-09-25
DBID 1955          - Display Parameters -          PACPD32
NucID 1021

----- Space Warning -----
ASSOSPACEWARN ..... 0
DATASPACEWARN ..... 0

----- Auto Increase -----
AUTOINCASSOTHRESHOLD ..... 0          AUTOINCDATATHRESHOLD ..... 0
AUTOINCASSOSIZE ... 0          CYL          AUTOINCDATASIZE ... 0          CYL
AUTOINCASSOTOTAL .. 0          CYL          AUTOINCDATATOTAL .. 0          CYL

----- SMF -----
SMF ..... NO

Page 3 of 7
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help      NextNuc   Exit      ABC List  Modify   -         +         Menu

```

```

19:15:21          ***** A D A B A S BASIC SERVICES *****          2017-09-25
DBID 1955          - Display Parameters -          PACPD32
NucID 1021

---- Command Logging ----          ----- Command Logging -----
Command Logging .. YES          Log VOLSER info (LOGVOLIO) .. NO
LOGCB ..... NO          Max buffer size/cmd (CLOGMAX) .. 16384
LOGFB ..... YES          Max buffer size/buf(CLOGBMAX) .. 4096
LOGRB ..... YES          Log ABDX (LOGABDX) .. NO
LOGSB ..... NO          Log multifetch buffer (LOGMB) .. NO
LOGVB ..... NO          Command log layout(CLOGLAYOUT).. 8
LOGIB ..... NO
LOGIO ..... NO
LOGUX ..... NO
LOGSIZE ..... 5064          ----- Protection Logging -----
DUAL CLOG Size ... 675          PLOG required (PLOGRQ) .. YES
DUAL CLOG Dev. ... 3390          DUAL PLOG Size (DUALPLS) .. 240
NCLOG ..... 0          DUAL PLOG Device (DUALPLD) .. 3390
NPLOG ..... 0

Page 4 of 7
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help      NextNuc   Exit      ABC List  Modify   -         +         Menu

```

Monitoring Adabas Sessions

```

19:15:21          ***** A D A B A S BASIC SERVICES *****          2017-09-25
DBID 1955          - Display Parameters -          PACPD32
NucID 1021

----- Large Pools -----
Flush I/O Pool (LFIOP) .. 80000

----- User Specific Limits -----
Hold Queue Limit (NISNHQ) .. 400
CIDs per User      (NQCID) .. 40
ISN per TBI Element(NSISN) .. 100

----- Buffer Pool -----
Bufferflush Dur. (TFLUSH) .. 1
Parallel LFIOP I/O (FMXIO) .. 1
Async. by Vol-Ser (ASYTVS) .. YES

----- Other Services -----
Triggers / Procedures (SPT) .. YES
Delta Save Facility (DSF) .. YES
Cache Facility (CACHE) .. NO
Transaction Manager (ATM) .. NO
TCP/IP Support (TCPIP) .. NO
Ext. Error Recovery (SMGT) .. YES
2 Phase Commit Support(DTP) .. NO

Review:
Support (REVIEW) .. NO
Filter ..... YES
Max bufsize cmd .... 16384
Max bufsize buf .... 5120

Page 5 of 7
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help      NextNuc   Exit      ABC List  Modify   -         +         Menu

```


in a NucID field on this screen. When the highest nucleus in a cluster is reached, PF2 causes AOS to cycle back to the beginning and changes the nucleus ID to the lowest nucleus ID in the cluster. Once the nucleus ID is changed, it remains in use for all Adabas Online System screens until it is changed again.

➤ **To modify Adabas nucleus (ADARUN) parameters:**

- Choose option **P** on the **Session Monitoring** menu and press **Enter**. Modifiable values are highlighted (intensified) on the displays. The equivalent direct command is:

```
MODIFY PARAMETERS
```

A series of Modify Parameters screens appear. You can scroll through the screens using the PF7 (scroll backward) and PF8 (scroll forward) keys. The information on these screens and the number of screens that appear varies depending on the type database you have selected. For a description of each ADARUN parameter, read *ADARUN Parameter Reference*, in the *Adabas Online Systems (AOS) Reference Guide*.

The following screens might display for an Adabas database in an Adabas cluster:

```
19:16:32          ***** A D A B A S BASIC SERVICES *****          2017-09-25
DBID 1955          - Modify Parameters -          PACP032
NucID 1021
Modify parameters below, as required:
----- Pools -----
Sort Area          (LS).. 19968
Int. User Buffer    (LU).. 400000
Buffer Pool        (LBP).. 283392
Format Pool        (LFP).. 150000
ISN List Table     (LI).. 360000
Seq. Cmd. Table    (LQ).. 20000
Work Pool          (LWP).. 1500000
Attached Buffer     (NAB).. 100
Security Pool      (LCP).. 10000
UQ-DE Pool        (LDEUQP).. 50000
Err. Recovery      (MSGBUF).. 36
----- Queues -----
Command Queue      (NC) .. 20
Hold Queue         (NH) .. 1200
User Queue         (NU) .. 200
----- Time Windows -----
Transaction Time   (TT) .. 4858
Max Transaction Time (MXTT) .. 3600
Nonactivity ACC-User (TNAA) .. 4858
Nonactivity ET-User (TNAE) .. 4858
Nonactivity EXU-User (TNAX) .. 4858
Max Nonactivity Time(MXTNA) .. 3600
Time Limit Sx-Cmds (TLSCMD) .. 300
Max Time for Sx-Cmds(MXTSX) .. 3600
Command Time       (CT) .. 3858
SYNS60 Interval   (INTNAS) .. 3600

Page 1 of 7
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help      NextNuc   Exit      ABC List   Display   +         Menu
```

Monitoring Adbas Sessions

```

19:16:32          ***** A D A B A S  BASIC  SERVICES  *****          2018-09-25
DBID 1955          -  Modify Parameters  -          PACP032  ↵

NucID 1021                                             ↵

Modify parameters below, as required:                 ↵

----- Miscellaneous -----      ----- Miscellaneous -----
Read only      (READONLY).. NO          LARGEPAGE ..... NO          ↵
UTI only       (UTIONLY).. NO          V64BIT ..... NO          ↵
OPEN required  (OPENRQ).. NO          SRLOG ..... Upd          ↵
Ignore DIB Entry(IGNDIB).. NO          LOGWARN (LOGWARN) ..... 0  ↵
Local nucleus  (LOCAL) .. NO          SECUID (SECUID) ..... ALLOW ↵
Number of Threads (NT) .. 5          INDEXCROSSCHECK (IND) .... YES ↵
Non DE Search  (NONDES) .. YES          Print on refresh (REFSTPRT) YES ↵
Log AOS/DBS Upd (AOSLOG).. YES          Number plog buffers ..... 1  ↵
Batch Support  (BATCH) .. NO          Number work1 buffers ..... 1  ↵
Data Protection Area(LP).. 1000          Event log buffer size ..... 1024 ↵
Ignore Wrk Prt4(IGNDTP) .. NO          Auto-restart buffers (ARN). 9  ↵
WORK-Part-4 Area (LDTP) .. 0          AUDITLOG (AUDITLOG) ..... CONSOLE ↵
WORK-Part-2 Area(LWKP2) .. 180          zIIP processors (ZIIP) .... YES  ↵
SVC              (SVC) .. 249          ↵
                                             ↵
                                             Page 2 of 7
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12----- ↵
Help      NextNuc   Exit      ABC List  Display  -      +      Menu

```

```

19:16:32          ***** A D A B A S BASIC SERVICES *****          2017-09-25
DBID 1955          - Modify Parameters -          PACP032
NucID 1021

----- Space Warning -----
ASSOSPACEWARN ..... 0_____
DATASPACEWARN ..... 0_____

----- Auto Increase -----
AUTOINCASSOTHRESHOLD ..... 0__          AUTOINCDATATHRESHOLD ..... 0__
AUTOINCASSOSIZE ... 0_____ CYL          AUTOINCDATASIZE ... 0_____ CYL
AUTOINCASSOTOTAL .. 0_____ CYL          AUTOINCDATATOTAL .. 0_____ CYL

----- SMF -----
SMF ..... NO

Page 3 of 7
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help      NextNuc   Exit      ABC List  Display  -          +          Menu

```

```

19:16:32          ***** A D A B A S BASIC SERVICES *****          2017-09-25
DBID 1955          - Modify Parameters -          PACP032
NucID 1021
Modify parameters below, as required:
---- Command Logging ----          ----- Command Logging -----
Command Logging .. YES          Log VOLSER info (LOGVOLIO) .. NO
LOGCB ..... NO          Max buffer size/cmd (CLOGMAX) .. 16384
LOGFB ..... YES          Max buffer size/buf(CLOGBMAX) .. 4096
LOGRB ..... YES          Log ABDX (LOGABDX) .. NO
LOGSB ..... NO          Log multifetch buffer (LOGMB) .. NO
LOGVB ..... NO          Command log layout(CLOGLAYOUT).. 8
LOGIB ..... NO
LOGIO ..... NO
LOGUX ..... NO
LOGSIZE ..... 5064          ----- Protection Logging -----
DUAL CLOG Size ... 675          PLOG required (PLOGRQ) .. YES
DUAL CLOG Dev. ... 3390          DUAL PLOG Size (DUALPLS) .. 240
NCLOG ..... 0          DUAL PLOG Device (DUALPLD) .. 3390
NPLOG ..... 0

Page 4 of 7
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help      NextNuc   Exit      ABC List  Display  -          +          Menu

```

Monitoring Adabas Sessions

```

19:16:32          ***** A D A B A S BASIC SERVICES *****          2017-09-25
DBID 1955          - Modify Parameters -          PACP032
NucID 1021

----- Large Pools -----
Flush I/O Pool (LFIOP) ... 80000

----- User Specific Limits -----
Hold Queue Limit (NISNHQ) .. 400
CIDs per User      (NQCID) .. 40
ISNs / TBI Element (NSISN) .. 100

----- Buffer Pool -----
Bufferflush Dur. (TFLUSH) .. 1
Parallel LFIOP I/O (FMXIO) .. 1
Async. by Vol-Ser (ASYTVS) .. YES

----- Other Services -----
Triggers / Procedures (SPT) .. YES
Delta Save Facility (DSF) .. YES
Cache Facility (CACHE) .. NO
Transaction Manager (ATM) .. NO
TCP/IP Support (TCPIP) .. NO
Ext. Error Recovery (SMGT) .. YES
2 Phase Commit Support(DTP) .. NO

Review:
Support (REVIEW) .. NO
Filter ..... YES
Max bufsize cmd .... 16384
Max bufsize buf .... 5120

Page 5 of 7
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help      NextNuc   Exit      ABC List  Display  -          +          Menu

```

```

19:16:32          ***** A D A B A S BASIC SERVICES *****          2017-09-25
DBID 1955          - Modify Parameters -          PACP032
NucID 1021

----- Cluster/Parallel Services -----
Environment ..... Sysplex
ARM element name .....
Cache structure name . ADA_CACHE4
Lock structure name .. ADA_LOCK4
Sysplex group name ... WISPLEX
Cache type ..... DSP
DIrratio ..... 4
Elemratio ..... 1
Redo Pool (LRDP) .... 80000
CLOGMRg ..... NO
CLUCACHEUnchanged ... No
CLULOCKSize ..... 0
CLUCACHESize ..... 0

----- Cluster/Parallel Services -----
MXMSG ..... 300
MXMSGWarn ..... 75
MXCANCEL ..... 300
MXCANCELWarn ..... 75
MXWtor ..... 0
MXStatus ..... 15
CLUPUBLPROT ..... YES
CLUWORK1CACHE ..... 0

Page 6 of 7
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help      NextNuc   Exit      ABC List  Display  -          +          Menu

```

```

19:16:32          ***** A D A B A S BASIC SERVICES *****          2017-09-25
DBID 1955          - Modify Parameters -          PACP032
NucID 1021

---- Replication Parameters -----
Replication ..... YES
RPWARNPercent ..... 0
RPWARNINcrement ..... 10
RPWARNINterval ..... 60
RPWARNMessageLimit ... 5
RPCONNECTCount ..... 0
RPCONNECTInterval ... 0
RPLSORT ..... YES
LRPL ..... 100000

Page 7 of 7
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help      NextNuc   Exit      ABC List  Display  -          Menu

```



Notes:

1. If you press PF4 (ABC List) on any of these screens, an alphabetic list of the ADARUN parameter settings is shown.
2. In cluster environments, the PF2 key allows you to scroll sequentially through nucleus IDs in the cluster using the NextNucid command. In addition, the current nucleus ID is shown in a NucID field on this screen. When the highest nucleus in a cluster is reached, PF2 causes AOS to cycle back to the beginning and changes the nucleus ID to the lowest nucleus ID in the cluster. Once the nucleus ID is changed, it remains in use for all Adabas Online System screens until it is changed again.

The following screen might display as the last screen of the series or parameter screens for an Adabas database that operates as an Event Replicator Server:

```
02:17:45          ***** A D A B A S BASIC SERVICES *****          2014-06-30
DBID 1954          - Modify Parameters -                               PACP022

----- Reptor Parameters -----
RPLParms ..... None
RPWARNPercent ..... 0
RPWARNINcrement ..... 10
RPWARNINTERval ..... 60
RPWARNMessageLimit ... 5
RPCONNECTCount ..... 0
RPCONNECTInterval .... 0
LRPL ..... 25000000

Page 6 of 6
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit      ABC List Display -          Menu          ↵
```

Displaying Installed Products

Choose option **I** on the **Session Monitoring** menu and press ENTER to display a list of installed products.

```

02:19:08          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
DBid 1955          - Display Installed Products -          PACII02
NucID 1021

-----
Cache Facility ..... NO          Extended Error Recovery ..... YES
Delta Save Facility ..... YES      Recovery Aid ..... YES
Cluster Services ..... YES        Stored Procedures & Triggers .. NO
Parallel Services ..... NO        Two Phase Commit ..... NO
Fastpath ..... NO                TCPIP support ..... NO
Vista ..... NO                   Event Replicator ..... YES
Transaction Manager ..... NO
SAF Security Interface ... NO
Review ..... LOCAL
Adabas Online System ..... YES

Command ==>
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit          Menu          ↵

```

This screen displays what is installed on the current selected Adabas

Displaying the Event Log Buffer

Selecting **Display Event Log Buffer** (option L) from the **Session Monitoring** menu invokes the Display Event Log Buffer screen.

The Adabas event log is a wraparound log in memory that is used to log each response code 145 (RSP145) event. The INFOBUFFERSIZE ADARUN parameter identifies the size of the Adabas event log. Each entry in the event log is currently 128 bytes, although this may change in later Adabas releases. When the Adabas event log fills up, the oldest entries in the log are overwritten.

This is the equivalent of running the ADADBS DEVENTLOG utility function.

Monitoring Adabas Sessions

```
16:05:10          ***** A D A B A S  BASIC  SERVICES *****          2014-05-01
DBID 11131          -  Display Event Buffer Log  -          PACL002
```

Sel	Nucid	File	Resp	ISN	Date	Time	Aff Jobn	Causer Jobn
—		1	145	9999	2009-08-14	20:12:18	SCAATATU	SCAATATU
—								
—								
—								
—								
—								
—								
—								
—								
—								
—								
—								

Enter 'S' to display

```
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help                Exit                Menu
```

When you enter an "S" next to an event listed on the Display Event Buffer Log screen, the Selected Event Buffer Log screen appears, allowing you to review detailed log data in the event log for the selected event.

```
16:05:10          ***** A D A B A S  BASIC  SERVICES *****          2014-05-01
DBID 11131          -  Selected Event Buffer Log  -          PACL002
```

File	Resp	ISN	Date	Time	Nucid
1	145	9999	2009-08-14	20:12:18	

Affected

Jobname	ET id	SAF id
SCAATATU	???	

Userid (hex)
0004A10E209800004040404040404000FC0100E4F0F0F200000000

Causer

Jobname	ET id	SAF id
SCAATATU	???	

Userid (hex)
0004A10E209800004040404040404000FC0100E4F0F0F100000000

Press ENTER to continue

Displaying Queues

Choose option **Q** on the **Session Monitoring** menu and press **ENTER** to display the **Queue Displays** menu.

```

16:31:49          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
                   - Queue Displays -                               PAC0002

                Code      Service
                ----      -
                A         Display User Queue Elements
                C         Display Command Queue
                H         Display Hold Queue
                ?         Help
                .         Exit
                ----      -

Code ..... _
Max No. Elements ... 100
Last Activity ..... 0          (elapsed time in seconds)
Selection Criteria (Selected User USASASW and Tid TSU03216)
  ET-ID (User-ID) .. _____ User Type ... ____
  Job Name ..... _____
  Terminal ID ..... _____
Database ID ..... 1955          (WIS1955)          NucID .. 1021

Command ==>
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help      NextNuc  Exit      Clear UID          Menu      ↵

```



Notes:

1. The **ET-ID (User-ID)** field can be used to specify an ETID or security user ID (SECUID), as appropriate for your site.
2. In cluster environments, the **PF2** key allows you to scroll sequentially through nucleus IDs in the cluster using the **NextNucid** command. In addition, the current nucleus ID is shown in a **NucID** field on this screen. When the highest nucleus in a cluster is reached, **PF2** causes AOS to cycle back to the beginning and changes the nucleus ID to the lowest nucleus ID in the cluster. Once the nucleus ID is changed, it remains in use for all Adabas Online System screens until it is changed again.

The Display Queues function shows, in table format, the contents of the user, command, or hold queue. Each displayed table entry contains a related terminal ID (TID), job name, user ID (ET-ID or security user ID, as appropriate), current status, and related information such as files currently in use and command type. These queues are a rapidly changing environment of individual entries, each with a life span of milliseconds. This can present challenges when you are scrolling through

results. For example, when you display, exit, or page forward and back, the previously displayed item might be changed or might be completed or unavailable.

If you try to display a queue that is currently empty, an appropriate message appears on the Display Queues menu.

Individual entries in the selected queues can be displayed to provide more detailed information, or selected for a later Basic Services function (the individual user-level statistics sampling described in section *Obtaining Current Snapshot Statistics* is an example).

When displaying user queue elements (UQE), command queue elements (CQE), or hold queue elements (HQE), you can use the program function key PF5 *Filter* to filter the displayed information. The PF5 key invokes the *Filter* pop-up menu and enables you to select what information is displayed. For user and command queues, you can specify *Secuid* and/or *File number*, and for hold queues, you can specify *File Number* and/or *ISN*. To return to the original display of information, clear the fields in the *Filter* pop-up menu.

This section covers the following topics:

- [Displaying User Queue Elements](#)
- [Displaying the Command Queue](#)
- [Displaying the Hold Queue](#)

Displaying User Queue Elements

If you select **Display User Queue Elements** (option A) on the **Queue Displays** menu, you must also specify the maximum number of elements to display. Other selection criteria you may optionally specify include:

- number of seconds since last activity
- logical user ID (ETID)
- type of user (ACC, AOS, ET, EXU, EXF, UTI)
- job name
- terminal ID and
- database ID

If multiple selection criteria are specified, they are combined with logical ORs.

The equivalent display direct command is:

```
DISPLAY UQ user queue
```

```

14:42:12          ***** A D A B A S BASIC SERVICES *****          2015-05-20
DBID 1955 (1021)          - Display User Queue -          PACQA42
SEL-CRIT: MAX-NUM = 100

Total Users .. 3
Mark entries with 'D' (Display) or 'S' (Select):
  I      I      I      I User I User I Last      I      I
M I TID      I ET-ID      I Jobname I Type I State I Active      I File(s)      I
-----
_ I TSU09745 I USAWIS      I USAWIS      I AOS      I      I      I      I None      I
_ I CEF94B54 I      I      I USAWISRP I ET      I ET      I      I 36 I 11      I
_ I USAWIS 1 I      I      I ZCOMPLET I ET      I ET      I      I 20 I None      I
_ I      I      I      I      I      I      I      I      I      I
_ I      I      I      I      I      I      I      I      I      I
_ I      I      I      I      I      I      I      I      I      I
_ I      I      I      I      I      I      I      I      I      I
_ I      I      I      I      I      I      I      I      I      I
_ I      I      I      I      I      I      I      I      I      I
_ I      I      I      I      I      I      I      I      I      I
_ I      I      I      I      I      I      I      I      I      I
_ I      I      I      I      I      I      I      I      I      I
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit      Refresh  SECUID      -      +      Menu

```



Note: In cluster environments, the PF2 key allows you to scroll sequentially through nucleus IDs in the cluster using the `NextNucid` command. In addition, the current nucleus ID is shown in a `NucID` field on this screen. When the highest nucleus in a cluster is reached, PF2 causes AOS to cycle back to the beginning and changes the nucleus ID to the lowest nucleus ID in the cluster. Once the nucleus ID is changed, it remains in use for all Adabas Online System screens until it is changed again.

The PF6 key allows you to switch columns of either having the ET-ID displayed or the security user ID (SECUID) displayed.

If you choose to display (D) an individual user ID, a user queue element information screen similar to the following appears:

```

16:55:21          ***** A D A B A S  BASIC  SERVICES *****          2015-05-20
DBID 1955  (1021)          -  Display User Queue Element  -          PACQA42

I          I          I          I          I User I User  I Last  I
I TID      I SECUID   I Jobname I ETID    I Type I State I Active I
-----
I TSU09745 I USAWIS   I USAWIS  I USAWIS  I AOS  I      I      0 I
-----
Global Uid= 0009A10E28280000 4040404040404040 00FBE100 E3E2E4F0F9F7F4F5
Hold Queue Limit ..... 0          ETID Hex Display .. E4E2C1E6C9E24040
Max. parallel CIDs per User . 40
Max. ISNs per TBI Element ... 100          Start Times
Max. Time of Nonactivity .... 3775          Session ..... 2015-05-20 10:42:09
Max. Transaction Time ..... 0          Transaction .. 0000-00-00
Time Limit for Sx Commands .. 300          File List
No. of ISNs currently held .. 0          None
No. of CIDs currently in use: 0
No. of Calls ..... 121
No. of I/Os ..... 131
Priority from ET/CP File .... 0

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit          Menu
    
```

 **Note:** The **ET-ID** column on both of these screens will show ETIDs or security user IDs (SECUIDs), as appropriate for your site. The column title will change, based on what is displayed.

Displaying the Command Queue

If you choose **Display Command Queue** (option C) on the **Queue Displays** menu, the current commands in the command queue and their status are listed. PF2 allows you to switch the display between "time-in" and "job name".

The equivalent display direct command is:

```

DISPLAY CQ
    
```


Monitoring Adabas Sessions

10:44:47 ***** A D A B A S BASIC SERVICES ***** 2014-05-02
DBID 1955 - Display Hold Queue - PACQH22

Mark entries with 'S' to select a user :

M	I	FNR	I	ISN	I	Mode	I	TID	I	SECUID	I	Jobname	I	ETID
-	I		1	I		20	I	I	USAXXX	2	I	USAXXX	I	I
-	I			I			I	I			I		I	I
-	I			I			I	I			I		I	I
-	I			I			I	I			I		I	I
-	I			I			I	I			I		I	I
-	I			I			I	I			I		I	I
-	I			I			I	I			I		I	I
-	I			I			I	I			I		I	I
-	I			I			I	I			I		I	I
-	I			I			I	I			I		I	I
-	I			I			I	I			I		I	I
-	I			I			I	I			I		I	I
-	I			I			I	I			I		I	I

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help Exit Refresh - + Menu

Refreshing Interval Statistics

Selecting **Refresh Interval Statistics** (option **R**) on the **Session Monitoring** menu displays the **Interval Statistics** screen:

```

13:18:12          ***** A D A B A S  BASIC  SERVICES *****          2014-04-29
DBID 1955          - Interval Statistics -          PACR012
NUCID 1021

                Mark each nucleus statistic to be reset:

                    - Command Usage
                    - File Usage
                    - Pool Usage
                    - Thread Usage
                    - Counters
                    - Time Elapsed
                    - I/O

Command ==>
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit          Menu          ↵

```

To select the statistics to be refreshed, place an "X" in the space next to the statistic type.

More than one statistic may be refreshed at the same time. The statistics selected are reset to zero.

PF3 cancels the request and returns to the **Session Monitoring** menu. PF12 cancels the request and returns to the AOS **Main Menu**.

Obtaining Current Snapshot Statistics

Selecting **Current Snapshot Statistics** (option S) on the **Session Monitoring** menu invokes the **Snapshot Statistics** menu:

```

13:22:10          ***** A D A B A S BASIC SERVICES *****          2014-04-29
                   - Snapshot Statistics -                               PACS002

                Code      Service
                ----      -
                G          Start General Statistics
                R          Read General Statistics
                S          Read User Statistics
                U          Start User Statistics
                ?          Help
                .          Exit
                ----      -

Code ..... _
Duration ..... 60 seconds
User ID .....
Database ID .. 1955      (WIS1955)          NucID .. 1021

Command ==>
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help      Disp UQ   Exit      Clear UID          Menu      ↵
    
```

Snapshot statistics provide information about file and command use either for a single user (user statistics) or for all currently active users (general statistics). The statistics must first be collected by starting a sampling period for which you have specified a time period in seconds (duration).

➤ **To obtain statistics for all currently active users**

- Start general statistics (option **G**) and, after the specified duration, read them (option **R**).

The equivalent direct commands are:

```

START STATISTICS
READ STATISTICS
    
```

For more information, read *Basic Services Direct Commands*.

If user statistics are started (option **U**) or subsequently read (option **S** after the specified duration), a user ID must either be indicated on this screen or have been previously selected in the **Display User Queue** (PF2) or **Display Command Queue** options. PF4 is used to deselect a previously selected user ID.

This section covers the following topics:

Three screens of statistics are displayed: the first two show command usage (use PF7 and PF8 to toggle between these; the third shows file usage (use PF4 to toggle between the file usage and command usage screens):

- Command Usage Display
- File Usage Display

Command Usage Display

The following general command usage information for all currently active users is displayed:

```

09:24:04          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
DBID 1955          -  General Statistic:  Command Usage  -          PACSR32
NUCID 1021
Statistic Start Time .. 2014-05-02  05:20:42
Total Commands .....          10,887

CMD-Type      Nr.  CMDs      CMD-Type      Nr.  CMDs      CMD-Type      Nr.  CMDs
-----
A1/4           0      L2/5           1      S5             0
BT             0      L3/6          2,136    S8             0
CL            30      L9            219      S9             0
C1             0      N1/2           0      UC            503
C3             0      OP             36      U0             0
C5             0      RC            1,569    U1             0
ET             0      RE             0      U2             0
E1/4           0      REST          5,288    U3             0
HI             0      RI             0      V1             0
LF             3      S1/4          1,061    V2             0
L1/4          15      S2             0      V3             13
                                           Page 1 of 2

PF1----- PF2----- PF3----- PF4----- PF7----- PF8----- PF9----- PF12-----
Help          Exit       File          +          Menu      ↵

```

Monitoring Adabas Sessions

```

09:24:04          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
DBID 1955          -  General Statistic:  Command Usage  -          PACSR32
NUCID 1021
Statistic Start Time .. 2014-05-02  05:20:42
Total Commands .....          10,887

CMD-Type      Nr. CMDs      CMD-Type      Nr. CMDs      CMD-Type      Nr. CMDs
-----
V4              13
YA              0
YB              0
YCAL           0
YF              0
YP              0

Page 2 of 2

PF1----- PF2----- PF3----- PF4----- PF7----- PF8----- PF9----- PF12-----
Help          Exit       File       -          -          -          -          Menu      ←
  
```

If PF4 (**File**) is clicked, the commands used by file number are shown.

```

09:24:04          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
DBID 1955          -  General Statistic:  File Usage  -          PACSR32
NUCID 1021
Statistic Start Time ..... 2014-05-02  05:20:42

File   File Name          No. Cmds   File   File Name          No. Cmds
-----
  0   *Cmds with no Fnr*      7         11  NAT-SYSTEM          2

Total Commands:          10887

Command ==>
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit       Cmds      --        -          +          -          Menu      ←
  
```

If user statistics are collected and read, the following command usage information is displayed for the specific user:

```

16:12:34          ***** A D A B A S  BASIC  SERVICES *****          2014-03-17
DBID 1957          -  User Statistics:  Command Usage  -          PACSS22

Statistic Start Time ..... 2013-03-05  11:11:15          UserID ... TSU02013
                                                (USAXXXX)

L1/4 - Read/Get Record ....          A1/A4 - Update Record ....
L2/5 - Read Physical .....          N1/N2 - Add Record .....
L3/6 - Read Logical .....          E1/E2 - Delete Record ....
L9   - Read Descriptor ....
LF   - Read Field Def. ....          OP   - Open User Sess ...
RE   - Read ET Data .....          CL   - Close User Sess ..
                                          ET   - End Transaction ..
S1/4 - Find Records .....          BT   - Backout Tran. ....
S2   - Find Sorted .....
S5   - Find Coupled ISN ...          RC   - Release Cmd ID ...
S8   - Process ISN List ...          UC   - Utility Command ..          9
S9   - Sort ISN List .....

                                          Press PF8 for more

Command ==>
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit          File          +          Menu          ↵

```

```

16:12:34          ***** A D A B A S  BASIC  SERVICES *****          2014-03-17
DBID 1957          -  User Statistics:  Command Usage  -          PACSS22

Statistic Start Time ..... 2013-03-05  11:11:15          UserID ... TSU02013
                                                (USAXXXX)

REST - Follow up cmds ....          U0   - U0 commands .....
                                          U1   - U1 commands .....
YA   - YA commands .....          U2   - U2 commands .....
YB   - YB commands .....          U3   - U3 commands .....
YC   - YC commands .....
YP   - YP commands .....          V1   - V1 commands .....
YCAL - YCAL commands .....          V2   - V2 commands .....
                                          V3   - V3 commands .....
                                          V4   - V4 commands .....

Thread Time (msec) ..... 0.0          100%  User's commands ..
No. of I/Os ..... 0          Total commands ...          10

Command ==>
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help      GStat      Exit      File      --      -          Menu          ↵

```

File Usage Display

The following general file usage information for all currently active users is displayed:

```
16:13:57          ***** A D A B A S  BASIC  SERVICES *****          2014-03-17
DBID 1957          -  General Statistic:  File Usage  -          PACSR22

Statistic Start Time ..... 2013-03-05  11:11:15

File   File Name                No. Cnds   File   File Name                No. Cnds
-----
      0  *Cmnds with no Fnr*          10

                                          Total Commands:          10

Command ==>
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit          Cnds          - -          -          +          Menu          ↵
```

If user statistics are collected and read, the following file usage information is displayed for the specific user:

```

16:55:50          ***** A D A B A S BASIC SERVICES *****          2014-03-17
DBID 1957          - User Statistics: File Usage -                      PACSS22
                                                                (USAXXXX)
Statistic Start Time ..... 2013-03-05 11:17:06          UserID ... TSU02013
Thread Time (msec) ..... 0.0                                No. I/Os.. 0
File   File Name          No. Cnds   File   File Name          No. Cnds
-----
*** No Files Used ***

Perc of all cmds .. 100%          Commands processed:

Command ==>
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help      GStat      Exit      Cmd                        Menu      ↵

```

Maintaining TCP/IP URLs

Selecting **Maintain TCP/IP URL** (option **T**) from the **Session Monitoring** menu invokes the Display/Maintain URL screen:

```

16:09:20          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
DBID 1955          -  Display/Maintain URL  -          PACTC02

Mark entries with 'O' to Open or 'C' to Close a URL:

      M          URL          Status          Message
      -          -          -          -
      -  HPS://TCPIPMS:1962_  Closed
      -  HPS://TCPIPMS:1963_  Open
      -  HPS://TCPIPMS:1964_  Open
      -  HPS://TCPIPMS:1965_  Open
      -  _____

Command ==>
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit          Refr          -          -          +          Menu
    
```

The screen displays a list of all defined URLs and their current status: open or closed.

➤ **To change the status of a URL:**

- Enter "O" to open or "C" to close a URL in the corresponding M column next to the URL entry.

➤ **To define a new URL and open it:**

- Use the blank line provided at the end of the URL list.

Once you have made your changes, press PF4 (Refr) to refresh the list.

Monitoring Interval Utilization

Interval utilization displays provide a comprehensive overview of Adabas operations for an interval.

Each of the interval utilization options contain a refresh capability (PF4) that allows you to refresh the displayed values, a convenience for long-term monitoring of Adabas system functions.

Selecting **Display Interval Utilization** (option U) from the **Session Monitoring** menu invokes the **Interval Utilization** menu:

```

16:39:08          ***** A D A B A S BASIC SERVICES *****          2014-05-05
                    - Interval Utilization -                          PACU002

Code  Service                               Code  Service
-----
C    Command usage                          S    System status
F    File usage                             T    Thread usage
H    High watermarks (pools/queues)         V    I/Os by Volser
L    Workpool (LWP) usage                   W    WORK status
N    Nucleus File Status                    Y    Display PPT
P    PLOG status
?    Help
.    Exit
-----

Code ..... _
File Number .. 0
Database ID .. 1955 (WIS1955)                NucID .. 1021

Command ==>
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help      NextNuc  Exit                                     Menu      ↵

```



Note: In cluster environments, the PF2 key allows you to scroll sequentially through nucleus IDs in the cluster using the `NextNucid` command. In addition, the current nucleus ID is shown in a `NucID` field on this screen. When the highest nucleus in a cluster is reached, PF2 causes AOS to cycle back to the beginning and changes the nucleus ID to the lowest nucleus ID in the cluster. Once the nucleus ID is changed, it remains in use for all Adabas Online System screens until it is changed again.

This section covers the following topics:

- [Monitoring Command Usage](#)
- [Monitoring File Usage](#)
- [Reviewing High Water Marks](#)
- [Monitoring Work Pool \(LWP\) Usage](#)
- [Reviewing Nucleus File Status](#)
- [Reviewing Protection Log \(PLOG\) Status](#)
- [Reviewing System Status](#)
- [Monitoring Thread Usage](#)
- [Reviewing I/Os by Volume Serial Number](#)
- [Reviewing Work Status](#)
- [Displaying the PPT](#)

■ [Displaying zIIP Statistics](#)

Monitoring Command Usage

Selecting **Command Usage** (option C) on the **Interval Utilization** menu displays the Command Usage screen, which shows the total and average execution time of each Adabas command type issued during the current session and processed by the Adabas nucleus. It also shows the total of all Adabas commands issued.

The values shown on this screen are shown in compressed form. Each can display as a nine-digit value, with appropriate multiplier letters "k" (1000), "M" (1000000), "G" (1000000000), and "T" (1000000000000) (representing consecutive powers of 1000) if necessary. On any of these screens, you can press PF9 to see the actual values (without the multipliers) of the counters on the screens. In this view (full view), there are fewer statistics on each screen, so there are more screens to page through. To return to compressed view, just press PF9 again.

If the value of a counter on these screens ever exceeds the space available for the statistic, the statistic will display in red.

The equivalent direct command is:

```
DISPLAY CMDUSAGE
```

A two-screen display appears:

```

18:35:22          ***** A D A B A S  BASIC  SERVICES *****          2014-04-30
DBID 1955          -  Command Usage  -          PACUC22
NucID 1021

Total Commands ..          7,228

CMD-Type I  Nr.  CMDs      I  Aver.  Dur.      CMD-Type I  Nr.  CMDs      I  Aver.  Dur.
-----
A1/4   I           0   I           0.000      BT       I           0   I           0.000
CL     I           18  I           4.627      C1       I           0   I           0.000
C3     I           0   I           0.000      C5       I           0   I           0.000
ET     I           0   I           0.000      E1/4    I           0   I           0.000
HI     I           0   I           0.000      LF       I           0   I           0.000
L1/4   I           15  I           1.486      L2/5    I           1   I           0.000
L3/6   I          1,633  I           3.580      L9       I          203  I           1.797
N1/2   I           0   I           0.000      OP       I           24  I          10.539
RC     I          1,260  I           0.008      RE       I           0   I           0.000
REST   I          3,127  I           0.000      RI       I           0   I           0.000
S1/4   I           678  I           7.635      S2       I           0   I           0.000
(Aver. Dur. - units of milliseconds)
Page 1 of 2

PF1----- PF2----- PF3----- PF4----- PF7----- PF8----- PF9----- PF12-----
Help          Exit      Refresh          +          Fullview Menu  ↵
    
```

```

18:35:22          ***** A D A B A S BASIC SERVICES *****          2014-04-30
DBID 1955          - Command Usage -          PACUC22
NucID 1021

Total Commands ..          7,228

CMD-Type I  Nr.  CMDs          I Aver. Dur.          CMD-Type I  Nr.  CMDs          I Aver. Dur.
-----
S5      I      0      I          S8      I      0      I
S9      I      0      I          UC      I      251   I      2.291
U0      I      0      I          U1      I      0      I
U2      I      0      I          U3      I      0      I
V1      I      0      I          V2      I      0      I
V3      I      9      I          V4      I      9      I      0.009
YA      I      0      I          YB      I      0      I
YCAL    I      0      I          YF      I      0      I
YP      I      0      I

(Aver. Dur. - units of milliseconds)                                Page 2 of 2

PF1----- PF2----- PF3----- PF4----- PF7----- PF8----- PF9----- PF12-----
Help          Exit      Refresh -          Fullview Menu      ↵

```

Adabas includes some V* and Y* commands , which you may see mentioned in Adabas shutdown statistics or in Adabas Online System (AOS) screens. These commands are used internally by Adabas and Adabas add-on products and should not be used in direct calls in your applications. Should you use them, errors will result.

Monitoring File Usage

Selecting **File Usage** (option F) on the **Interval Utilization** menu displays the File Usage screen , which shows one of the following things.

- If you select file number 0 (zero) on the **Interval Utilization** menu, all files of the database used during the session and the number of accesses to each file are displayed on the File Usage screen.

The equivalent direct command is:

```
DISPLAY FILUSAGE
```


Reviewing High Water Marks

Selecting **High Water Marks** (option **H**) on the **Interval Utilization** menu displays the use of major Adabas pools and queues. It shows the size of each pool or queue as well as the highest amount or the pool or queue used and the current amount in use.



Note: The Replication Pool may appear as "Replication N/A" on this screen if the database is not an Event Replicator Server or if replication is not activated for the database.

The **HW Used** column and the **%Used** column following it show the highest size (in bytes) and highest percentage of the pool or queue reached in the current session. These counters may be doubleword fields. They are shown as nine digits with an optional multiplier letter: "k" (1000), "M" (1000000), "G" (1000000000), and "T" (1000000000000), representing consecutive powers of 1000.

These values are a good starting point when looking for a problem with limited buffer, pool, or queue space, or if you are looking for unused storage resources.

The equivalent direct command is:

```
DISPLAY HWM
```

A multiple-screen report appears.

```
18:38:32          ***** A D A B A S  BASIC  SERVICES *****          2014-04-30
DBID 1955          - High Watermarks -          PACUH22
NucID: 1021
```

Sel	Pool / Queue	I	Size	I	HW Used	%Used	I	Current	%Used
_	Attached Buffer(NAB)	I	409600	I	33536	8.1	I	0	0.0
_	Command Queue (NC)	I	3840	I	192	5.0	I	192	5.0
_	Unique DE Pool (DUQ)	I	50000	I	0	0.0	I	0	0.0
_	Format Pool (LFP)	I	150000	I	8416	5.6	I	8416	5.6
_	Hold Queue (NH)	I	41600	I	0	0.0	I	0	0.0
_	PLOG Prot buf(NPLOGB)	I	1	I	1	100.0	I	0	0.0
_	Redo Pool (LRDP)	I	80000	I	28	0.0	I	0	0.0
_	Replication Pool(LRP)	I	100000	I	0	0.0	I	0	0.0
_	Security Pool (LCP)	I	10000	I	0	0.0	I	0	0.0
_	ISN List Tab (LI)	I	360000	I	0	0.0	I	0	0.0
_	Seq. Cmd. Table(LQ)	I	20000	I	508	2.5	I	0	2.5
_	User Queue (NU)	I	74256	I	1820	2.4	I	1456	1.9
_	UQ File List (UQF)	I	19584	I	216	1.1	I	144	0.7

Page 1 of 2

```
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help                Exit      Refresh                +      Menu      ←
```

Monitoring Adabas Sessions

```
18:38:32          ***** A D A B A S BASIC SERVICES *****          2014-04-30
DBID 1955          - High Watermarks -          PACUH22
NucID: 1021
```

Sel	Pool / Queue	I	Size	I	HW Used	%Used	I	Current	%Used	
_	Work Prt1 Prot	bf(NW)	I	1	I	1	100.0	I	0	0.0
_	Work Pool	(LWP)	I	1500000	I	62788	4.1	I	8016	0.5
_	Work Part 1	(LP)	I	1000	I	1	0.1	I	0	0.0
_	Work Part 2	(LWKP2)	I	158	I	0	0.0	I	0	0.0
_	Work Part 3	(WORKPT3)	I	6932	I	0	0.0	I	0	0.0
_	ATM Trans. IDs	(XID)	I	0	I	0	0.0	I	0	0.0
			I		I			I		
			I		I			I		
			I		I			I		
			I		I			I		
			I		I			I		
			I		I			I		

Page 2 of 2

```
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit      Refresh          -          Menu          ↵
```

You can select each line to see the full values of the pool or queue, since only nine digits can be displayed. Simply enter an "s" to the left of the pool or queue and a popup window appears showing you the full values for that pool or queue. The following sample shows detailed high-water statistics for the hold queue.



Note: You can select more than one pool or queue at a time; multiple popup windows will appear in sequence (you only need to press any key to move to the next one). When all the popups have been displayed once, you are returned to the High Water Marks selection screen.

```
Selected pool / queue .. Hold Queue(NH)
Available .....          41,600
High watermark .....          0
High watermark % used .          0.0
High watermark date ...    2014-04-30
High watermark time ...    14:06:52
Current used .....          0
Current % used .....          0.0
```

Press any key



The time and date values on this popup window show you when the highest value was reached. Values may be zero when the pool/queue is not used. For the attached buffer pool, no time and

date value are given. Also, note that Work part 3 values show the leftover amounts after the Work allocation of Work parts 1 and 2.

Monitoring Work Pool (LWP) Usage

Selecting **Work Pool (LWP) Usage** (option L) on the **Interval Utilization** menu displays the length of the used and unused parts of the work pool as well as the length of the longest single unused part. These numbers can be used to tune the work pool length for the next session.

The equivalent direct command is:

```
DISPLAY LWPUSAGE
```

```
18:40:38          ***** A D A B A S  BASIC  SERVICES *****          2014-04-30
DBID 1955          -  Workpool Usage  -          PACUL02
NUCID 1021

Workpool (LWP)
  Used part .....          8016 Bytes
  Unused part .....       1481312 Bytes
  Biggest unused part ..   1480336 Bytes

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit          Refresh          Menu          ↵
```

Reviewing Nucleus File Status

Selecting **Nucleus File Status** (option N) on the **Interval Utilization** menu is the equivalent of entering the DNFV operator command. The following display appears:

```

18:41:18          ***** A D A B A S BASIC SERVICES *****          2014-04-30
DBID 1955          - Nucleus File Status -          PACUN02
NucID 1021

          Locking
File   NucID  Access count  Update count  State
-----
11          0           0           0 Access
12          0           0           0 Access
19          0           0           0 Access

Last page
PF1----- PF2----- PF3----- PF4----- PF7----- PF8----- PF9----- PF12-----
Help   Repos   Exit   Refresh   -       +       Menu ←
    
```

In an Adabas cluster environment, the file may be locked for exclusive use by another cluster nucleus. If this is the case and the file is in the nucleus file status table, the Locking NucID column for the file shows the ID of the nucleus that has exclusive control.

The Access count and Update count columns display the number of access or update users, respectively, that refer to the specified file in their user queue elements (UQEs). These users either have specified the file in an OP command with the "R" option or are using the file in an as yet incomplete transaction.

The State column indicates when the file is used for access only or for access and update. It indicates to what extent a nucleus can use a file on its own. If the requested use exceeds the given state, the nucleus must first communicate with the other nuclei in the cluster in order to upgrade the state.

Reviewing Protection Log (PLOG) Status

Selecting **Protection Log (PLOG) Status** (option P) on the **Interval Utilization** menu displays the status of dual protection logs, if used.

The equivalent direct command is:

```

DISPLAY PLOGSTATUS
    
```

```

18:41:52          ***** A D A B A S BASIC SERVICES *****          2014-04-30
DBID 1955          - PLOG Status -          PACUP02
NucID: 1021

    The nucleus is currently writing on ..... PLOGR1

    Size of one PLOG area (in BLKs.) .....          240
    Last block written .....          46 ( 19 %)

    Number of switches since nucleus start .....          0
    Date/Time of last switch ..... 0000-00-00 00:00:00

    Number of switches due to coordinated switch....          0
    Number of writes forced by the merge process....          0

    Number of switch requests before threshold met..          0
    Threshold setting ..... 75%

    Number of PLOGs .....          2

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit      Refresh          PrevNuc  NextNuc  Menu
0                02,001      ↵

```

Reviewing System Status

Selecting **System Status** (option **S**) on the **Interval Utilization** menu displays I/O counts for the ASSO, DATA, WORK, and PLOG data sets; remote and local call distribution; and other current session status information.

The equivalent direct command is:

```
DISPLAY SYSTEMSTATUS
```

The values shown on this screen are shown in compressed form. Each can display as a nine-digit value, with appropriate multiplier letters "k" (1000), "M" (1000000), "G" (1000000000), and "T" (1000000000000) (representing consecutive powers of 1000) if necessary. On any of these screens, you can press PF9 to see the actual values (without the multipliers) of the counters on the screens. In this view (full view), there are fewer statistics on each screen, so there are more screens to page through. To return to compressed view, just press PF9 again.

If the value of a counter on these screens ever exceeds the space available for the statistic, the statistic will display in red.



Note: The values on the sample screens in this section have been artificially enhanced.

Monitoring Adbas Sessions

```

21:07:32          ***** A D A B A S BASIC SERVICES *****          2016-12-05
DBID 1955          - System Status -          PACUS12
NucID: 1021
Physical          Reads          Writes          Call Distribution
-----
ASSO              997              7              No. of HQEs active .....          0
DATA              287              0              No. of UQEs in User Queue ..          2
WORK              2                3              No. of CQEs waiting in CQ ..          0
PLOG              15               3              No. of PLOG switches .....          0
CLOG              19               2              No. of CLOGs .....          2
                  No. of PLOGs .....          2
PLOG protection blks .          2
PLOG protection I/Os .          2          Format translations .....          22
PLOG different blks .          2          Format overwrites .....          0
WORK1 protection blks.          2          Auto-restarts .....          0
WORK1 protection I/Os.          2          Throw-backs for ISN .....          0
WORK1 different blks .          1          Throw-backs for Space....          0

Logical reads .....          1,482
Buffer efficiency ....          1.1
                                                    page 1 of 5

PF1---- PF2---- PF3----- PF4----- PF6----- PF7----- PF8----- PF9----- PF12----
Help          Exit          Refresh          +          FullView Menu ←

```

Pressing PF8 displays additional system status statistics.

```

21:07:32          ***** A D A B A S BASIC SERVICES *****          2016-12-05
DBID 1955          - System Status -          PACUS12
NucID: 1021
Call Distribution          Commands
-----
User sessions .....          3          Remote .....          0
Buffer flushes .....          0          Local .....          287
Flush phases .....          0          Internal .....          18
Blocks flushed .....          0          Operator .....          0
Flush I/Os .....          0          Total .....          305

Flush Requests Returned          Time Elapsed
-----
Immediately .....          0          Duration .... 0 day, 00:13:51
After logical flush ..          0          Wait-time ... 0 day, 00:13:49
After entire flush ...          2          CPU time .... 0 day, 00:00:00

                                                    page 2 of 5

PF1---- PF2---- PF3----- PF4----- PF6----- PF7----- PF8----- PF9----- PF12----
Help          Exit          Refresh          -          +          FullView Menu ←

```

Pressing PF8 again will display an additional screen that indicates if one or more of the following are in progress:

- Online database save running;
- ADAEND in progress;
- Online file save running;
- READONLY/UTIONLY transition;
- READONLY status;
- Update processing suspended;
- ET-sync in progress;
- UTIONLY status; and
- Exclusive-DB-control utility running.

Otherwise, "Adabas operation normal" is displayed.

```

21:07:32          ***** A D A B A S  BASIC  SERVICES *****          2016-12-05
DBID 1955          - System Status -          PACUS12
NucID: 1021

                                Nucleus Status Flags
                                -----
                                Adabas operation normal

                                                                page 3 of 5

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF9----- PF12-----
Help          Exit      Refresh          -          +          FullView Menu  ←

```



Note: The following screens are only visible in a cluster environment.

Monitoring Adbas Sessions

```
21:07:32          ***** A D A B A S  BASIC  SERVICES *****          2016-12-05
DBID 1955          - System Status -          PACUS12
NucID: 1021

Cluster Nucleus
-----
WORK1 publishing blocks ..          0
WORK1 publishing I/Os ....          0
WORK1 publishing waits ...         0
Buffer flush V2 timeouts .          0

page 4 of 5

PF1---- PF2---- PF3----- PF4----- PF6----- PF7----- PF8----- PF9----- PF12----
Help      Exit      Refresh      -          +          FullView Menu  ↵
```

```
21:07:32          ***** A D A B A S  BASIC  SERVICES *****          2016-12-05
DBID 1955          - System Status -          PACUS12
NucID: 1021          Cluster WORK I/O Statistics
NucID      Read I/Os      Write I/Os      Nucid      Read I/Os      Write I/Os
-----
1021          1              0

page 5 of 5

PF1---- PF2---- PF3----- PF4----- PF6----- PF7----- PF8----- PF9----- PF12----
Help      Exit      Refresh      -          +          FullView Menu  ↵
```

Monitoring Thread Usage

Selecting **Thread Usage** (option **T**) on the **Interval Utilization** menu displays a table of all defined Adabas threads, the status of each, the command type currently in process in each active thread, and the number of commands processed by each thread in the current session.

The equivalent direct command is:

```
DISPLAY THREADUSAGE
```

The values shown on this screen are shown in compressed form. Each can display as a nine-digit value, with appropriate multiplier letters "k" (1000), "M" (1000000), "G" (1000000000), and "T" (1000000000000) (representing consecutive powers of 1000) if necessary.

If the value of a counter on these screens ever exceeds the space available for the statistic, a greater than symbol (>) appears as the multiplier letter.

```
20:59:55          ***** A D A B A S BASIC SERVICES *****          2015-05-01
DBID 1955          - Thread Usage -          PACUT12
NucID: 1021
```

Nr.	I Thread Status	I Command Type	I Wait Event	I Nr. CMDs
1	I Active	I Simple Cmd.	I	I 6,576
2	I Not active	I	I	I 103
3	I Not active	I	I	I 71,981,983 K
4	I Not active	I	I	I 5,792,340 M
5	I Not active	I	I	I 8,462,628 M
6	I Not active	I	I	I 0
7	I Not active	I	I	I 16,777,215 T
8	I Not active	I	I	I 16,777,215 >
9	I Not active	I	I	I 0
10	I Not active	I	I	I 0
11	I Not active	I	I	I 0
12	I Not active	I	I	I 0
13	I Not active	I	I	I 0
14	I Not active	I	I	I 0
15	I Not active	I	I	I 0

```
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF9----- PF12-----
Help          Exit      Refresh          Fullview Menu  ↵
```

Press the **Enter** key to scroll through the Thread Usage screens.

You can press **PF9** to see the actual values (without the multipliers) of the counters. A pop-up window appears showing the actual values aligned to the right. To return to compressed view, just press **Enter** again.

Thr	Command Counts
1	6,576
2	103
3	73,709,551,615
4	6,073,709,551,615
5	8,873,709,551,615
6	0
7	18,446,744,073,709,551,614
8	18,446,744,073,709,551,614
9	0
10	0
11	0
12	0
13	0
14	0
15	0
Enter -	
Continue	

Reviewing I/Os by Volume Serial Number

Selecting **I/O by Volser** (option **V**) on the **Interval Utilization** menu displays a table of the read and write I/Os performed by volume serial number on the I/O by Volser screen. It also shows the highest RABN on each volume.

The equivalent direct command is:

```
DISPLAY IQVOLSER
```

The I/O counts shown on this screen are shown in compressed form. Each can display as a nine-digit value, with appropriate multiplier letters "k" (1000), "M" (1000000), "G" (1000000000), and "T" (1000000000000), representing consecutive powers of 1000, if necessary.

Reviewing Work Status

Selecting **WORK Status** (option **W**) on the **Interval Utilization** menu displays the Work area sizes (in blocks) for the:

- data protection area (Work part 1; ADARUN LP parameter);
- work part 1B (Work part 1B; ADARUN CLUWORK1CACHE parameter);
- area used for intermediate ISN lists (Work part 2; ADARUN LWKP2 parameter);
- area used for resulting ISN lists (Work part 3);

The equivalent direct command is:

```
DISPLAY WORKSTATUS
```

```

21:01:15          ***** A D A B A S  BASIC  SERVICES  *****          2016-12-05
DBID 1955          -  WORK Status  -          PACUW02
NucID 1021

          W O R K  Dataset
+-----+
I  Protection Area          1000 Blks I
I-----I
I  Work Part 1B (CLUWORK1CACHE)          0 Blks I
I-----I
I  Intermediate ISN Area          176 Blks I
I-----I
I  Resulting ISN Area          9614 Blks I
I-----+
I  Distributed Transaction Processing Area          0 Blks I
+-----+

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit          Menu          ↵
    
```

If you have **DTP=RM** in your **ADARUN** parameter settings, and press **PF4** on the new screen, then the new screen **DTP Work Area** displays (shown below):

```

16:08:09          ***** A D A B A S  BASIC  SERVICES *****          2014-05-01
                  - DTP Work Area -                                PACUK02

                  Code      Service
                  -----
                  D        Display PET-status users
                  H        Display heuristically terminated users
                  R        Display DTP rabns
                  U        Work Part 4 usage
                  X        Force heuristic BT/ET
                  ?        Help
                  .        Exit
                  -----
Code ..... _
Selected User ....
Database ID ..... 1955 (WIS1955)

Command ==>
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help  Clear UID   Exit                                     Menu

```

The DTP Work Area menu performs the following functions:

Option	Function	Action
D	Display PET-status users	Displays the current environment of PET-status users. You can select one or more to display additional information.
H	Display heuristically terminated users	Displays a list of the heuristically terminated users. You can select one or more to display additional information.
R	Display DTP Rabns	Displays a list of allocated RABNs. You can select a user, display additional information, issue BT or ET, and display total RABNs for a user.
U	Work Part 4 Usage	Displays the breakdown of information of the Work Part 4.
X	Force Heuristic BT/ET	Issues a BT or ET for a selected user. Select the user through the "Display DTP RABNs" menu item.
---	PF2	Clears the selected user.

If you select Display PET-status users, the screen Display PET-Status Users displays (shown below):


```

16:40:12          ***** A D A B A S  BASIC  SERVICES *****          2014-05-05
DBID 1955          - Display PPT -          MACA022

NucID .. 1021      Active Nucleus, PLOG(s) not copied, CLOG(s) not copied
Image .. ZHST      All Sysplex Services Active

          Label Name          Dataset Name
          -----
          WORK1              RD.USAWIS.DB1955.WORKR1
          PLOGR1             RD.USAWIS.DB1955.PLOGR1
          PLOGR2             RD.USAWIS.DB1955.PLOGR2
          CLOGR1             RD.USAWIS.DB1955.CLOGR1
          CLOGR2             RD.USAWIS.DB1955.CLOGR2

PF1----- PF3----- PF4----- PF6----- PF7----- PF8----- PF9----- PF12-----
Help      Exit      Refresh  PrevPPT          NextPPT  Menu      ↵

```

Use the PF6 and PF9 fields to scroll between the PPTs.

Displaying zIIP Statistics

Selecting **zIIP Statistics** (option **Z**) on the **Interval Utilization** menu allows you to review zIIP statistics for the ongoing session. The **zIIP Statistics** screens display.



Note: This option is only available for selection when Adabas was started with ZIIP=YES.

Monitoring Adabas Sessions

```

15:00:06          ***** A D A B A S  BASIC  SERVICES *****          2018-04-04
DBID 1955          -  zIIP Statistics  -                               PACUZ02

Counts / Times                                                    zIIP mode SRB
-----
zIIP normalization factor .....                               10.97
Integrated inform. processor(zIIP).                             1
  zIIP SMT threads .....                                       1
General central processors (GCP) ..                             2

Total enclave CPU time .....                                0:00:23.455
  Enclave GCP CPU time .....                                0:00:11.058
  Enclave zIIP CPU time .....                               0:00:12.397
  Enclave zIIP CPU time(%) .....                            52.85

Eligible zIIP CPU time .....                               0:00:12.398
  Enclave zIIP CPU time .....                               0:00:12.397
  Eligible zIIP CPU time on GCP ....                        0:00:00.001
  Eligible zIIP CPU time on GCP(%) .                        0.00

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit       Refresh          +          Menu
  
```

```

15:00:06          ***** A D A B A S  BASIC  SERVICES *****          2018-04-04
DBID 1955          -  zIIP Statistics  -                               PACUZ02

Counts / Times                                                    -----
Switches into SRB mode .....                               60,138
Switches into TCB mode .....                               60,137
Parallel requests .....                                   15,039
  No free element for request .....                        0
  Parallel requests per TCB pause ..                       1.16

Extended statistics

Pause   SRB .....                                         15
Release SRB .....                                         0
Pause   TCB .....                                       12,864
Release TCB .....                                       12,878
Pause   for wait .....                                   86,358
Release from wait .....                                   86,961

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit       Refresh          -          +          Menu
  
```

```

15:00:06          ***** A D A B A S  BASIC  SERVICES *****          2018-04-04
DBID 1955          -  zIIP Statistics  -          PACUZ02

SRB/TCB Scheduling by type of work
-----
EXCPs                15040
Miscellaneous         65
Sequential writes    253
Timer services       119956

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit      Refresh          -          Menu          ↵

```

Replicator Management

The Replicator management screens are only visible if the Event Replicator for Adabas is installed and active. If the **V** option on the **Session Monitoring** menu is not highlighted, the Event Replicator is *not* installed and this option cannot be selected. For more detailed information concerning Replicator Management screens, refer to the Event Replicator for Adabas documentation.

Displaying Session Utilization

Selecting **Display session utilization** (option **W**) on the **Session Monitoring** menu displays the **Session Utilization** menu:

```

18:06:16          ***** A D A B A S BASIC SERVICES *****          2018-04-04
                   - Session Utilization -                               PACW002

                   Code  Service
                   -----
                   C    Command usage
                   F    File usage
                   H    High watermarks (pools/queues)
                   S    System status
                   T    Thread usage
                   Z    zIIP statistics
                   ?    Help
                   .    Exit
                   -----

Code ..... _
File Number .. 0
Database ID .. 1955   (WIS1955)           NucID .. 1021

Command ==>
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help      NextNuc  Exit                                     Menu

```

This menu provides access to command usage, file usage, high watermark, system status, and thread usage statistics for the ongoing session. If you elected to refresh these statistics during your Adabas session, the numbers presented in this area of Adabas Online System may be different than the interval statistics. Otherwise, they should be identical. For examples of the session utilization statistics that are collected and displayed, read the following sections:

- [Displaying Session Command Usage Statistics](#)
- [Displaying Session File Usage Statistics](#)
- [Displaying Session High Water Mark Statistics](#)
- [Displaying Session System Status Statistics](#)
- [Displaying Session Thread Usage Statistics](#)
- [Displaying Session zIIP Statistics](#)

Displaying Session Command Usage Statistics

Selecting **Command Usage** (option C) on the **Session Utilization** menu allows you to review command usage statistics for the ongoing session. The **Session Command Usage** screen displays.

```

18:06:37          ***** A D A B A S  BASIC  SERVICES *****          2014-06-30
DBID 1955          -  Session Command Usage  -          PACWC22
NucID 1021

Total Commands ..          3,058

CMD-Type I  Nr.  CMDs          I  Aver.  Dur.          CMD-Type I  Nr.  CMDs          I  Aver.  Dur.
-----
A1/4   I           0   I           4.565          BT      I           0   I
CL     I          15   I           C1      I           0   I
C3     I           0   I           C5      I           0   I
ET     I           0   I           E1/4   I           0   I
HI     I           0   I           LF      I           0   I
L1/4   I           0   I           L2/5   I           0   I
L3/6   I         1,000  I           L9      I          180   I          1.201
N1/2   I           0   I           OP      I          20    I          10.017
RC     I           710  I           RE      I           0   I
REST   I           500  I           RI      I           0   I
S1/4   I           549  I           S2      I           0   I
(Aver. Dur. - units of milliseconds)
Page 1 of 2

PF1----- PF2----- PF3----- PF4----- PF7----- PF8----- PF9----- PF12-----
Help          Exit      Refresh          +          Fullview Menu  ↵

```

This screen shows the number of times a command was issued during the session and the average duration of each command. The statistics are displayed in two sets of repeated columns, unless you press the PF9 key, when they are displayed in longer form.

You can scroll forward and backward between the screens of command statistics using the PF8 (forward) and PF7 (backward) keys.

Displaying Session File Usage Statistics

Selecting **File Usage** (option F) on the **Session Utilization** menu allows you to review file usage statistics for the ongoing session. The **Session File Usage** screen displays.

```
18:09:29          ***** A D A B A S BASIC SERVICES *****          2014-06-30
DBID 1955          - Session File Usage -          PACWF42
Nucid: 1021
  Fnr  Tot. Cnds          I      Fnr  Tot. Cnds          I
-----
    0          1,343 I      11          1,747 I

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help      Repos      Exit      Refresh  --          Menu      ↵
```

This screen shows the number of commands issued against a file during the session.

You can scroll forward and backward between the screens of file statistics using the PF8 (forward) and PF7 (backward) keys.

Displaying Session High Water Mark Statistics

Selecting **High watermarks** (option **H**) on the **Session Utilization** menu allows you to review high watermark (pool and queue) statistics for the ongoing session. The **Session High Watermarks** screens display.

```
18:09:55          ***** A D A B A S BASIC SERVICES *****          2014-06-30
DBID 1955          - Session High Watermarks -          PACWH22
NucID: 1021
```

Sel	Pool / Queue	I	Size	I	HW Used	%Used	I	Current	%Used
_	Attached Buffer(NAB)	I	409600	I	32768	8.0	I	0	0.0
_	Command Queue (NC)	I	3840	I	192	5.0	I	192	5.0
_	Unique DE Pool (DUQ)	I	50000	I	0	0.0	I	0	0.0
_	Format Pool (LFP)	I	150000	I	0	0.0	I	6528	4.3
_	Hold Queue (NH)	I	41600	I	0	0.0	I	0	0.0
_	PLOG Prot buf(NPLOGB)	I	1	I	1	100.0	I	0	0.0
_	Redo Pool (LRDP)	I	80000	I	28	0.0	I	0	0.0
_	Replication Pool(LRP)	I	100000	I	0	0.0	I	0	0.0
_	Security Pool (LCP)	I	10000	I	0	0.0	I	0	0.0
_	ISN List Tab (LI)	I	360000	I	0	0.0	I	0	0.0
_	Seq. Cmd. Table(LQ)	I	20000	I	0	0.0	I	0	0.0
_	User Queue (NU)	I	74256	I	1820	2.4	I	1456	1.9
_	UQ File List (UQF)	I	19584	I	216	1.1	I	144	0.7

Page 1 of 2

```
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit      Refresh          +          Menu          ↵
```

```
20:54:19          ***** A D A B A S BASIC SERVICES *****          2016-12-05
DBID 1955          - Session High Watermarks -          PACUH22
NucID: 1021
```

Sel	Pool / Queue	I	Size	I	HW Used	%Used	I	Current	%Used
_	Work Prt1 Prot bf(NW)	I	1	I	1	100.0	I	0	0.0
_	Work Pool (LWP)	I	1500000	I	53364	3.5	I	0	0.0
_	Work Part 1 (LP)	I	1000	I	1	0.1	I	0	0.0
_	Work Part 2 (LWKP2)	I	176	I	0	0.0	I	0	0.0
_	Work Part 3 (WORKPT3)	I	9614	I	0	0.0	I	0	0.0
_	ATM Trans. IDs (XID)	I	0	I	0	0.0	I	0	0.0
_	Work Part 1B(CLUWOR.)	I	0	I	0	0.0	I	0	0.0
		I		I			I		
		I		I			I		
		I		I			I		
		I		I			I		
		I		I			I		
		I		I			I		

Page 2 of 2

```
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit      Refresh          -          Menu          ↵
```

This screen shows the size, amount used, percentage used, current usage, and current percentage used of each pool, queue, and Work part. T

You can scroll forward and backward between the screens of high watermark statistics using the PF8 (forward) and PF7 (backward) keys.

Displaying Session System Status Statistics

Selecting **System status** (option S) on the **Session Utilization** menu allows you to review system status usage statistics for the ongoing session. The **Session System Status** screens display.

```

18:10:32          ***** A D A B A S BASIC SERVICES *****          2014-06-30
DBID 1955          - Session System Status -          PACWS12
NucID: 1021

Physical      Reads          Writes          Call Distribution
-----
ASSO          1,310           28             No. of HQEs active ..... 0
DATA          2,025           7              No. of UQEs in User Queue .. 1
WORK          2               33             No. of CQEs waiting in CQ .. 0
PLOG          6               24             No. of PLOG switches ..... 0
CLOG          20              4              No. of CLOGs ..... 2
               20              4              No. of PLOGs ..... 2
PLOG protection blks .          23
PLOG protection I/Os .          23             Format translations ..... 39
WORK1 protection blks.          33             Format overwrites ..... 0
WORK1 protection I/Os.          33             Auto-restarts ..... 0
               12,292         Throw-backs for ISN ..... 0
Logical reads .....
Buffer efficiency ....          3.6             Throw-backs for Space.... 0

                                           page 1 of 3

PF1---- PF2---- PF3----- PF4----- PF6----- PF7----- PF8----- PF9----- PF12-----
Help          Exit      Refresh          +          FullView Menu ←
    
```

```
18:10:32      ***** A D A B A S  BASIC  SERVICES *****      2014-06-30
DBID 1955          -  Session System Status  -                      PACWS12
NucID: 1021
```

Call Distribution		Commands	
User sessions	25	Remote	0
Buffer flushes	7	Local	2,612
Flush phases	7	Internal	505
Blocks flushed	28	Operator	0
Flush I/Os	28	Total	3,117

Flush Requests Returned		Time Elapsed	
Immediately	0	Duration	0 day, 07:29:54
After logical flush ..	0	Wait-time ...	0 day, 07:29:52
After entire flush ...	9	CPU time	0 day, 00:00:04

page 2 of 3

```
PF1---- PF2---- PF3----- PF4----- PF6----- PF7----- PF8----- PF9----- PF12----
Help          Exit      Refresh          -          +          FullView Menu
0                                     02,001      ↵
```

```
18:10:32      ***** A D A B A S  BASIC  SERVICES *****      2014-06-30
DBID 1955          -  Session System Status  -                      PACWS12
NucID: 1021
```

Nucleus Status Flags

Adabas operation normal

page 3 of 3

```
PF1---- PF2---- PF3----- PF4----- PF6----- PF7----- PF8----- PF9----- PF12----
Help          Exit      Refresh          -          +          FullView Menu      ↵
```

These screens show various system statistics for the session and span three screens, with statistics on some of the screens displayed in two sets of repeated columns. If you press the PF9 key, they are displayed in a single column,

You can scroll forward and backward between the screens of system status statistics using the PF8 (forward) and PF7 (backward) keys.

Displaying Session Thread Usage Statistics

Selecting **Thread usage** (option T) on the **Session Utilization** menu allows you to review thread usage statistics for the ongoing session. The **Session Thread Usage** screens display.

```

18:12:54          ***** A D A B A S  BASIC  SERVICES *****          2014-06-30
DBID 1955          -   Session Thread Usage   -          PACWT12
NucID 1021
Nr. I Thread Status      I Command Type      I Wait Event          I Nr. CMDs
-----
 1 I Active                I Simple Cmd.        I                      I      3,155
 2 I Not active            I                    I                      I         6
 3 I Not active            I                    I                      I         0
 4 I Not active            I                    I                      I         0
 5 I Not active            I                    I                      I         0
 6 I Not active            I                    I                      I         0
 7 I Not active            I                    I                      I         0
 8 I Not active            I                    I                      I         0
 9 I Not active            I                    I                      I         0
10 I Not active            I                    I                      I         0
11 I Not active            I                    I                      I         0
12 I Not active            I                    I                      I         0
13 I Not active            I                    I                      I         0
14 I Not active            I                    I                      I         0
15 I Not active            I                    I                      I         0

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF9----- PF12-----
Help                Exit      Refresh          Fullview Menu      ↵
    
```

This screen shows the threads in numerical order and indicates the thread status, command type, wait event, and number of commands processed by the thread in the session. To see a smaller, more summarized view of the thread usage statistics, press the PF9 key. A popup window appears listing only the thread number and number of commands processed by the thread in the session.

Press ENTER to see the next screen of threads. When you press ENTER on the last screen, the **Session Utilization** menu appears again.

Displaying Session zIIP Statistics

Selecting **zIIP Statistics** (option **Z**) on the **Session Utilization** menu allows you to review zIIP statistics for the ongoing session. The **zIIP Statistics** screens display.



Note: This option is only available for selection when Adabas was started with ZIIP=YES.

```

15:46:59          ***** A D A B A S  BASIC  SERVICES  *****          2018-04-04
DBID 1955          -  zIIP Statistics  -          PACWZ02

Counts / Times Session                                     zIIP mode SRB
-----
zIIP normalization factor .....                          10.97
Integrated inform. processor(zIIP).                        1
zIIP SMT threads .....                                    1
General central processors (GCP) ..                        2

Total enclave CPU time .....                              0:00:23.558
Enclave GCP CPU time .....                               0:00:11.105
Enclave zIIP CPU time .....                              0:00:12.453
Enclave zIIP CPU time(%) .....                           52.86

Eligible zIIP CPU time .....                             0:00:12.454
Enclave zIIP CPU time .....                              0:00:12.453
Eligible zIIP CPU time on GCP ....                       0:00:00.001
Eligible zIIP CPU time on GCP(%) .                       0.00

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit      Refresh          +          Menu

```

Monitoring Adabas Sessions

```
15:46:59          ***** A D A B A S  BASIC  SERVICES *****          2018-04-04
DBID 1955          -  zIIP Statistics  -                               PACWZ02
```

Counts / Times Session

```
-----
Switches into SRB mode .....                60,420
Switches into TCB mode .....                60,419
Parallel requests .....                    15,083
  No free element for request .....                0
  Parallel requests per TCB pause ..            1.16
```

Extended statistics

```
Pause  SRB .....                            15
Release SRB .....                            0
Pause  TCB .....                           12,907
Release TCB .....                           12,921
Pause  for wait .....                       86,722
Release from wait .....                     87,325
```

```
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help                Exit      Refresh          -         +         Menu
```

```
15:46:59          ***** A D A B A S  BASIC  SERVICES *****          2018-04-04
DBID 1955          -  zIIP Statistics  -                               PACWZ02
```

SRB/TCB Scheduling by type of work Session

```
-----
EXCPs                15082
Miscellaneous         67
Sequential writes    255
Timer services       120518
```

```
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help                Exit      Refresh          -         +         Menu
```

Monitoring Cluster Usage



Note: This option is only active in an Adabas nucleus cluster environment.

Selecting **Cluster usage** (option **X**) on the **Interval Utilization** menu displays nucleus cluster statistics that are equivalent to those displayed using the DXCACHE, DXLOCK, and DXFILE operator commands. These statistics are made available through selections on the **Cluster Usage** menu. For more information, read the *Adabas Cluster Services* or *Adabas Parallel Services* documentation.

The equivalent direct command is:

```
DISPLAY CLUSTERSTATUS
```

```
14:05:08          ***** A D A B A S BASIC SERVICES *****          2014-06-19
                   - Cluster Usage -                               PACUX02

                   Code      Service
                   ----      -
                   C         Cache statistics
                   F         File statistics
                   L         Lock statistics
                   M         Message statistics
                   ?         Help
                   .         Exit
                   ----      -

Code ..... _
File Number .. 0
Database ID .. 1955 (WIS1955)          NucID .. 1021

Command ==>
PF1----- PF2----- PF3----- PF4----- PF6----- PF9----- PF10----- PF12-----
Help      NextNuc  Exit                               Fuse      Flist      Menu
```

This section covers the following topics:

- [Cache Statistics](#)
- [File Statistics](#)
- [Lock Statistics](#)

- Message Statistics

Cache Statistics

Choosing **Cache Statistics** (option C) on the **Cluster Usage** menu displays the **Cache Statistics** menu:

```

10:47:57          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
                  - Cache Statistics -                               PACUX12

      Code      Service
      ----      -
      K      Cast-out / Directory
      P      Publishing requests
      X      Individual cache blocks
      .      Exit
      ?      Help
      ----      -

Code ..... _
Database ID .. 1955   (WIS1955)           NucID .. 1021

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help       Exit       Refresh      Menu       ↵
    
```

On all subscreens of cache statistics, displayed counters may include a unit code, with the following possible values:

Unit Code	The total shown is in . . .
blank	bytes
k	1000 bytes
M	1,000,000 bytes
G	1,000,000,000 bytes
T	1,000,000,000,000 bytes

If a value has a unit code shown, it has been divided by the unit measurement to convert it to bytes, showing the significant digits to nine places with no decimal point.

Press PF9 to see the entire value. This value is the exact count up to 20 digits in length.

- Cast-out / Directory

- Publishing Requests
- All Cache Blocks

Cast-out / Directory

Choosing **Cast-out / Directory** (option **K**) on the **Cache Statistics** menu display the following:

```

10:47:57          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
DBID  1955          - Cast-out / Directory -          PACUX12
NucID 1021

      Cast-out Directory Reads          Directory Reads
      -----
Total .....          170          Total .....          1
  Sync .....          107          Sync .....          0
  Async ....          63          Async ....          1

      Unlock Cast-out Calls
      -----
Total .....          85
  Sync .....          0
  Async ....          85

PF1----- PF2----- PF3----- PF4----- PF7----- PF8----- PF9----- PF12-----
Help          Exit      Refresh          Detail      Menu      ↵

```

Publishing Requests

Choosing **Publishing Requests** (option **P**) on the **Cache Statistics** menu displays the following:

```

10:49:46          ***** A D A B A S BASIC SERVICES *****          2014-05-02
DBID 1955          - Publishing Requests -          PACUX12
NucID 1021

          Publishing Request Category
          -----
          Update sync .....          85
          BT or CL or ET ....          2
          Redo threshold ....          0
          Full bufferpool ...          0
          All blocks .....          86
          Specific RABN .....          0
          File DS blocks ....          0
          All DSST blocks ...          85
          File NI blocks ....          0

PF1----- PF2----- PF3----- PF4----- PF7----- PF8----- PF9----- PF12-----
Help       Exit       Refresh      Detail      Menu       ↵
    
```

All Cache Blocks

Choosing **Individual Cache Blocks** (option **X**) on the **Cache Statistics** menu displays the following:

```

10:50:17          ***** A D A B A S BASIC SERVICES *****          2014-05-02
DBID 1955          - All Cache Blocks -          PACUX12
NucID 1021

          Reads                               Writes
          -----                               -----
          Total .....          6,378          Total .....          347
          Sync .....          963          Sync .....          153
          Async .....          5,415          Async .....          194

          In cache .....          85          Written .....          347
          Not in cache ..          6,293          Not written .....          0
          Struc. full ...          0          Struc. full .....          0

          Cast-out Reads                         Other
          -----                               -----
          Total .....          340          Validates .....          37,896
          Sync .....          340          Invalid .....          0
          Async .....          0          Deletes .....          0
                                   Timeouts .....          0
                                   Redo processes .....          0

PF1----- PF2----- PF3----- PF4----- PF7----- PF8----- PF9----- PF12-----
Help       Repos      Exit       Refresh   PrevBlk   NxtBlk    Detail      Menu       ↵
    
```

Use PF7 and PF8 to scroll through the cache blocks; use PF2 to reposition.

Statistics are displayed for the following:

- All cache blocks;
- Address converter (AC) cache blocks;
- Data Storage (DS) cache blocks;
- Data Storage space table (DSST) cache blocks;
- File control block (FCB) cache blocks;
- Normal index (NI) cache blocks;
- Upper index (UI) cache blocks.
- Work cache blocks.

File Statistics

Choosing **File Statistics** (option **F**) on the **Cluster Usage** menu for file 25 displays the following screen:

```

10:51:09          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
DBID 1955          - File 12 Statistics -          PACUX22
NucID 1021
  Reads
-----
Total .....          86          Writes
Sync .....          4          Total .....          0
Async .....         82          Sync .....          0
                                     Async .....          0
                                     In cache .....          0
                                     Not in cache ..         86          Written .....          0
                                     Struc. full ...          0          Not written .....          0
                                                                         Struc. full .....          0
Cast-out Reads
-----
Total .....          0          Other
Sync .....          0          Validates .....         1,502
Async .....          0          Invalid .....          0
                                     Deletes .....          0
                                     Timeouts .....          0
                                     Redo processes .....          0
PF1----- PF2----- PF3----- PF4----- PF7----- PF8----- PF9----- PF12-----
Help      Repos      Exit      Refresh      Detail      Menu      ↵

```

Lock Statistics

Choosing **Lock Statistics** (option L) on the **Cluster Usage** menu displays the **Lock Statistics** menu:

```

10:51:28          ***** A D A B A S BASIC SERVICES *****          2014-05-02
                    - Lock Statistics -                               PACUX39

Code  Service                Code  Service                Code  Service
-----
A  Buffer flush                L  Global ET sync        W  Replicat handshake
B  Cancel                     M  Glbl upd cmd sync     X  Security
C  Checkpoint                 N  Hold ISN              Y  Spats
D  Container                  O  LOB tracker           Z  Unique descriptor
E  Delta Save (DSF)          P  Net-wrk DBID asgmt   1  User
F  Distributed tranID        Q  New-Data-RABN        2  Wkpt4 RABN index
G  ETID                       R  Online save          3  Wkpt4 PET user tbl
H  File-lock-table           S  Parameter             .  Exit
I  Format-addr-conver        T  Record read          ?  Help
J  Free space table          U  Recovery (online)
K  GCB                        V  Recovery log(RLOG)

-----
Code ..... _
Database ID .. 1955 (WIS1955)          NucID .. 1021

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit          Refresh          Menu          ↵
    
```

Each of the options on the **Lock Statistics** menu displays statistics for a particular lock. For each lock, the screen displays obtain-and-release information about the various types of that lock that are currently in use by a cluster nucleus:

- The system may obtain locks conditionally or unconditionally, synchronously or asynchronously. A conditional request for a lock may be granted or rejected.
- Releases may be issued synchronously or asynchronously.
- The system may alter locks conditionally or unconditionally, synchronously or asynchronously, A conditional request to alter a lock may be granted or rejected. An unconditional request to alter a lock may be deadlocked and rejected.

For example, choosing **Hold ISN Lock** (option N) on the **Lock Statistics** menu displays the Hold ISN Lock screen:

```

10:51:28          ***** A D A B A S BASIC SERVICES *****          2014-05-02
DBID 1955          - Hold ISN Lock -          PACUX39
NucID 1021

Obtains          Alters
-----          -----
Conditional ....          86          Conditional .....          0
  Granted .....          86          Granted .....          0
  Rejected ....          0          Rejected .....          0
Unconditional ..          0          Unconditional .....          0
          Rejected-deadlock ..          0

Sync .....          3          Sync .....          0
Async .....          83          Async .....          0

Releases
-----
Issued .....          86
  Sync .....          8
  Async .....          78

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help   Repos   Exit   Refresh           PrevLok   NxtLok   Menu           ↵

```

Use PF7 and PF8 to scroll through the lock displays; use PF2 to reposition to a different lock display.

Message Statistics

Choosing **Message Statistics** (option C) on the **Cluster Usage** menu displays the **Message Statistics** screens. There are two message statistics screens; use PF8 and PF7 scroll forward and backward between them.



Note: These screens display the same information you would see if you entered the Adabas DXMSG command.

Monitoring Adabas Sessions

14:08:50 ***** A D A B A S BASIC SERVICES ***** 2014-06-19
 DBid 1955 - Message Statistics - PACUX50
 Nucid 1021

Message Control Block Statistics		Statistics for ACMD-type messages	
Allocated	25,094	Messages sent	183,378
Used	4	Messages arrived ...	146,411
Total	329,789	Messages accepted ..	146,411
		Replies sent	146,358

Number of message type areas ... 1
 Number of transport areas 1
 Page 1 of 2

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
 Help NextNuc Exit + Menu

14:13:55 ***** A D A B A S BASIC SERVICES ***** 2014-06-19
 DBid 1955 - Message Statistics - PACUX50
 Nucid 1021

Statistics for SMM transport messages

	Msgs subject MXMSG	Msgs not subj. MXMSG	Total all Msgs
Minimum ..	0.000011	0.000011	0.000011
Maximum ..	12.807110	53.605695	53.605695
Mean	0.021852	0.069410	0.033985
Std Dev ..	0.227699	1.436602	0.194475

Msg Count		4,292	1,470	5,762
> 1000 s	0%	0	0	0
> 100 s	0%	0	0	0
> 10 s	0%	1	1	2
> 1 s	0%	3	3	6
> 100 ms	2%	81	21	102
> 10 ms	24%	1,015	483	1,498
> 1 ms	22%	942	168	1,110
> 100 us	33%	1,418	549	1,967
<= 100 us	19%	832	245	1,077

Page 2 of 2

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
 Help NextNuc Exit + Menu

Displaying Maintenance Levels



Note: This function is only available for Adabas version 8 or above databases.

Selecting **Display Maintenance Levels** (option **Z**) on the **Session Monitoring** menu displays information about the Adabas nucleus modules:

```

10:52:25          ***** A D A B A S BASIC SERVICES *****          2014-05-02
DBID 1955          - Display Maintenance Levels -                      PACZ002
NucID .. 1021

Select Module Name: _____
-----
ADARUN  RUNMVS  Date 2013-09-17, Version 8.3, SP 8
          RUNIND  Date 2014-03-21, Version 8.3, SP 8
ADANCX          Date 2014-04-21, Version 8.3, SP 8
ADAXCF          Date 2012-04-19, Version 8.3, SP 8
ADAXEC          Date 2012-10-11, Version 8.3, SP 8
ADAXEL          Date 2013-10-21, Version 8.3, SP 8
ADACLU          Date 2014-04-15, Version 8.3, SP 8
ADAMXI          Date 2013-12-10, Version 8.3, SP 8
ADAMIM          Date 2014-03-21, Version 8.3, SP 8
ADARVU          Date 2014-03-21, Version 8.3, SP 8
ADACLX          Date 2013-12-30, Version 8.3, SP 8
ADARMT          Date 2014-03-19, Version 8.3, SP 8

Command ==>
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit          --          -          +          Menu          ↵

```

Maintenance levels for each module are displayed. Any zaps that are applied to the module are also listed.

The list of modules can be limited by entering a specific module name in the **Select Module Name** field at the top of the screen. An asterisk (*) can also be used as a wildcard value in this field. For example, specifying "ADARUN" displays information for the ADARUN module only. Specifying "ADAR*" lists all modules with names that begin with "ADAR", which would include ADARUN as well as ADARVU and other modules.

5 Maintaining Checkpoints

- Listing Checkpoints 102
- Deleting Checkpoints 104

Selecting **Checkpoint Maintenance** (option C) from the Adabas Online System **Main Menu** invokes the **Checkpoint Maintenance** menu:

```

12:31:41          ***** A D A B A S BASIC SERVICES *****          2014-05-02
                   - Checkpoint Maintenance -                          PCP0002

                                Code      Service
                                -----
                                C          List checkpoints
                                D          Delete checkpoints
                                ?          Help
                                .          Exit
                                -----

Code ..... _
Date(YYYY-MM-DD) . 0000-00-00
Ext. CP-list ..... N
Checkpoint Name .. ALL
Database ID ..... 1955   (WIS1955)

Command ==>
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help           Exit           Menu           ↵
    
```

Using the AOS checkpoint maintenance environment, you can perform the following functions, accessible by menu option:

Option	Function
C	<i>Listing Checkpoints</i> lists checkpoints currently in the checkpoint file.
D	<i>Deleting Checkpoints</i> allows you to remove all checkpoint file entries up to a specified date.

Listing Checkpoints

Selecting **List checkpoints** (option C) on the **Checkpoint Maintenance** menu lists checkpoints currently in the checkpoint file.

The result can be either a basic or an extended list, depending on the setting of the `External CP-list` field, which can be used to override the `CPEXLIST` operating control parameter.

You can start the list of checkpoints on a particular day by entering the date in the `Date` field in exactly the format shown.

You can specify the database for which the checkpoint list is to be written.

You can restrict the list to a particular checkpoint name by changing the ALL designation in the Checkpoint Name field to one of the following:

Type	Description
SYNC	nucleus initialization
SYNF	user open EXF
SYNP	utility, without nucleus
SYNS	ADARES
SYNV	volume ID change
SYNX	utility
SYN1	ADASAV DB begin
SYN2	ADASAV DB end
SYN4	ADASAV file begin
SYN5	ADASAV file end

For more information about checkpoint names, refer to your *Adabas Utilities* documentation.

The following screen displays a normal checkpoint list:

```

12:33:25          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
DBID 1955          - List Checkpoints -          PCPC012

  CP   CP   Date      Time          PLOG      Block      Vol/Ser      User Job Name
  Name Type                                Number      Number      Number      Type
  ----
SYNC  01   2010-12-14 11:29:34
SYNS  5B   2010-12-14 11:29:34
SYNP  07   2010-12-14 11:30:19          2          1      DUAL
SYNC  01   2010-12-14 11:30:45          2          2      DUAL
SYNS  61   2010-12-14 11:32:40          2          417     DUAL
SYNS  5B   2010-12-14 11:42:43          2          29341   DUAL      EXU  ADAEND
SYNC  01   2010-12-14 11:43:26          3          1      DUAL
SYNS  60   2010-12-14 16:05:31          3          1524   DUAL
SYNS  60   2010-12-15 10:08:02          3          1525   DUAL
SYNS  60   2010-12-15 11:53:37          3          1526   DUAL
SYNS  60   2010-12-15 12:56:37          3          1527   DUAL
SYNS  60   2010-12-15 13:59:37          3          1528   DUAL
SYNS  60   2010-12-15 15:02:37          3          1529   DUAL
SYNS  60   2010-12-15 16:05:37          3          1530   DUAL
SYNS  60   2010-12-15 17:08:42          3          1531   DUAL
PF1----- PF2----- PF3----- PF4----- PF6----- PF7 ----- PF8----- PF12-----
Help          Exit          Top          -          +          Menu          ↵
  
```

You can get an extended checkpoint list by setting the **Ext. CP-list** field to "Y" on the **Checkpoint Maintenance** menu. The following screen illustrates an extended checkpoint list providing additional information about each checkpoint:

Maintaining Checkpoints

```

12:34:40          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
DBID 1955          - List Checkpoints -          PCPC012

  CP   CP   Date      Time      PLOG      Block      Vol/Ser      User Job Name
  Name Type                                Number      Number      Number      Type
-----
SYNC  01   2010-12-14 11:29:34                                USAWISCR
      SESSION OPEN          IGNDIB = N , FORCE = N
SYNS  5B   2010-12-14 11:29:34                                EXU  ADAEND
      REFRESH STATS
SYNP  07   2010-12-14 11:30:19          2          1   DUAL          USAWISRE
      RESTORE FILE(S)      1, 3, 6, 7, 9, 10, 11, 12, 13, 20, 21, 22,
SYNC  01   2010-12-14 11:30:45          2          2   DUAL          USAWISRP
      SESSION OPEN          IGNDIB = N , FORCE = N , SESSION = 2
SYNS  61   2010-12-14 11:32:40          2          417  DUAL          ADABAS
      FILE SPACE ALLOC     FNR=11,NI,FROM=16220,TO=16528
SYNS  5B   2010-12-14 11:42:43          2          29341 DUAL          EXU  ADAEND
      REFRESH STATS
SYNC  01   2010-12-14 11:43:26          3          1   DUAL          USAWISRP
      SESSION OPEN          IGNDIB = N , FORCE = N , SESSION = 3
SYNS  60   2010-12-14 16:05:31          3          1524 DUAL          ADABAS
PF1----- PF2----- PF3----- PF4----- PF6----- PF7 ----- PF8----- PF12-----
Help                Exit                Top          -          +          Menu          ↵

```

Deleting Checkpoints

You can remove all checkpoint file entries up to the date you specify in the `Date` field by selecting **Delete checkpoints** (option **D**) on the **Checkpoint Maintenance** menu. The following screen appears:

```
12:36:09          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
DBID 1955          -  Delete Checkpoints  -                               PCPD002
```

All checkpoint entries up to .. 2014-05-02 (YYYY-MM-DD)
will be deleted.

Confirm by pressing the 'ENTER' key or
modify the date and then press 'ENTER'.

```
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help                Exit                Menu                ↵
```


6 Maintaining Files

▪ Defining or Modifying the FDT	109
▪ Releasing a Descriptor	120
▪ Deleting an Adabas File	122
▪ Defining a New File	123
▪ Logically Deleting or Undeleting a Descriptor	125
▪ Modifying File Parameters	127
▪ Reordering a File Online	131
▪ Refreshing a File to Empty Status	133
▪ Allocating or Deallocating File Space	134
▪ Maintaining Expanded Files	135

Selecting **File Maintenance** (option **F**) from the Adabas Online System **Main Menu** invokes the **File Maintenance** menu:

```

12:37:27          ***** A D A B A S BASIC SERVICES *****          2014-05-02
                    - File Maintenance -                               PFL0004

Code  Service                                           Code  Service
-----
C   Define/modify FDT                                  M   Modify file parameters
D   Release descriptor                                O   Reorder file online
E   Delete existing file                              R   Refresh file to empty status
F   Define new file                                   S   Allocate/deallocate file space
L   Logically delete/undelet descriptor              X   Maintain expanded files
?   Help                                             .   Exit
-----

Code ..... _
File No ..... 0      Descriptor Name .. ___
Database ID .. 1955  (WIS1955)

Command ==>
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit          Menu
0              14,025      ←
    
```

Options **C** (Define/modify FDT) and **X** (Maintain expanded files) on this menu display additional menus. The other file maintenance options require you to enter a valid file number and database ID. Option **D** (Release descriptor) also requires that you specify the name of the descriptor to be released.

From the **File Maintenance** menu, you can perform any of the following functions, selectable by menu option:

Option	Function
C	<i>Defining or Modifying the FDT</i> allows you to change the length of a field; add a field to a file; create a new field definition table (FDT); or create a special descriptor table (SDT).
D	<i>Releasing a Descriptor</i> allows you to release a field from descriptor status by freeing the specified field's inverted list in the Associator.
E	<i>Deleting an Adabas File</i> allows you to free extents used by an existing Adabas file.
F	<i>Defining a New File</i> allows you to define a new database file for which an FDT has already been created.
L	<i>Logically Deleting or Undeleting a Descriptor</i> allows you to logically delete or undelete a descriptor field.

Option	Function
M	<i>Modifying File Parameters</i> allows you to modify the padding factor, the maximum compressed record length, file number, file name, extent allocation for NI/UI/AC/DS, ISN reuse, and DS reuse.
O	<i>Reordering a File Online</i> allows you to start a process to reorder the Associator, Data Storage, or the entire file.
R	<i>Refreshing a File to Empty Status</i> allows you to delete all file records and assign a single extent to each file component.
S	<i>Allocating or Deallocating File Space</i> allows you to create or remove extents for the address converter, normal and upper index, and Data Storage of a file.
X	<i>Maintaining Expanded Files</i> allows you to insert or remove a component file into/from an expanded file chain.

Defining or Modifying the FDT

Selecting **Define/Modify FDT** (option C) on the **File Maintenance** menu displays the **FDT/SDT Definition / Modification** menu:

```

12:37:59          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
                -  FDT/SDT Definition / Modification  -                PFLC004

Code  Service                                Code  Service
-----
  A   Add new field(s)                        I   Online invert
  C   Change field parameters                 S   Define/add SDT
  D   Define new FDT                          U   Release UQ from descriptor
  F   Delete field from FDT                  ?   Help
  G   Undelete field from FDT                .   Exit
-----

Code ..... _
File No. ....
Field Name ... _
File Password.
Database ID .. 1955  (WIS1955)

Command ==>
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help      Def. File Exit                                     Menu      ←

```

This section covers the following topics:

- [Adding One or More Fields](#)
- [Changing Field Parameters](#)

- Defining a New Field Definition Table (FDT)
- Deleting a Field from the FDT
- Undeleting a Field from the FDT
- Inverting a File Online
- Defining a Special Descriptor Table (SDT)
- Releasing the UQ Option from a Descriptor

Adding One or More Fields

Selecting **Add New Field(s)** (option **A**) on the **FDT/SDT Definition / Modification** allows you to add one or more fields to an existing Adabas file.

The **Add New Field(s)** function corresponds to the Adabas ADADBS NEWFIELD utility function. The equivalent direct command is:

```
ADD FIELD
```

➤ **To add a new field definition to the field definition table (FDT) of an existing file:**

- 1 In the `Code` field, select option **A** (add new fields) on the **FDT/SDT Definition / Modification** menu.
- 2 Specify the number of the existing file in the `File No` field.
- 3 Specify a unique two-character field name that is not currently being used by the specified file in the `Field Name` field.
- 4 Press `Enter`.



Note: You can view the FDT of the existing file by selecting option **R**, *Database Report* from the Adabas Online System **Main Menu**.

An Add New Field(s) screen similar to the following is displayed providing input fields for defining a new field:

```

12:41:36          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
DBID 1955          -  Add New Field(s)  -          PFLCA22

File = 1          (EMPLOYEES)          In Parallel .. YES

Enter Password if file is security protected ...

Level | Name | Length | Format | Options          | DT and SY fields
-----|-----|-----|-----|-----|-----|-----
___ I ___ I
___ I ___ I ___ I ___ I ___ I ___ I ___ I ___ I ___ I
___ I ___ I ___ I ___ I ___ I ___ I ___ I ___ I ___ I
___ I ___ I ___ I ___ I ___ I ___ I ___ I ___ I ___ I
___ I ___ I ___ I ___ I ___ I ___ I ___ I ___ I ___ I
___ I ___ I ___ I ___ I ___ I ___ I ___ I ___ I ___ I
___ I ___ I ___ I ___ I ___ I ___ I ___ I ___ I ___ I
___ I ___ I ___ I ___ I ___ I ___ I ___ I ___ I ___ I
___ I ___ I ___ I ___ I ___ I ___ I ___ I ___ I ___ I
___ I ___ I ___ I ___ I ___ I ___ I ___ I ___ I ___ I
Continue: _

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help                Exit                Menu

```

- Specify the field level, name, length, format and any appropriate field options in the appropriate fields on the Add New Field(s) screen. For complete information on defining new fields, refer to the description of field definition statements in your Adabas ADACMP utility documentation.

If the file is password-protected, be sure to supply the password in the appropriate place at the top of the screen.



Caution: The `In Parallel` field allows you to specify whether processing should continue against a file while the function you have selected modifies the file. Specify "YES" to allow file processing to continue; specify "NO" to give Adabas exclusive file control while performing the function. With this option set to "YES", Adabas performs the function while all applications executing against the file are temporarily quiesced and suspended. File integrity is always maintained. For this reason, your applications that are executing against the file may experience difficulty. Please maintain an awareness of the impact on your environment and the consequences of performing your selected functions against a file when using this option. With this option set to "NO" (the default), Adabas requires exclusive file control (that is, no applications can be executing against the file) when performing the function.

The `DT and SY fields` area can be used to specify a valid date-time edit mask for binary, packed, or unpacked fields. Valid edit masks are: `DATE`, `TIME`, `DATETIME`, `TIMESTAMP`, `NATDATE`, `NATTIME`, `UNIXTIME`, and `XTIMESTAMP`. For complete information about these edit masks, refer to your Adabas documentation.

Changing Field Parameters

Selecting **Change Field Parameters** (option C) on the **FDT/SDT Definition / Modification** allows you to change the parameters of an existing field in an Adabas file.

This function corresponds to the Adabas utility function ADADBS CHANGE. The equivalent direct command is:

```
CHANGE FIELD file-number field-name
```

➤ **To change the parameters of an existing field in an existing file:**

- 1 In the `Code` field, select option **C** (change field parameters) on the **FDT/SDT Definition / Modification** menu.
- 2 Specify the number of the existing file in the `File No` field.
- 3 Specify the two-character field name of the field to be changed in the `Field Name` field.



Note: You can view the FDT of the existing file by selecting option **R**, *Database Report* from the Adabas Online System **Main Menu**.

- 4 Press Enter.

The Change Field Parameters screen appears.

```

20:34:13          ***** A D A B A S  BASIC  SERVICES  *****          2018-07-17
DBID 1955          -  Change Field Parameters  -          PFLCC32

Enter New Field Length or Option:

File ..... 102
File Name ..... TEST-102
Field Name ..... YF

Field Format ... A
Field Length ...
Field Option ... _

In Parallel .... NO
File Password ..

Change Field Option:
NB .... NO
NC .... NO
NN .... NO
NU .... NO
NV .... YES

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit          Rel UQ          Menu
    
```


- the standard length of an Adabas field. To do this, enter the new value in the `Field Length` field.
- a normal alphanumeric (A) field to a long-alpha (LA) field. To do this, enter "LA" in the `Field Option` field (if it appears on the screen).
- the default field format from unpacked (U) to packed(P). To do this, overwrite the "U" in the `Field Format` field with "P".

An elementary field defined as format "U" can only be changed to "P" if the field:

- has not been defined with the field option "FI" (fixed storage length);
 - is not the parent of a sub-/super-/hyperdescriptor; and
 - is not within an expanded file chain.
- the edit mask for a date-time field. To do this, change the value in the `DT= editmask` field (if it appears on the screen). Valid edit masks are: DATE, TIME, DATETIME, TIMESTAMP, NATDATE, NATTIME, UNIXTIME, and XTIMESTAMP. For complete information about these edit masks, refer to your Adabas documentation.
 - the setting of NB, NC, NN, NU, and NV, according to the allowed settings
 - NU and NC cannot be set at the same time, but a change from one to the other is possible.
 - If NC is set, existing records' empty values will appear as null values, and for a new record, a value will be suppressed when the null value indicator is set to NULL, otherwise an empty value will not be suppressed and is stored.
 - If NU is set, empty values will be suppressed and not stored (e.g., blanks in an alpha field).

If the field you selected has been defined with the UQ (unique descriptor) option, you can press PF4 (Rel UQ) to remove it.

No modifications to records in Data Storage are made by this function. You are, therefore, responsible for preventing references to the field that would cause invalid results because of an inconsistency between the new parameter value as defined to Adabas and the actual value contained in the record.

- 6 If the file is protected, enter the password in the `File Password` field before you press Enter.



Caution: The `In Parallel` field allows you to specify whether processing should continue against a file while the function you have selected modifies the file. Specify "YES" to allow file processing to continue; specify "NO" to give Adabas exclusive file control while performing the function. With this option set to "YES", Adabas performs the function while all applications executing against the file are temporarily quiesced and suspended. File integrity is always maintained. For this reason, your applications that are executing against the file may experience difficulty. Please maintain an awareness of the impact on your environment and the consequences of performing your selected functions against a file when using this option. With this option set to "NO" (the default),

Adabas requires exclusive file control (that is, no applications can be executing against the file) when performing the function.

Defining a New Field Definition Table (FDT)

Selecting **Define New FDT** (option D) on the **FDT/SDT Definition / Modification** allows you to define a new FDT for an Adabas file.

This function corresponds to the Adabas utility function ADACMP COMPRESS. The equivalent direct command is:

```
DEFINE FDT
```

> To define a new FDT:

- In the **Code** field, select option **D** (define new FDT) on the **FDT/SDT Definition / Modification** menu.

The Define FDT screen appears, which can be used to define a new FDT for a new file:

```
12:46:24          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
DBID 1955          -   Define FDT   -          PFLCD12

File Number .... 90          New FDT ... Y

Enter Field Description(s) ::

I Lev1 I Name I Length I Format I Options          I Date/time and System fields
I-----
I ___ I ___ I ___ I ___ I ___ I ___ I ___
I ___ I ___ I ___ I ___ I ___ I ___ I ___
I ___ I ___ I ___ I ___ I ___ I ___ I ___
I ___ I ___ I ___ I ___ I ___ I ___ I ___
I ___ I ___ I ___ I ___ I ___ I ___ I ___
I ___ I ___ I ___ I ___ I ___ I ___ I ___
I ___ I ___ I ___ I ___ I ___ I ___ I ___
I ___ I ___ I ___ I ___ I ___ I ___ I ___
I ___ I ___ I ___ I ___ I ___ I ___ I ___
I ___ I ___ I ___ I ___ I ___ I ___ I ___

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help      Def SDT   Exit      Def File  Disp FDT          Menu      ↵
```

FDTs for existing files cannot be redefined with this option.

Deleting a Field from the FDT

Selecting **Delete field from FDT** (option F) on the **FDT/SDT Definition / Modification** allows you to logically delete a field from the FDT for a file.

This function corresponds to the Adabas ADADBS DELFN utility function.

The **Delete Field** screen appears.

```

12:48:40          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
DBID 1955          -  Delete Field  -          PFLCF02

Field Name ..... AA
File Number ..... 1
File Name ..... EMPLOYEES

Enter 'DELETE' to confirm ... _____

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit          Confirm          Menu          ↵
    
```

> To delete the field:

- Press PF6 to delete the field.

Or:

Type "DELETE" in the space provided and press Enter.

The field is deleted from the FDT.



Note: Fields marked for deletion are identified in the **Field Definition Table (FDT)** section of the **Database Report**.

Undeleting a Field from the FDT

Selecting **Undelete field from FDT** (option **G**) on the **FDT/SDT Definition / Modification** allows you to logically undelete a field you had previously deleted from the FDT for a file.

This function corresponds to the Adabas ADADBS UNDELFN utility function.

The Undelete Field screen appears.

```

12:48:40          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
DBID 1955          - Undelete Field -          PFLCG02

Field Name ..... AA
File Number ..... 1
File Name ..... EMPLOYEES

Enter 'UNDELETE' to confirm .. _____

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help                Exit                Confirm                Menu                ↵

```

> To undelete the field:

- Press PF6 to undelete the field.

Or:

Type "UNDELETE" in the space provided and press Enter.

The field is undeleted from the FDT.

Inverting a File Online

Selecting **Online Invert** (option I) on the **FDT/SDT Definition / Modification** displays the Online Invert screen.

The equivalent direct command is:

ONLINE INVERT

```
13:02:04          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
DBID 1955          -  Online Invert  -          PFLCI02
```

```
File Number .... 1      EMPLOYEES
Password .....
```

Enter the definition, using the syntax of the ADADBS ONLINVERT utility:

```
_____
_____
```

Note: Only one Invert Process can be active for a file at any time.

Examples:

```
FIELD='AA'                HYPDE='01,HD,20,A,NU,MU=AA,AB'
SUBDE='SB=AA(1,5)'        PHONDE='PH(AA) '
SUPDE='SP=AA(1,5),BB(1,2),CC(3,5)' COLDE='1,CD=AA'
```

Enter Descriptor information and press 'enter'

```
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help                Exit                Menu                ↵
```

The specified file must be currently loaded.

Specify the definition in the space provided, using the ADADBS ONLINVERT syntax. PF1 provides help information for this syntax; see the *Adabas Utilities* documentation for additional information.

Only one descriptor can be specified per process.

Only one invert process can be active for a file at any time. If an attempt is made to start a second invert process before the first one has completed, a response code 64 is returned.

Defining a Special Descriptor Table (SDT)

Selecting **Define/add SDT** (option **S**) on the **FDT/SDT Definition / Modification** menu allows you to define special descriptors in an existing FDT for a new file. This option is available only if an FDT exists but no file control block (FCB) exists for the file (for example, if the FDT has been created but no records loaded, or if the file was deleted with the option to retain the FDT).

This function corresponds to the Adabas utility function ADACMP COMPRESS. The equivalent direct command is

```
DEFINE STD
```

The Define SDT screen appears.

```
13:02:42          ***** A D A B A S  BASIC SERVICES *****          2014-05-02
DBID 1955          - Define SDT -                                     PFLCH12

File Number .... 1
Password .....

Enter SDT-Definition, using the syntax of the ADACMP Utility:

_____
_____
_____
_____
_____
_____
_____
_____
_____
_____

Enter SDT information and press 'enter'
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help      Def File  Exit      Refresh                                     Menu      ↵
```

Use ADACMP syntax (see the *Adabas Utilities* documentation) on this screen.

Releasing the UQ Option from a Descriptor

Selecting **Release UQ from descriptor** (option U) on the **FDT/SDT Definition / Modification** menu after specifying the file number and descriptor field on the menu allows you to release the UQ (unique descriptor) option from the descriptor field.

The Release UQ screen appears.

```

13:08:00          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
DBID 1955          -  Release UQ  -          PFLCU02

Confirm Release of UQ:

File ..... 41
File Name ..... BIGFDT2
Field Name ..... AA

File Password ..

Enter 'RELEASE' to confirm ... _____

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit          Confirm          Menu          ↵
    
```

Releasing a Descriptor

Selection option **D, Release Descriptor**, on the **File Maintenance** menu allows you to remove a descriptor by freeing the specified field's inverted list in the Associator. Field names listed in the field definition table (FDT) with an option of "DE" are descriptors.



Note: You can view the FDT of the existing file by selecting option **R, Database Report**, from the AOS main menu.

This function corresponds to the Adabas utility function ADADBS RELEASE. The equivalent direct command is

```
RELEASE DESCRIPTOR file-number descriptor
```

➤ **To release a descriptor:**

- 1 Select option **D** (Release Descriptor) on the **File Maintenance** menu.
- 2 Specify the number of the existing file.
- 3 Specify the name of the existing descriptor to be released.
- 4 Press **ENTER**.
- 5 Confirm the release on the Release Descriptor screen:

```

13:48:20          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
DBID 1955          - Release Descriptor -          PFLD022

Descriptor Name .. AA
File Number ..... 1
File Name ..... EMPLOYEES
Password .....
In Parallel ..... NO_

Enter 'RELEASE' to confirm .. _____

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help                Exit                Confirm                Menu                ↵

```

Press **PF6** to release the descriptor.

Or:

Type "RELEASE" in the space provided and press **Enter**.

The descriptor is released.

Deleting an Adabas File

Selecting option **E** (Delete existing file) on the **File Maintenance** menu allows you to free extents used by an existing file for use by other existing files or newly added files.

You have the option to save the field definition table (FDT) so that the field description of the deleted file remains in the database and can be used for a subsequent new file definition.

If the file to be deleted is a coupled file, it must first be uncoupled using option **U** on the **Database Maintenance** menu or the `UNCOUPLE` direct command.

This function corresponds to the utility function `ADADBS DELETE`.

The equivalent direct command is

```
DELETE FILE file-number
```

> To delete an Adabas file:

- 1 Select option **E** (Delete existing file) on the **File Maintenance** menu.
- 2 Specify the number of the existing file.
- 3 Press `ENTER`.

The Delete File screen appears.

```

13:48:50          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
DBID 1955          - Delete File -          PDMD002

File Number ..... 1
File Name ..... EMPLOYEES

Enter File Name to confirm delete ...

Save Field Description Table ..... N

File Password .....

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit          Menu

```

- 4 Tab to the Enter File Name to confirm delete field and type in the name of the file.
- 5 Tab to the Save Field Description Table field and type "Y" to save the FDT for the file or "N" to delete the FDT.
- 6 Tab to the File Password field and specify the file password, if any.
- 7 Press Enter to delete the file.

The file is deleted.

Defining a New File

Before option F (Define new file) on the **File Maintenance** menu can be used to add a new file to the specified database, an FDT must be defined for the file. Alternatively, you may choose to use an already existing FDT (retained from a Delete File function run with the "SAVE FDT" option).

This function corresponds to the utility function ADALOD LOAD.

The equivalent direct command is

```
DEFINE FILE file-number
```

To define a new FDT for a file, read [Defining a New Field Definition Table \(FDT\)](#), elsewhere in this guide.

➤ **To add a new file for which an FDT has been defined:**

- 1 Select option **F** (Define new file) on the **File Maintenance** menu.
- 2 Specify the number of the file to be added.
- 3 Specify the database to which it will be added.
- 4 Press **Enter**.

If the file already exists in that database, a message is displayed at the top of the menu. Otherwise, the Define File screen appears.

```

13:49:15          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
DBID 1955          - Define File -          PFLF012

File Name ..... TEST-90_____
MAXISN ..... _____          ACRABN .....
Datastorage Size .. _____ B (BLKs/CYLs)          DSRABN .....
Normalindex Size .. _____ B (BLKs/CYLs)          NIRABN .....
Upperindex Size ... _____ B (BLKs/CYLs)          UIRABN .....

MINISN .....* 1          ISN Size ..... 3 Byte Anchor Fnr .....
ISN Reuse ....* N          MIXDSDEV ..... N          Ciphering ..... N
DS Reuse ....* Y          Spanned Records ... N          Alpha Code .....
DATA device ..* 3390          MU / PE > 191 ..... N          Wide Code .....
ASSO padding .* 10 %          LOB file ..... N          User Wide Code .
DATA padding .* 10 %          Rel. LOB file # ...          Reptor upd only. N
SYFMAXUV ..... 0

Max Blks:          Max comp. rec.len . 5060
  DS extents ..          Index Compression . N          Multi Client
  NI extents ..          No AC Extension ... N          Support ..... N
  UI extents ..          Program Refresh ... N          Owner-ID Len ... 8

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit          ADAM          Menu          ↵
    
```

- 5 Supply values for the **MAXISN**, **Datastorage Size**, **Normalindex Size**, and **Upperindex Size**, at a minimum. Alter any other fields as appropriate for the file.
- 6 When all field values have been specified, press **Enter** to define the file.

➤ **To specify parameters for an ADAM file:**

- 1 Press **PF7** (ADAM).

The following ADAM File Information window appears:

```
ADAM File Information:
```

```
ADAMDE (field/ISN).  
ADAMPARM .....  
ADAM Overflow .....  
ADAM Dataform ..... Y
```

```
↵
```

- 2 Supply values for all fields and press Enter.

Logically Deleting or Undeleting a Descriptor

You can use AOS to logically delete and undelete a descriptor. Logically deleting a field from a file removes the field from the FDT, but retains the field data in the database. Logically undeleting a field that was previously logically deleted reinstates the field in the FDT.

Selecting **Logically delete/undel descriptr** (option **L**) on the **File Menu** allows you to logically delete a descriptor from a file.

This function corresponds to the Adabas ADADBS DELDE, DELFN, UNDELDE, and UNDELFN utility functions.

The Logically Delete Undelete Descriptor screen appears.

```
13:50:16          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
DBID 1955          -  Logically Delete Undelete Descriptor  -          PFLL002

Descriptor Name ..... AA
File Number ..... 29
File Name ..... TEST-29
Password .....
Delete (yes) or Undelete (no) ... NO

Enter 'LDELETE' to confirm .. _____

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help                Exit                Confirm                Menu                ↵
```

- [Deleting a Descriptor](#)
- [Undeleting a Descriptor](#)

Deleting a Descriptor

➤ **To delete the descriptor:**

Be sure that a valid descriptor is correctly identified on the **File Maintenance** menu.

- 1 Tab to the Delete (yes) or Undelete (no) field and type "YES".
- 2 Press PF6 to confirm the descriptor deletion.

Or:

Type "LDELETE." in the space provided and press Enter.

The descriptor is logically deleted.

Undeleting a Descriptor

➤ To undelete a descriptor:

Be sure that a valid descriptor is correctly identified on the **File Maintenance** menu.

- 1 Tab to the Delete (yes) or Undelete (no) field and type "NO".
- 2 Press PF6 to confirm the descriptor undeleting.

Or:

Type "LDELETE." in the space provided and press Enter.

The descriptor is logically undeleted.

Modifying File Parameters



Note: AOS is not able to modify file parameters for Adabas files incorporated in Predict. This is because AOS cannot modify the FCB of these files. Error messages are produced when such an attempt is made. We recommend that you use Predict 4.5.1 to make file parameter updates for Adabas files incorporated in Predict.

You can use AOS to modify file parameters unless they are incorporated in Predict.

This function corresponds to the utility function ADADBS MODFCB. The equivalent direct command is

```
MODIFY FILE file-number
```

➤ To modify parameters for a file

- 1 Select option **M** (Modify file parameters) on the **File Maintenance** menu.
- 2 Specify the number of the file to be modified.
- 3 If the file is protected, supply the password.
- 4 Press Enter.

The Modify File Parameters screen appears:

```

15:46:43          ***** A D A B A S  BASIC  SERVICES *****          2016-07-15
DBID 1974          -  Modify File Parameters  -          PFLM032

File No. ... 21
File Name .. FILE-1974-21          in Parallel ..... YES
-----
ASSO PFAC ..... 10          Max. UI Blks per extent .. 0
DATA PFAC ..... 10          Max. NI Blks per extent .. 0
Max. RECL ..... 5060          Max. DS Blks per extent .. 0
ISN Reuse ..... OFF
New File Name ..... FILE-1974-21_____ with RESET ..... ____
New File No. .... 21          SETISN ..... 0
User ISN ..... OFF          DS Reuse ..... ON_
File Password .....          with RESET ..... ____
Filereadonly ..... OFF          Mixed DS Device ..... OFF
Spanned Records ... OFF          Program Refresh ..... OFF
MU/PE indices ..... 1          Max occur system fields .. 0
Reptor update only. OFF          Replication ..... OFF__
AlphaNum Encoding . 0
WideChar Encoding . 0

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit          Menu
  
```

If large object (LOB) flags are set (if the file is a LOB file) and you press PF4 on the screen when it displays a LOB file, a pop-up window appears showing detailed information about the file:

```

- LOB File Information -

*****

* File 16 *

*****

File Info: LOB file
Related LOB File Number ..... 15____

PF3---
Cancel
  
```

5 Update file parameters as described in the rest of this section

- [Change Padding Factors](#)
- [Changing Maximum Allocation](#)
- [Changing Record Length](#)
- [Renaming or Renumbering the File](#)
- [Supplying a Password for the File](#)
- [Setting ISN and Data Storage Block Reuse](#)

- [Making the File Read-Only](#)
- [Activating Spanned Record Support](#)
- [Selecting File Options](#)
- [Changing Code Pages](#)
- [Changing Replication Parameters](#)

Change Padding Factors

Using the `ASSO PFAC` and the `DATA PFAC` fields on the Modify File Parameters screen, you can change the Associator and Data Storage padding factors for the file.

The "padding factor" is the percentage (%) of each Associator or Data Storage block that is reserved; that is, not loaded. This area is used to create new records later. The range is from 3 to 90 percent. The factor size allocated should depend on the amount of updating that is expected. The number of bytes left in the Associator after padding must exceed the largest descriptor value by at least 10.

Changing Maximum Allocation

Using the `Max Allocation` fields on the Modify File Parameters screen, you can change the maximum number of blocks that can be allocated for Data Storage (field `DS Blks per extent`), the normal index (field `NI Blks per extent`), or the upper index extent (field `UI Blks per extent`).

The value specified must be specified in blocks. If one of the parameters is either not specified or specifies "0", the maximum secondary extent allocation for that component has no limit.

In all cases, however, Adabas enforces minimum secondary allocations for these parameters:

```
DS Blks per extent=6
NI Blks per extent=6
UI Blks per extent=15
```

If you specify a value lower than these minimum allocations, the Adabas-enforced minimum value is used.

Changing Record Length

Using the `Max. RECL` field on the Modify File Parameters screen, you can change the maximum compressed record length allowed.

Renaming or Renumbering the File

Using the `New File Name` and `New File No.` fields on the `Modify File Parameters` screen, you can change the name or number of the file.

The equivalent direct commands are

```
RENAME FILE file-number
```

```
RENUMBER FILE file-number
```

Supplying a Password for the File

Use the `File Password` field to specify a password for the file.

Setting ISN and Data Storage Block Reuse

`ISN Reuse` and `DS Reuse` determine whether ISNs and Data Storage blocks for deleted records are reused as new records are added to the file. The equivalent direct commands are

```
REUSE ISNS file-number
```

```
REUSE DS file-number
```

When setting either of these two options to "ON", you can also set the `RESET` option "ON" to start the search for an unused ISN or Data Storage block at the beginning of the file.

Making the File Read-Only

If you want this file to be accessed only in read-only mode, set the `Filereadonly` field to ON. This is useful if you need to maintain them while the rest of the database is up.

Activating Spanned Record Support

To activate spanned record support for a file, set the `Spanned Records` field to ON. Once spanned record support is turned on, you can create spanned records in that file; if spanned record support is *not* turned on, you cannot create spanned records in a file.

Selecting File Options

You can also turn off or on several file options on this screen:

```
User ISN
ISN Reuse ...with RESET
DS Reuse ...with RESET
Mixed DS Device
MU PE Indices
Program Refresh
```

Changing Code Pages

If the file was loaded using universal encoding support (UES), the code values may be changed on this screen using the `AlphaNum Encoding` and `WideChar Encoding` fields.

Changing Replication Parameters

You can change the settings of several replication parameters:

Parameter	Description
Reptor update only	Indicates whether the file may be updated only by the Event Replicator Server as part of Adabas-to-Adabas replication or by other means as well.
Replication	Indicates whether replication has been turned on for the Adabas file.

Reordering a File Online



Notes:

1. This function is not available in the Adabas Cluster Services or Adabas Parallel Services environments. It cannot be started for the checkpoint or security files.
2. You cannot use this option to reorder a spanned file. Reordering of spanned files cannot be done online; you must use Adabas batch utilities to reorder a spanned file.

Selecting Reorder File Online (option **O**) on the **File Maintenance** menu displays the Online Reorder File screen, which can be used to start an online reorder process for the specified file.

The equivalent direct command is

```
ONLINE REORDER
```

```

14:14:17          ***** A D A B A S  BASIC  SERVICES *****          2025-09-08
DBID 1955          - Online Reorder File -          PFL0002

Reorder for file... 1      EMPLOYEES
Password....

-----

Type of Reorder..... _

Options:  Asso Padding Factor.. __
          Data Padding Factor.. __
          Sort Sequence..... ____

Command ==>
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help       Exit      Chk REORD                               Menu           ↵
    
```

➤ **To select the type of reorder to be performed:**

- 1 Enter one of the following reorder type codes in the `Type of Reorder` field:

Reorder type	Corresponds to ADADBS function...	Reorders ...
B (both)	ONLREORFILE	the entire file
A (Associator)	ONLREORFASSO	the Associator for the file only
D (Data Storage)	ONLREORFDATA	Data Storage for the file only

The only file level parameters that can be changed using this function are the padding factors. If these fields are left blank, the current parameter settings are used during the reorder.

When reordering Data Storage for a file, you can specify a sort sequence. The default is physical sequence or "PHY". Other possible options include "ISN" if the file is to be sorted in ISN order, or the two character descriptor name to sort the file according to the value of the specified descriptor.

- 2 Press `Enter`.
- 3 Monitor the progress of the reorder via the Console messages listed for the executing Adabas.

Or:

From the AOS **Main menu**,, choose option **O (Session Opercoms)**, and then option **U (Manage Online Utilities)** to check the status of the reorder (or press `PF4` if available).

Refreshing a File to Empty Status

Option **R**, (Refresh file to empty status) on the **File Maintenance** menu deletes all file records and assigns a single extent to each file component.

This function corresponds to the utility function ADADBS REFRESH. The equivalent direct command is

```
REFRESH FILE file-number
```

➤ To refresh a file to empty status:

- 1 Select option **R** (Refresh file to empty status) on the **File Maintenance** menu.
- 2 Specify the number of the existing file in the specified database.
- 3 Press Enter.

The Refresh File screen appears.

```
13:56:13          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
DBID 1955          - Refresh File -          PFLR002

File Number ... 29
File Name ..... TEST-29
Password .....

Enter File Name to confirm ...

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit          Menu          ↵
```

- 4 Tab to the Password field and enter a password for the file, if necessary.
- 5 Tab to the Enter File Name to confirm field and enter the name of the file.
- 6 Press Enter to confirm the refresh on the Refresh File screen.

Allocating or Deallocating File Space

Option **S**, (Allocate/deallocate file space) on the **File Maintenance** menu allows you to allocate or deallocate extents for the address converter, normal index, upper index, and Data Storage of a file. You can specify the allocation in blocks or in cylinders, a starting relative Adabas block number, and the device where the allocated space should be located.

This function corresponds to the utility functions ADADBS ALLOCATE and ADADBS DEALLOCATE.



Note: If an attempt is made to allocate AC beyond MAXISN, Adabas will detect this and only allocate up to MAXISN.

The equivalent direct commands are

```
ALLOCATE SPACE file-number
```

```
DEALLOCATE SPACE file-number
```

➤ To allocate or deallocate space for a file:

- 1 Select option **S** (allocate/deallocate file space).
- 2 Specify the file to be modified.
- 3 Press Enter.

The Allocate/Deallocate File Space screen appears.

```

13:56:35          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
DBID 1955          -  Allocate/Deallocate File Space  -          PFLS002

File Number ..... 29
File Name ..... TEST-29

Enter Parameters :          Possible values:

  Allocate/Deallocate ... _          (A/D)
  Table Type ..... _          (AC/A2/DS/NI/UI)
  Size .....
  Blocks or Cylinders ... B          (B/C)
  Start RABN ..... _____
  Device Type ..... _____

File Password .....

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit          Menu          ↵

```

- 4 Indicate whether you are allocating or deallocating space in the `Allocate/Deallocate` field. Specify "A" to allocate space and "D" to deallocate space.
- 5 Tab to the `Table Type` field and specify the type of space you are allocating or deallocating (address converter, Data Storage, normal index, or upper index)>
- 6 Specify the amount of space that should be allocated or deallocated using the `Size` field.
- 7 Specify whether the space should be allocated or deallocated in blocks (B) or cylinders (C) using the `Blocks or Cylinders` field.
- 8 Optionally specify a starting RABN in the `Start RABN` field.
- 9 If the file is protected, supply the password in the `File Password` field.
- 10 Press `Enter` to perform the allocation or deallocation.

Maintaining Expanded Files

Selecting option **X** and a file number (`File No` field) on the **File Maintenance** menu displays the **Expanded File Maintenance** menu:

```

13:57:18          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
                  - Expanded File Maintenance -                      PFLX002

                Code      Service
                -----
                I         Insert file into chain
                R         Remove file from chain
                ?         Help
                .         Exit
                -----

Code .....
File No. .... 29
Master Fnr ...
Password .....
Database ID .. 1955   (WIS1955)

Command ==>
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit                               Menu          ↵
    
```

The functions available on this menu correspond to the utility functions ADALOD LOAD and ADALOD UPDATE.

➤ **To insert an existing file into an expanded file chain:**

- 1 Select option **I** on the **Expanded File Maintenance** menu.
- 2 Specify the number of the file to be inserted (**File No** field).
- 3 Specify the number of the master file of the expanded file chain into which the file is being inserted (**Master Fnr** field).
- 4 If the file is protected, supply the password in the **File Password** field.
- 5 Press **Enter**.

 **Note:** If the file to be inserted is to be the first (master) file of the chain, both **File No** and **Master Fnr** fields must be set to the same value.

➤ **To remove a component file from an expanded file chain:**

- 1 Select option "R" on the **Expanded File Maintenance** menu.
- 2 Specify just the number of the file to be removed (**File No** field) from the chain.

If the file to be removed is the master file, the next file in the chain will become the new master file.

- 3 If the file is protected, supply the password in the `File Password` field.
- 4 Press `Enter`.

7 Maintaining Databases

▪ Adding a New Associator or Data Storage Extent	141
▪ Increasing or Decreasing Associator or Data Storage Data Set Size	142
▪ Displaying and Resetting DIB Block Entries	143
▪ Recovering Unused Space	143
▪ Uncoupling Adabas Files	143

The AOS Database Maintenance function controls Adabas database (ASSO/DATA) file and space allocation. You can:

- add data sets, increase or decrease the size of the last data set;
- uncouple Adabas files;
- display or reset entries in the data integrity block (DIB); and
- recover space previously allocated but not used by Adabas utilities that ended abnormally.

Database maintenance tasks can be performed from the **Database Maintenance** menu:

```

13:58:00          ***** A D A B A S BASIC SERVICES *****          2014-05-02
                   - Database Maintenance -                          PDM0002

                Code      Service
                ----      -
                A         Add new dataset to ASSO/DATA
                I         Increase/decrease ASSO/DATA
                R         List/reset DIB block entries
                S         Recover unused space
                U         Uncouple two ADABAS files
                ?         Help
                .         Exit
                ----      -

Code ..... _
File No. .... 29
Coupled File .. 0
Database ID ... 1955 (WIS1955)

Command ==>
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help           Exit           Menu           ↵
    
```

Database maintenance includes the following functions:

Option	Function
A	<i>Adding a New Associator or Data Storage Extent</i> allows you to add a preformatted data set to the Associator or Data Storage.
I	<i>Increasing or Decreasing Associator or Data Storage Data Set Size</i> allows you to change the size of an existing Associator or Data Storage data set.
R	<i>Displaying and Resetting DIB Block Entries</i> allows you to display and reset the data integrity block (DIB) entries for each Adabas utility currently operating.
S	<i>Recovering Unused Space</i> allows you to recover unused space from utility operations that ended abnormally.
U	<i>Uncoupling Adabas Files</i> allows you to remove the physical coupling between files.

Adding a New Associator or Data Storage Extent

Option **A (Add new dataset to ASSO/DATA)** on the **Database Maintenance** menu is used to add a preformatted data set to the Associator or Data Storage. Before using this option, the data set to be added must be formatted using the ADAFRM utility.

Option **A** should be used only if the new data set is located on a different physical device.

This function corresponds to the utility function ADADBS ADD.

The equivalent direct commands are:

```
ADD ASSO
```

```
ADD DATA
```

The Add Dataset screen appears.

```

13:58:28          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
DBID 1955          -  Add Dataset  -          PDMA002

Enter Parameters to Add either a DATA OR ASSO dataset:

      ASSO Device ..... ____
      ASSO Size ..... _____

      DATA Device ..... ____
      DATA Size ..... _____

      Blocks/Cylinders .. B

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit          Menu          ↵

```

Increasing or Decreasing Associator or Data Storage Data Set Size

Option **I (Increase/decrease ASSO/DATA)** on the **Database Maintenance** menu is used to change the size of an existing data set for the specified component. If the component has more than one data set, option **I** changes the size of the last data set.

Since this option only changes the Adabas general control block entry, you must also ensure that the needed space is physically allocated and formatted when the data set is being increased.

When the Data Storage component has been increased four times, an ADAORD REORASSO utility function must be executed to reorder the DSST extents in the Associator component.

This function corresponds to the utility functions ADADBS INCREASE and ADADBS DECREASE.

The equivalent direct commands are:

```
INCREASE ASSO
```

```
INCREASE DATA
```

```
DECREASE ASSO
```

```
DECREASE DATA
```

The Increase/Decrease screen appears.

```
13:58:46          ***** A D A B A S BASIC SERVICES *****          2014-05-02
DBID 1955          - Increase/Decrease -          PDMI002

Enter Parameters :          Possible values:

          Increase/Decrease .. _          (I/D)

          ASSO/DATA .. _          (A/D)
          Size .. _____
          Blocks or Cylinders .. B          (B/C for Increase)
          (B for Decrease)

Note: After an INCREASE operation is completed, the nucleus session will
      be automatically ended to allow for the necessary Associator or Data
      Storage formatting.

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit          Menu          ↵
```

Displaying and Resetting DIB Block Entries

The data integrity block (DIB) comprises entries for each Adabas utility currently operating, describing the resources each utility is using.

Option **R (List/reset DIB block entries)** on the **Database Maintenance** menu allows you to list and remove any unwanted entries from the DIB.

This function corresponds to the utility function ADADBS RESETDIB. It can also be accomplished using the operator command DDIB.

The equivalent direct commands are:

```
DISPLAY DIB
```

```
RESET DIB
```

Recovering Unused Space

Space allocated for utility operations that ended abnormally remains unavailable unless it is intentionally recovered.

Option **S (Recover unused space)** on the **Database Maintenance** menu is used to purposely reclaim such space for use. A message is returned indicating that the space has been successfully recovered.

This function corresponds to the utility function ADADBS RECOVER.

The equivalent direct command is:

```
RECOVER SPACE
```

Uncoupling Adabas Files

Option **U (Uncouple two ADABAS files)** on the **Database Maintenance** menu is used to remove the physical coupling between the specified files by erasing the coupling inverted lists from each file's Associator. No change is made to the field definition tables (FDTs) or descriptors for the specified files.

This option must be executed before either of the specified files is deleted.

To determine if a file is physically coupled, check the **C (coupling)** indicator in the Database Report option's **Display File** screen. Using the same function for those selected files, you can see the

specific coupling information; that is, the specific fields in one file and their coupling to fields in other files.

This function corresponds to the utility function ADADBS UNCOUPLE.

The equivalent direct command is

```
UNCOUPLE FILES file1 file2
```

8

Performing System Operator Command Functions

▪ Allocating/Deallocating CLOG and PLOG Data Sets	147
▪ Reactivating Command Logging	150
▪ Extended Error Recovery Functions	150
▪ Forcing Dual/Multiple CLOG/PLOG Switch	157
▪ Locking / Unlocking Files	158
▪ CLOG/PLOG Dataset Status	160
▪ Resetting Online Dump Status	164
▪ Stopping Users	164
▪ Termination Commands	168
▪ Managing Online Utilities	169
▪ Maintaining the User Table	170

Selecting **Session Opercoms** (option **O**) from the **Main Menu** displays the **Session Opercoms** menu:

```

16:14:44          ***** A D A B A S BASIC SERVICES *****          2024-01-11
                   - Session Opercoms -                               PACI002

Code  Service                                           Code  Service
-----
A    Allocate/Deallocate CLOG/PLOG                      R    Reset ONLINE-DUMP-Status
C    Issue reactivate CLOG command                      S    Stop user(s)
E    Extended Error Recovery                            T    Termination Commands
F    Force CLOG or PLOG switch                          U    Manage Online Utilities
L    Lock or unlock files                               V    User Table Maintenance
M    CLOG/PLOG dataset status                           X    Replicator Management
.    Exit                                               ?    Help
-----

Code ..... _
Userid(ETID) ... _____
CLOG/PLOG Ind .. _                                     Global.. _
Database ID .... 1955   (WIS1955)                     NucID .. 1021

Command ==>
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help           Exit           Menu
    
```

 **Note:** A zero value in the NucID field indicates that the command applies to all nuclei in the cluster (global). A non-zero value for NucID indicates that the command applies only to the cluster nucleus specified.

System operator command functions you can perform are accessed from the Session Opercoms menu by entering the appropriate code, as follows:

Option	Function
A	<i>Allocating/Deallocating CLOG and PLOG Data Sets</i>
C	<i>Reactivating Command Logging</i>
E	<i>Extended Error Recovery Functions</i>
F	<i>Forcing Dual/Multiple CLOG/PLOG Switch</i>
L	<i>Locking / Unlocking files</i>
M	<i>CLOG/PLOG dataset status</i>
R	<i>Resetting Online Dump Status</i>
S	<i>Stopping Users</i>
T	<i>Termination Commands</i>
U	<i>Managing Online Utilities</i>

Option	Function
V	<i>Maintaining the User Table (nucleus cluster environments only)</i>
X	<p>Displays the Replication Management menu, which allows you to access the Adabas Event Replicator Subsystem (SYSRPTR) as well as to activate and deactivate subsystem definitions, run the RPLCHECK, RPLCLEANUP, or RPLREFRESH utilities, and display subsystem parameters and definitions.</p> <p>Note: This option is only available if the database you have selected is an Event Replicator Server database.</p> <p>For more information about the Adabas Event Replicator Subsystem or any of the functions you can perform from the Replication Management menu, refer to your Event Replicator for Adabas documentation.</p>

Allocating/Deallocating CLOG and PLOG Data Sets

Option **A** (**Allocate/Deallocate CLOG/PLOG**) on the **Session Opercoms** menu is used to dynamically add and delete CLOG and PLOG data sets without terminating your current nucleus session. Using this function, you can specify up to eight CLOG or PLOG data sets. This will reduce the chances of a wait condition in the nucleus, when the nucleus waits for an available CLOG or PLOG. You might find this particularly useful during busier times of the month or year.

This function corresponds to the utility functions ADADBS ADDCLOG, ADDPLOG, DELCLOG, and DELPLOG.

When you select option **A**, the **Allocate/Deallocate CLOG/PLOG** menu appears.

To add a CLOG or PLOG data set dynamically, the nucleus must know about its JCL at startup time. To use this functionality in AOS, you must set up your Adabas nucleus startup jobs to include definition statements for the maximum number of CLOG and PLOG data sets as you plan to use, but limit the actual usage of the PLOGs using the ADARUN NCLOG and NPLOG parameters. For example, you might start a nucleus with eight PLOG definitions in the Adabas startup JCL, but limit the number of PLOGs actually used during nucleus processing to three PLOGs by setting the NPLOG parameter to "3". When the nucleus starts up, only three PLOGs will be opened and logged in the PPT, even though eight are defined in the JCL. The additional PLOG data sets can then be dynamically added using this ADADBS ADDPLOG utility or the functions provided on the AOS **Allocate/Deallocate CLOG/PLOG** menu.



Note: Any CLOG or PLOG data sets you add dynamically will not be retained once you recycle your Adabas nucleus. To retain these new data sets when Adabas is stopped and restarted, alter the Adabas startup JCL as well, ensuring that the number of PLOG definition statements in the JCL matches the increased number of PLOG data sets and that the NPLOG ADARUN parameter setting includes the new PLOG data sets.

```

15:13:17          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
                  - Allocate/Deallocate CLOG/PLOG -                   PACIA02

                  Code      Service
                  ----      -
                  A        Allocate CLOG
                  D        Deallocate CLOG
                  P        Allocate PLOG
                  S        Deallocate PLOG
                  ?        Help
                  .        Exit
                  ----      -

Code ..... _
Dataset number . _
Dataset Name ... _____

Database ID .... 1955 (WIS1955)          NucID .. 1021

Command ==>
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help      PPT       Exit                               Menu      ←

```

This section covers the following topics:

- [Allocating CLOG Data Sets](#)
- [Deallocating CLOG Data Sets](#)
- [Allocating PLOG Data Sets](#)
- [Deallocating PLOG Data Sets](#)

Allocating CLOG Data Sets

Option **A (Allocate CLOG)** on the **Allocate/Deallocate CLOG/PLOG** menu is used to dynamically add CLOG data sets without terminating your current nucleus session.

This function corresponds to the utility function ADADBS ADDCLOG.

➤ To allocate a CLOG data set:

- 1 Select option **A** on the **Allocate/Deallocate CLOG/PLOG** menu.
- 2 In the **Dataset number** field, specify the number of the CLOG data set, as defined in your Adabas startup JCL.
- 3 In the **Dataset Name** field, specify the data set name of the CLOG data set, as defined in your Adabas startup JCL.
- 4 Press Enter.

The CLOG data set is allocated and can immediately be used.

When you select option **A**, the **Allocate/Deallocate CLOG/PLOG** menu appears.

Deallocating CLOG Data Sets

Option **D** (**Deallocate CLOG**) on the **Allocate/Deallocate CLOG/PLOG** menu is used to dynamically delete CLOG data sets without terminating your current nucleus session.

This function corresponds to the utility function ADADBS DELCLOG.

» To deallocate a CLOG data set:

- 1 Select option **D** on the **Allocate/Deallocate CLOG/PLOG** menu.
- 2 In the `Dataset number` field, specify the number of the CLOG data set, as defined in your Adabas startup JCL.
- 3 In the `Dataset Name` field, specify the data set name of the CLOG data set, as defined in your Adabas startup JCL.
- 4 Press Enter.

The CLOG data set is deallocated and can no longer be used.

Allocating PLOG Data Sets

Option **P** (**Allocate PLOG**) on the **Allocate/Deallocate CLOG/PLOG** menu is used to dynamically add PLOG data sets without terminating your current nucleus session.

This function corresponds to the utility function ADADBS ADDPLOG.

» To allocate a PLOG data set:

- 1 Select option **P** on the **Allocate/Deallocate CLOG/PLOG** menu.
- 2 In the `Dataset number` field, specify the number of the PLOG data set, as defined in your Adabas startup JCL.
- 3 In the `Dataset Name` field, specify the data set name of the PLOG data set, as defined in your Adabas startup JCL.
- 4 Press Enter.

The PLOG data set is allocated and can immediately be used.

Deallocating PLOG Data Sets

Option **S** (**Deallocate PLOG**) on the **Allocate/Deallocate CLOG/PLOG** menu is used to dynamically delete PLOG data sets without terminating your current nucleus session.

This function corresponds to the utility function ADADBS DELPLOG.

➤ To deallocate a PLOG data set:

- 1 Select option **S** on the **Allocate/Deallocate CLOG/PLOG** menu.
- 2 In the `Dataset number` field, specify the number of the PLOG data set, as defined in your Adabas startup JCL.
- 3 In the `Dataset Name` field, specify the data set name of the PLOG data set, as defined in your Adabas startup JCL.
- 4 Press `Enter`.

The PLOG data set is deallocated and can no longer be used.

Reactivating Command Logging

Option **C** (**Issue reactivate CLOG command**) on the **Session Opercoms** menu is used to reactivate command logging in an active nucleus where it had been disabled previously as a result of an I/O error. The cause of the I/O error needs to be corrected before running this function or command logging will simply fail again and will not be reactivated.

This function corresponds to the utility function ADADBS REACTLOG.

When you select option **C**, a request to reactivate command logging is issued.

Extended Error Recovery Functions

Selecting option **E** (Extended Error Recovery) on the **Session Opercoms** menu displays the **Extended Error Recovery** menu:

```

15:21:46          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
                  - Extended Error Recovery -                          PACIE02

                Code      Service
                -----
                B      Display message buffer
                D      Display/modify environment
                E      Display/modify Exit routines
                M      Add/Delete PIN modules
                P      Display/modify PIN routines
                R      Refresh threshold and alert exits
                S      SNAP a nucleus dump
                ?      Help
                .      Exit
                -----

Code ..... _
Start Address .. _____ End Address ... _____
Database ID .... 1955      (WIS1955)          NUCID .. 1021

Command ==>
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit          Menu          ↵
    
```

 **Note:** Option **R** (Refresh threshold and alert exits) is no longer a functional option.

From this menu you can:

- display the message buffer
- display or modify the parameters controlling the extended error handling environment;
- display or modify parameters for invoking the error handling exits;
- add or delete PIN modules;
- display, activate, or deactivate specific PIN routines;
- SNAP a dump image of nucleus memory.

This section covers the following topics:

- [Display Message Buffer](#)
- [Display/Modify Environment](#)
- [Display/Modify Exits](#)
- [Add/Delete PIN Modules](#)
- [Display/Modify PIN Routines](#)
- [Refresh Threshold and Alert Exits](#)

▪ SNAP a Nucleus Dump

Display Message Buffer

Selecting option **B (Display Message Buffer)** on the **Extended Error Recovery** menu displays the contents of the message buffer on the **Display Message Buffer** screen.

These functions are the same as the error handling operator commands:

```
SMGT,DISPLAY=MSGBUF

15:19:47          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
DBID 1955          -  Display Message Buffer  -          PACIEB2
NUCID .. 1021
Select starting message _____
  Msg Num      Time      Msg ID          Message
-----
  2307      10584254+00E0  00000000 00000000 00000000 00000000  *.....
  2308      10584264+00F0  00000000 00000000 00000000 00000000  *.....
  2309      10584274+0100  00000000 10584284 1058428C 10584284  *.....d..
  2310
  2311
  2312      Snap Basic System Status flags:
  2313
  2314      00067746+0000  00000004 00000000 00000001 00000027  *.....
  2315
  2316 11:09:49 ADAH51 Dump format completed
  2317 11:09:49 ADANX1 *****End P I N R S P Output *****
  2318 11:09:49

Command ==>
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit       Latest    --        -         +         Menu      ↵
```

Press **PF4** to refresh the screen and show the latest messages added to the buffer.

The **Msg Num** column contains the sequential record number for each item in the message buffer. Enter a record number in the field **Select starting message** to position the display to a particular record.

Display/Modify Environment

Selecting option **D (Display/modify environment)** on the **Extended Error Recovery** menu displays the current setting of several extended error handling parameters on the Display/Modify Environment screen.

The functions on this screen mirror the error handling operator commands:

```

SMGT,{ON | OFF}
SMGT,ABNORMALTERM={ON | OFF}
SMGT,DUMP={ON | OFF}
SMGT,MSGBUF={ON | OFF}
SMGT,DISPLAY=LAST

15:22:18          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
DBID 1955          -  Display/Modify Environment  -                    PACIED2
NUCID .. 1021

          ----- Parameters ----- Status - Executions -
Extended Error Recovery (SMGT)  ON          0
Message Buffering .....         ON
Abnormal Term. Handler .....    ON          0
Response Code Handler .....     ON          0
Full System Dump (DUMP) .....   OFF

          ----- Most Recent Recovery Action -----
Last error occurred at: 2014-05-02 11:09:49
Condition: Rsp 009 Location: * N/A *

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help      MsgBuf   Exit                    Menu      ←
    
```

The parameters with "ON"/"OFF" values in the Status column can be activated and deactivated by changing the value.

Code	Description
A	Activates the exit
D	Deactivates the exit
L	Reloads the exit program in memory or to loads a new exit
C	Makes the exit critical
N	Makes the exit noncritical

After changes have been made, use PF4 to refresh this screen.

Add/Delete PIN Modules

Selecting option **M (Add/Delete PIN modules)** on the **Extended Error Recovery** menu displays a list of currently available PIN modules on the **Add/Delete PIN Modules** screen.

These functions are the same as the error handling operator commands

```
SMGT,{ADDPIN | DELPIN}=module-name
```

```
15:27:27          ***** A D A B A S  BASIC SERVICES *****          2014-05-02
DBID 1955          -  Add/Delete PIN Modules  -                      PACIEM2
NUCID .. 1021
```

Mark entries with 'A' to Add or 'D' to Delete:

M	Module	Description	Message
-	-----	-----	-----
-	ADAMXY	Standard Nucleus PIN Routines	
	PINAAP	SAF Security	
	PINAFP	Adabas Fastpath	
	PINATM	Adabas Transaction Manager	
	PINAVI	Adabas Vista	
-	PINRSP	Adabas Response Code Handler	
-	PINUES	Universal Encoding Support	

```
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help                Exit                Menu                ↵
```

➤ To load a PIN module into memory:

- Enter "A" in the M column next to the module name.

This command is successful only if the exit module exists in a library accessible to the Adabas nucleus.

➤ **To remove a PIN module from memory:**

- Enter a "D" in the M column next to the module name.

When deleting a PIN module from memory, all related PIN routines are also removed.

Display/Modify PIN Routines

Selecting option **P (Display/modify PIN routines)** on the **Extended Error Recovery** menu displays a list of PINs currently loaded in memory on the **List/Modify PIN Routines** screen.

These functions are the same as the error handling operator commands

```
SMGT,DISPLAY=PINS
SMGT,{ACTPIN | DEACTPIN}=pin-number
```

```
15:28:01          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
DBID 1955          - List/Modify PIN Routines -          PACIEP2
NUCID .. 1021
Mark entries with 'A' Activate, or 'D' Deactivate:          Total Pins: 267
```

M	Condition	Error Location	Status	Uses	Module	Message
-	000C1000	All Locations	Active	0	ADAMXY	
-	000C2000	All Locations	Active	0	ADAMXY	
-	000C3000	All Locations	Active	0	ADAMXY	
-	000C4000	All Locations	Active	0	ADAMXY	
-	000C5000	All Locations	Active	0	ADAMXY	
-	000C6000	All Locations	Active	0	ADAMXY	
-	000C7000	All Locations	Active	0	ADAMXY	
-	000C8000	All Locations	Active	0	ADAMXY	
-	000C9000	All Locations	Active	0	ADAMXY	
-	000CB000	All Locations	Active	0	ADAMXY	
-	000CF000	All Locations	Active	0	ADAMXY	
-	00047000	All Locations	Active	0	ADAMXY	

```
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit      Refr      --      -      +      Menu      ↵
```

For all PIN routines on the list, the screen indicates the conditions that cause them to be executed, the current status, the number of times they have been used, and the module in which they are located.

To change the status of the PINs from this screen, enter one of the following codes in the M column next to the PIN number:

Code	Description
A	Activates a PIN
D	Deactivates a PIN

After changes have been made, use PF4 to refresh the screen.

Refresh Threshold and Alert Exits

Selecting option "R" (Refresh Threshold and Alert Exits) from the Extended Error Recovery menu is no longer a functional option.

SNAP a Nucleus Dump

Selecting option S (**SNAP a nucleus dump**) on the **Extended Error Recovery** menu generates a formatted dump of the nucleus without error diagnostics.

This function is the same as the error handling operator command

```
SMGT,SNAP[=(start,end)]
```

➤ To generate a dump of the whole nucleus:

- 1 Leave the **Start Address** and **End Address** fields on the menu blank.

Or:

To generate a SNAP dump of only a range of addresses, enter hexadecimal addresses in the **Start Address** and **End Address** fields on the menu.

- 2 Press **Enter**.

The formatted dump is written to the DDPRINT data set specified in the nucleus.

Forcing Dual/Multiple CLOG/PLOG Switch

Option F (**Force CLOG or PLOG switch**) on the **Session Opercoms** menu allows you to immediately switch (by forcing an end-of-file) between dual or multiple command log (CLOG) or protection log (PLOG) files. Switching (that is, "toggling") changes from one CLOG or PLOG file to another.

Equivalent direct commands are:

```
FORCE CLOGSWITCH
```

```
FORCE PLOGSWITCH
```

Locking / Unlocking Files

Option **L (Lock or unlock files)** on the **Session Opercoms** menu is used to lock, unlock, or display locked files. Files can be locked or unlocked for all users or for all but utility or EXF users. Once locked for all users, a file cannot be unlocked for utility users only.

- Locking is immediate; a transaction in process whose file becomes locked will be backed out.
- Unlocking makes the file available again for normal use.

Equivalent direct commands are:

LOCK FILE

UNLOCK FILE

Selecting option **L** displays the **Lock/Unlock Files** menu.

```

15:28:48          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
                  - Lock / Unlock Files -                          PACIL02

Code      Service
-----
D         Display locked files
F         Lock file for all users
K         Advance lock file
L         Lock file except for UTI/EXF users
N         Unlock file from general lock
R         Release an advance lock
U         Unlock file from UTI/EXF lock
?         Help
.         Exit
-----

Code ..... _
File Number ..
UTI/EXF Ind .. U
Database ID .. 1955 (WIS1955)

Command ==>
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit          Menu          ↵
    
```

For the most part, the options on this menu perform locking or unlocking functions without the use of additional AOS screens.

CLOG/PLOG Dataset Status

The CLOG/PLOG Dataset Status program provides current information about the individual status of the CLOG or PLOG datasets per Adabas DBID/Nucid. If you select a DBID that is an Auditing Server, the program provides information about the status of each ALOG or PLOG dataset.

To display the CLOG/PLOG dataset status, select the **M - CLOG/PLOG dataset status** option in the **Session Opercoms** menu.

```

19:52:38          ***** A D A B A S  BASIC  SERVICES *****          2023-10-31
DBID 1955          - CLOG/PLOG DATASET STATUS -          MACIM02

Switch CLOG .. ____          Switch PLOG .. ____

CLOG file size  BLKs 675          PLOG file size  BLKs 240
                  CYLs 5          CYLs 2
No logs available, current > 70%
CLOG# Stat writing BLK  %used          PLOG# Stat writing BLK  %used
-----
CLOGR1 F          100          PLOGR1 W    7    3
CLOGR2 W    501    74          PLOGR2 F          100

Stat ==>> A-Available W-Writing F-Completed(Copy needed) R-ADARES running

PF1----- PF2----- PF3----- PF4----- PF6----- PF8----- PF9----- PF12-----
Help          Exit          Refresh  CYL          PPT          Menu
    
```

The status of each dataset is indicated by the status of the first record of each of those datasets. The status field of each CLOG/PLOG dataset indicates if it is A-Available, W-Writing, F-Completed(Copy needed), or R-ADARES running.

The ALOG/CLOG/PLOG file size is shown in BLK, with a calculation for CYL. The PF6 key switches the display between a cylinder calculation and the standard blocks that Adabas uses. The %used calculation is always based on BLK. PF4 refreshes the information, issuing the necessary calls to gather it again. PF9 jumps to the display of the PPT information.

You can switch between the ALOG/CLOG and PLOG by typing YES in the indicated SWITCH field.

If the program detects an error, it shows a warning message. For example, in a dual clog/plog environment, if no CLOG/PLOG is available and the current log is greater than 70% used, the program shows the message No logs available, current > 70%. If the environment has more than 2

CLOGs/PLOGs but none of them are available, the program shows the warning message Warning: No logs marked available.

```

18:42:07          ***** A D A B A S  BASIC  SERVICES  *****          2023-09-01
DBID 1955          - CLOG/PLOG DATASET STATUS -          MACIM02

Switch CLOG .. ____          Switch PLOG .. ____

CLOG file size  BLKs 675          PLOG file size  BLKs 240
                  CYLs 5          CYLs 2
                  No logs available, current > 70%
CLOG# Stat writing BLK  %used          PLOG# Stat writing BLK  %used
-----
CLOGR1 W    216          32          PLOGR1 F          100
CLOGR2 F          100          PLOGR2 W    214          89

Stat ==>> A-Available W-Writing F-Completed(Copy needed) R-ADARES running

PF1----- PF2----- PF3----- PF4----- PF6----- PF8----- PF9----- PF12-----
Help          Exit          Refresh  CYL          PPT          Menu
    
```

In the example, for the CLOGs, CLOGR1 is currently being written, at writing block 216 of a total of 675 for the file. CLOGR2 has been completed (F) and has not been copied yet, 100% used, and is highlighted in red. For the PLOGs, PLOGR2 is being written, and is at 89% capacity, without PLOGR1 being available for use. This causes the program to issue the warning message No logs available, current > 70%.

If you select a DBID that is in a cluster/parallel nucleus environment, the display starts with the currently selected Nucid.

```

13:28:20          ***** A D A B A S  BASIC  SERVICES *****          2023-10-31
DBID 62900          - CLOG/PLOG DATASET STATUS -          MACIM02
Nuc 17031

Switch CLOG .. ____ Global ____          Switch PLOG .. ____ Global ____

CLOG file size  BLKs 675          PLOG file size  BLKs 240
                CYLs 5          CYLs 2

CLOG# Stat writing BLK  %used          PLOG# Stat writing BLK  %used
----- --
CLOGR1 F          100          PLOGR1 F          100
CLOGR2 F          100          PLOGR2 F          100
CLOGR3 F          100          PLOGR3 F          100
CLOGR4 F          100          PLOGR4 W    3          1
CLOGR5 W    3          1          PLOGR5 A
CLOGR6 A          PLOGR6 A
CLOGR7 A          PLOGR7 A
CLOGR8 A

Stat =>> A-Available W-Writing F-Completed(Copy needed) R-ADARES running

PF1----- PF2----- PF3----- PF4----- PF6----- PF8----- PF9----- PF12-----
Help      Next Nuc  Exit      Refresh  CYL          PPT      Menu

```

The status of each dataset, the log file sizes, and the function keys perform the same way as in a dual CLOG/PLOG environment. You can switch between the ALOG/CLOG and PLOG by typing YES in the indicated SWITCH field. In the cluster/parallel nucleus environment, you can also specify a Global switch to apply the command to all Nucids in that environment.

Press PF2 to switch to the next Nucid in the system. When more than 2 logs occur for an environment but no log is available, the program shows a warning message.

```

13:28:20          ***** A D A B A S  BASIC  SERVICES *****          2023-10-31
DBID 62900          - CLOG/PLOG DATASET STATUS -          MACIM02
Nuc 22021

Switch CLOG .. ___ Global ___          Switch PLOG .. ___ Global ___

CLOG file size  BLKs 675          PLOG file size  BLKs 240
                  CYLs 5                  CYLs 2
Warning: No logs marked available
CLOG# Stat writing BLK  %used          PLOG# Stat writing BLK  %used
-----
CLOGR1 F          100          PLOGR1 F          100
CLOGR2 F          100          PLOGR2 F          100
CLOGR3 F          100          PLOGR3 F          100
CLOGR4 W    3          1          PLOGR4 W    3          1
CLOGR5 F          100          PLOGR5 A

Stat ==>> A-Available W-Writing F-Completed(Copy needed) R-ADARES running

PF1----- PF2----- PF3----- PF4----- PF6----- PF8----- PF9----- PF12-----
Help      Next Nuc  Exit      Refresh  CYL          PPT      Menu

```

If you select a DBID that is an Auditing Server, the program provides information about the status of each ALOG instead of each CLOG:

```

19:37:19          ***** A D A B A S  BASIC  SERVICES *****          2023-09-01
DBID 1956          - ALOG/PLOG DATASET STATUS -          MACIM02

Switch ALOG .. ___          Switch PLOG .. ___

ALOG file size  BLKs 675          PLOG file size  BLKs 240
                  CYLs 5                  CYLs 2

ALOG# Stat writing BLK  %used          PLOG# Stat writing BLK  %used
-----
ALOGR1 F          100          PLOGR1 F          100
ALOGR2 W    9          1          PLOGR2 W    3          1

Stat ==>> A-Available W-Writing F-Completed(Copy needed) R-ADARES running

PF1----- PF2----- PF3----- PF4----- PF6----- PF8----- PF9----- PF12-----
Help          Exit      Refresh  CYL          PPT      Menu  ←

```

ALOG also replaces CLOG on the **Session Opercoms** menu. If you are using SAF for security, you must apply zaps to add the CLOG/PLOG function. For Adabas SAF Security version 8.3.1 apply AX831004 and for Adabas SAF Security version 8.4.1 apply AX841004.

Resetting Online Dump Status

Option **R (Reset ONLINE-DUMP-Status)** on the **Session Opercoms** menu is used to reset the online dump status for use when an ADASAV online dump operation has abended.

An equivalent direct command is:

```
RESET ONLINESTATUS
```

Stopping Users

Selecting option **S (Stop user(s))** on the **Session Opercoms** menu displays the **Stop Users** menu.

```

19:43:12          ***** A D A B A S BASIC SERVICES *****          2015-05-19
                   - Stop Users -                                     PACIS12

Code  Service                               Code  Service
-----
F    Stop users using file                   S    Stop all selected Secuid
I    Stop inactive users                     U    Stop a selected user
J    Stop users by jobname                   .    Exit
?    Help

Code ..... _
File Number ..... _____
Last Activity .... _____ (elapsed time in seconds)
Job Name ..... _____
Purge UQE(s) ..... N
With Resp 22/54 .. N
Selected Secuid ..                Selected Userid ..
Database ID ..... 1955           (WIS1955)

Command ==>
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help      Disp UQ   Exit      Clear UID                               Menu
    
```

You can stop a specific user, all users from a specific job, all users using a specific file, or all inactive users. Any open transactions of the stopped users are backed out. When the Purge UQE(s) field is set to "Y", the stopped users are also deleted. Note that EXF and UTI users are not stopped or deleted.

The following table describes what each of the screen options allows you to do and how to use them effectively:

Option	Description
F	<p>Stops all users who are using a specific file. When you use this option, specify the file number in the File Number field. This is the equivalent of running the Adabas STOPF operator command.</p> <p>The nucleus backs out all open transactions of any users of the file. If the Purge UQE(s) field is set to "Y", the stopped users are also deleted. If the Purge UQE(s) field is set to "N" or Adabas is running with ADARUN OPENRQ=YES, a stopped user who returns (by sending a command) will receive response code 9.</p> <p>Caution: If Adabas is running with ADARUN OPENRQ=NO (specifying that users are not required to issue an OP as the first command of the session), select this option with the Purge UQE(s) field set to "Y" only if you are certain that the users to be deleted are no longer active. If a user with an open transaction is deleted, but then returns (by sending a command), no indication is given about the transaction backout. If the user continues the transaction, logical inconsistencies in the database could occur.</p>
I	<p>Stops all users who have not executed a command during a specific time interval. When you use this option, specify the inactivity time (in seconds) in the Last Activity field. This is the equivalent of running the Adabas STOPI operator command.</p> <p>The nucleus backs out all open transactions of the affected users. If the Purge UQE(s) field is set to "Y", the stopped users are also deleted. If the Purge UQE(s) field is set to "N" or Adabas is running with ADARUN OPENRQ=YES, a stopped user who returns (by sending a command) will receive response code 9.</p> <p>Caution: If Adabas is running with ADARUN OPENRQ=NO (specifying that users are not required to issue an OP as the first command of the session), select this option with the Purge UQE(s) field set to "Y" only if you are certain that the users to be deleted are no longer active. If a user with an open transaction is deleted, but then returns (by sending a command), no indication is given about the transaction backout. If the user continues the transaction, logical inconsistencies in the database could occur.</p>
J	<p>Stops and deletes all users from a specific job. When you use this option, specify the job name in the Job Name field. This is the equivalent of running the Adabas STOPU operator command with a job name specified.</p> <p>The nucleus backs out any open transactions from the job and deletes the users (purges their user queue elements), regardless of the setting of the Purge UQE(s) field. No response code is issued, when the field With Resp 22/54 is set to "N"; the next time a stopped user issues a command, a new user queue element (UQE) is created.</p> <p>If the field With Resp 22/54 is set to "Y", this is the equivalent of running the Adabas STOPUR operator command with a job name specified.</p> <p>The nucleus backs out any open transactions from the job and deletes the users (purges their user queue elements), regardless of the setting of the Purge UQE(s) field. However, the stopped users are only deleted after they have issued a subsequent command and response code 22 (ADARSP22), subcode 54 has been issued in response to that command. This response code/subcode combination</p>

Option	Description
	<p>is used to notify users that their Adabas activity has been halted and their user session resources have been freed. Only after the response code/subcode combination has been issued will the user queue element of the stopped users be deleted.</p> <p>Caution: If Adabas is running with ADARUN OPENRQ=NO (specifying that users are not required to issue an OP as the first command of the session), select this option only if you are certain that the users to be deleted are no longer active. If a user with an open transaction is deleted, but then returns (by sending a command), no indication is given about the transaction backout. If the user continues the transaction, logical inconsistencies in the database could occur.</p>
S	<p>Stops and deletes all specific security user IDs. When you use this option, specify the security user ID (secuid) of the user you want to stop in the Selected Userid field. You can do this by selecting a user from the current user queue (select PF2 on this screen) and specifying "N" in the With Resp 22/54 field. This is the equivalent of running the Adabas STOPSU operator command with a security user ID specified.</p> <p>The nucleus backs out any open transaction of the user and deletes the user (purges the user queue element), regardless of the setting of the Purge UQE(s) field. No response code is issued; the next time a stopped user issues a command, a new user queue element (UQE) is created.</p> <p>If the field With Resp 22/54 is set to "Y", this is the equivalent of running the Adabas STOPSUR operator command with a security user ID specified.</p> <p>The nucleus backs out any open transactions from the job and deletes the users (purges their user queue elements), regardless of the setting of the Purge UQE(s) field. However, the stopped users are only deleted after they have issued a subsequent command and response code 22 (ADARSP22), subcode 54 has been issued in response to that command. This response code/subcode combination is used to notify users that their Adabas activity has been halted and their user session resources have been freed. Only after the response code/subcode combination has been issued will the user queue element of the stopped users be deleted.</p> <p>Caution: If Adabas is running with ADARUN OPENRQ=NO (specifying that users are not required to issue an OP as the first command of the session), select this option only if you are certain that the user to be deleted is no longer active. If a user with an open transaction is deleted, but then returns (by sending a command), no indication is given about the transaction backout. If the user continues the transaction, logical inconsistencies in the database could occur.</p>
U	<p>Stops and deletes a specific ET-ID user. When you use this option, specify the user ID (ET-ID) of the user you want to stop in the Selected Userid field. You can do this by selecting a user from the current user queue (select PF2 on this screen and then press PF6 to show ET-ID).</p> <p>The nucleus backs out any open transaction of the user and deletes the user (purges the user queue element), regardless of the setting of the Purge UQE(s) field. However, the stopped user is only deleted after they have issued a subsequent command and response code 22 (ADARSP22), subcode 54 has been issued in response to that command. This response code/subcode combination is used to notify users that their Adabas activity has been halted and their user session resources have been freed. Only after the response code/subcode combination has been issued will the user queue element of the stopped user be deleted.</p>

Option	Description
	Caution: If Adabas is running with ADARUN OPENRQ=NO (specifying that users are not required to issue an OP as the first command of the session), select this option only if you are certain that the user to be deleted is no longer active. If a user with an open transaction is deleted, but then returns (by sending a command), no indication is given about the transaction backout. If the user continues the transaction, logical inconsistencies in the database could occur.
?	access online help for this screen.
.	exit this screen.

The following table describes the use of the fields on this screen:

Field	Description
Code	Specify the code of the function you wish to perform, as described in the table above.
File Number	When selecting the F option (stop users of a specific file), specify the file number; all users of the file will be stopped.
Last Activity	When selecting the I option (stop inactive users), specify the inactivity time of the users (in seconds); users who have not executed a command during the specified time interval will be stopped.
Job Name	When selecting the J option (stop and delete users from a specific job), specify the job name; all users from that job will be stopped and deleted.
Purge UQE(s)	When selecting the F or I options specify (with "Y" or "N") whether the user queue elements (UQEs) of the stopped users should be purged. Users stopped via the J or U options are always purged. Caution: If Adabas is running with ADARUN OPENRQ=NO (specifying that users are not required to issue an OP as the first command of the session), select this option only if you are certain that the users to be deleted are no longer active. If a user with an open transaction is deleted, but then returns (by sending a command), no indication is given about the transaction backout. If the user continues the transaction, logical inconsistencies in the database could occur.
With Resp 22/54	When selecting the J , S , or U options specify (with "Y" or "N") whether the user queue elements (UQEs) of the stopped users should be purged or have a response 22, subcode 54, returned.
Selected Secuid	Lists the selected security user ID. To change the security user ID, press the PF2 key and select a new security user ID from the current user queue. To clear a security user ID from this field, press the PF4 key. If no specific user is listed in this field, all users are assumed. This field is used only when the S Code (stop a specific secuid) is selected.
Selected Userid	Lists the selected user ID. To change the user ID, press the PF2 key (and PF6 for ET-ID) and select a new user ID from the current user queue. To clear a user ID from this field, press the PF4 key. If no specific user is listed in this field, all users are assumed. This field is used only when the U Code (stop a specific user) is selected.
Database ID	Specify the database ID of the database for which the users are stopped.

The following special function keys are also available for use on this screen:

- Press PF2 (Disp UQ) to display the current user queue. You can select a user from the current user queue list.
- Press PF4 (Clear UID) to clear the Selected Userid field.

An equivalent direct command is:

STOP USERS

Termination Commands

Selecting option **T (Termination Commands)** on the **Session Opercoms** menu invokes the **Session Termination** menu from which you can choose to terminate a session normally (ADAEND), cancel a session immediately (CANCEL), or stop a session (HALT).

```

15:56:48          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
                  -  Session Termination  -                               PACT002

                Code      Service
                ----      -
                A         Normal session termination (ADAEND)
                C         Cancel session immediately (CANCEL)
                H         Stop session (HALT)
                ?         Help
                .         Exit
                ----      -

Code ..... _
Database ID .. 1955 (WIS1955)          NUCID .. 1021
                                   Global.. _

Current nr. of users in User Queue ... 1
Nr. of users with open transactions .. 0
Nr. of active nucs in Plex cluster ... 1

Command ==>
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit          Menu          ↵
    
```

In all cases, you are prompted to confirm your termination request before the action is taken.

An equivalent direct command is:

TERMINATE SESSION

Managing Online Utilities

Selecting option **U (Manage Online Utilities)** on the **Session Opercoms** menu displays the **Manage Online Processes** screen:

```

15:58:02          ***** A D A B A S  BASIC SERVICES  *****          2014-05-02
DBID 1955          - Manage Online Processes -          PACIP02

Total Processes...
Mark entries with 'S' (Suspend), 'R' (Resume), or 'X' (Stop):
  I      I Process I Sort I Current I Throw- I Process I
M I  FNR I   Type I Seq I RABN/ISN I Backs I   ID   I Status I
-----
_ I    50 I Reor Data I Phy I      3345 I      6 I 000003FC I Active I
_ I    61 I Invert DE I AA I      286 I      1 I 000003FF I Suspended I
_ I   101 I Reor Asso I BJ I           I      1 I 000000C2 I Active I
_ I      I           I   I           I           I           I           I
_ I      I           I   I           I           I           I           I
_ I      I           I   I           I           I           I           I
_ I      I           I   I           I           I           I           I
_ I      I           I   I           I           I           I           I
_ I      I           I   I           I           I           I           I
_ I      I           I   I           I           I           I           I
_ I      I           I   I           I           I           I           I
_ I      I           I   I           I           I           I           I
_ I      I           I   I           I           I           I           I

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help                Exit      Refresh  --      -      +      Menu
  
```

From this screen, you can manage (that is, monitor, suspend, resume, and stop) online utility processes.

All online processes currently in the database nucleus are listed, up to a maximum of 40. You can use PF6 (back to the start of the list), PF7 (back one screen), and PF8 (forward one screen) to scroll among the processes.

The equivalent direct command is:

```

DISPLAY PROCESS
  
```

To maintain the processes, enter one of the following maintenance codes in the M column to the left of the process named in the Process Type column:

Code	Description
S	Suspends an active process
R	Resumes a suspended process
P	Stops a process

You can maintain multiple processes at the same time.

The equivalent direct command is

`MANAGE PROCESS`

The sort sequence used by a process is indicated in the Sort Seq column:

For process type . . .	Sort Seq. contains the descriptor currently being . . .
reorder Data Storage	reordered*
invert descriptor	inverted
reorder Associator	reordered

* When reordering Data Storage for a file, the default sort sequence is physical sequence or "PHY". Other possible options include "ISN" if the file is to be sorted in ISN order, or the two character descriptor name to sort the file according to the value of the specified descriptor.

The Current RABN/ISN column shows the progress of work:

For process type . . .	Current RABN/ISN displays the current . . .
reorder Data Storage	RABN being processed
invert descriptor	ISN, as this function works in ISN sequence
reorder Associator	(left blank)

Maintaining the User Table



Note: This option is available in Adabas nucleus cluster environments only.

When option **V (User Table Maintenance)** is selected on the **Session Opercoms** menu, the **User Table Maintenance** menu appears:

```

15:58:04          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
                   - User Table Maintenance -                          PACIV02

                   Code      Service
                   ----      -
                   C         Begin CLUFREEUSER process
                   ?         Help
                   .         Exit
                   ----      -

Code ..... _
TNA ..... 0 _____
UID ..... _____
Force ..... _
Global ..... _

Database ID .. 1955 (WIS1955)          NucID .. 1021

Command ==>
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit          Menu          ↵
    
```

The CLUFREEUSER command is only valid in cluster environments. It can be issued against the local nucleus only or, with the Global option, against all active and inactive nuclei in the cluster.

The command is used to delete leftover user table elements (UTES) in common storage that are no longer associated with user queue elements (UQEs) in a nucleus where:

Screen Field	Description
TNA	A decimal number specifying the timeout value in seconds. UTes that are not used during the time specified may be deleted if other conditions are fulfilled. If TNA is not specified, UTes may be deleted without regard to their recent use.
UID	<p>A character string or hexadecimal byte string as follows:</p> <p>ccccccc where the argument is 1-8 letters, digits, or embedded '-' signs without surrounding apostrophes.</p> <p>'ccccccc' where the argument is 1-8 characters with surrounding apostrophes.</p> <p>X'xxxxxxxxxxxxxxxx' where the argument is an even number of 2-16 hexadecimal digits enclosed by apostrophes and preceded by an X.</p> <p>A character string must be enclosed in apostrophes if it contains characters other than letter, digits, or embedded '-' signs. If a specified character string is less than 8 characters long, it is implicitly padded with blanks. If a specified hexadecimal string is shorter than 16 hexadecimal digits, it is implicitly padded with binary zeros. If the last 8 bytes of a user's 28-byte communication ID match a specific user ID or user ID prefix, that user's UTE may be deleted</p>

Screen Field	Description
	if other conditions are fulfilled. If UID not specified, UTEs may be deleted regardless of their user IDs.
FORCE	Indicates whether leftover UTEs should be deleted even if the users are due a response code 9, subcode 20. If FORCE is not specified, such UTEs are not deleted. Before using the FORCE parameter, ensure that the users owning the UTEs to be deleted will not expect any of their transactions to remain open. Specify FORCE on this screen by marking the Force field with any character.
GLOBAL	Indicates whether leftover UTEs should be deleted throughout the Adabas cluster if they are no longer associated with UQEs and are eligible according to the other specified parameters. Additionally and subject to the other rules, delete leftover UTEs if their assigned nuclei have terminated since their last use. If GLOBAL is not specified, only UTEs assigned to the local nucleus and used since the nucleus start are eligible for deletion. Specify GLOBAL on this screen by marking the Global field with any character.

9 Reviewing the Database Report

■ Displaying Files with Critical Number of Extents	175
■ Displaying Field Definition Table (FDT)	175
■ Displaying Files	178
■ Displaying General Database Layout	185
■ Displaying Volume Serial Numbers for Database	187
■ Displaying ASSO/DATA/WORK Block (RABN)	188
■ Displaying Unused Storage	190
■ Displaying Used Storage	191

Selecting **Database report** (option **R**) from the **Main Menu** displays the **Database Report** menu:

Options on the **Database Report** menu provide information only; none of the displayed information can be changed. However, direct commands can be entered on this menu to invoke other Adabas Online System (AOS) functions for making changes.

Database Report functions provide both general and specific information in either table or report format. They correspond to selected functions of the Adabas ADAREP utility.

```

16:11:48          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
                   - Database Report -                               PDR0002

Code   Service
-----
C      List files with crit. no. of extents
D      Display field description table (FDT)
F      Display file(s)
G      General database layout
L      List VOLSER distribution of database
R      Display ASSO/DATA block (RABN)
U      Display unused storage
V      Display used storage (DSPACE)
?      Help
.      Exit
-----

Code ..... _
File No ..... 0_____ Password ..
Database ID .. 1955 (WIS1955)          VOLSER .. _____

Command ==>
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit          Menu          ↵
    
```

Options allow you to view database-level general information and tables of database files, files whose extents are at or near the allowable maximum, file-specific information for any file, physical database distribution by volume/serial number (VOLSER), and available space that is not currently being used. Additional displays are available using direct commands.

The **Database Report** provided in AOS includes the following information, selected using the appropriate option code, as follows:

Option	Function
C	<i>Displaying Files with Critical Number of Extents</i> shows a list of the files that have a critical number of extents.
D	<i>Displaying Field Definition Table (FDT)</i> shows the field definition table (FDT) and special descriptor table (SDT) for the specified file.
F	<i>Displaying Files</i> shows file(s), either a list of all files in the specified database or detailed information about a specific file.

Option	Function
G	<i>Displaying General Database Layout</i> shows the general layout of the specified database.
L	<i>Displaying Volume/Serial Numbers for Database</i> shows the volume/serial number layout of the specified database.
R	<i>Displaying ASSO/DATA/WORK Block (RABN)</i> shows Associator / Data Storage blocks (RABNs).
U	<i>Displaying Unused Storage</i> shows unused storage.
V	<i>Displaying Used Storage</i> shows how much space is defined and used for the Associator (ASSO) and Data Storage (DATA) areas of your databases.

Displaying Files with Critical Number of Extents

Option C (**List files with crit. no. of extents**) on the **Database Report** menu provides a list of the files in the database that are at the critical number of extents. If no such files exist in the database, a message is displayed.



Note: The exact extent count is provided in the general **Display File(s) (F) option** by table type (AC, NI, UI, or DS).

Displaying Field Definition Table (FDT)

Option D (**Display field description table (FDT)**) on the **Database Report** menu provides a list of the field definitions in the FDT. The Display FDT screen appears.



Note: For more detailed information about field definitions, read your Adabas ADACMP utility documentation; for more information about interpreting FDTs, read your Adabas ADAREP utility documentation. Both are available in the *Adabas Utilities* documentation.

```

16:12:15          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
DBID 1955          - Display FDT -                                     PDRD032

Field Description Table: File 1          (EMPLOYEES)
=====
Total Fields without SDT ... 30
***** T o p   o f   F D T *****
Lev  I Name I Leng  I Form  I      Options          I Predict Fld Name or DT / SY
-----I-----I-----I-----I-----I-----I-----
  1  I  AA  I  008  I   A  I  DE
  1  I  AB  I           I           I
  2  I  AC  I  020  I   A  I  NU
  2  I  AE  I  020  I   A  I  DE
  2  I  AD  I  020  I   A  I  NU
  1  I  AF  I  001  I   A  I  FI
  1  I  AG  I  001  I   A  I  FI
  1  I  AH  I  006  I   P  I  DE NC
  1  I  A1  I           I           I
  2  I  AI  I  020  I   A  I  MU NU
  2  I  AJ  I  020  I   A  I  DE NU
  2  I  AK  I  010  I   A  I  NU

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help      Disp SDT  Exit          --          -          +          Menu      ↵
    
```

For a specified file, option **D** displays the field definition table (FDT), which includes:

- the total number of fields in the file;
- the level number of each field;
- the two-character name of each field;
- the length of each field in bytes;
- the data type (format) of each field: Alphanumeric, Binary, Fixed point, floatinG point, Packed decimal, Unpacked decimal, or Wide-character;
- data definition options for each field: CK for untranslatable characters, Descriptor, Fixed storage, Long Alphanumeric, Multiple-value field, Null/not Counted (that is, SQL null representation), Null/Not allowed, NULL value suppression, NV no conversion, Periodic group (the fields that compose the periodic group are those that follow and have a higher level number), UniQue descriptor value;



Note: If an online inversion of a field is in process, this information is noted in the Options column. In addition, if the field has been deleted online, this information is noted in the Options column.

- equivalent Predict names, if any, for each field or, if the field is a date or time, the edit mask used for the field. A complete description of edit masks can be found in your Adabas documentation.

On the Display FDT screen, press PF2 to access the special descriptor table (SDT) for the file on the Display SDT screen:

```

16:12:50          ***** A D A B A S BASIC SERVICES *****          2014-05-02
DBID 1955          - Display SDT -          PDRD012

SUB-/SUPER Table: File 1      (EMPLOYEES)
=====

Type  I Name I Length I Format I Options          I Structure          I
-----I-----I-----I-----I-----I-----I-----I
SUPER I  H1  I   4   I   B   I DE NU          I AU ( 1 - 2 )I
      I   I   I   I   I   I   I AV ( 1 - 2 )I
PHON  I  PH  I   I   I   I   I DE          I PHON( AE )    I
SUB   I  S1  I   4   I   A   I DE          I AO ( 1 - 4 )I
SUPER I  S2  I  26   I   A   I DE          I AO ( 1 - 6 )I
      I   I   I   I   I   I   I AE ( 1 - 20 )I
SUPER I  S3  I  12   I   A   I DE NU PE       I AR ( 1 - 3 )I
      I   I   I   I   I   I   I AS ( 1 - 9 )I

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help      Disp FDT  Exit          --          -          +          MENU      ↵
    
```

The SDT provides field information about all sub-/super-/hyperdescriptors, collation descriptors, phonetic descriptors, and sub-/superfields for the file.

In addition to the field's special descriptor type, two-character name, length, format (data type), and data definition options, the SDT identifies the structure of the special descriptor; that is, the component fields and field bytes of sub-/super-/hyperdescriptors and sub-/superfields; the equivalent alphanumeric elementary fields of phonetic descriptors; and the associated user exit of collation descriptors.

The equivalent direct commands are:

```

DISPLAY FDT file-number
    
```

Displaying Files

If no particular file is specified, option **F (Display file(s))** on the **Database Report** menu lists all files in the specified database. If a file is specified, option **F** provides detailed layout information for the file. Physical device and file layout information is available only for a specific file.

This section covers the following topics:

- [Display a List of Files in the Specified Database](#)
- [Display Information for a Specific File](#)

Display a List of Files in the Specified Database

When no file number or "0" (zero) is specified in the `File No` field on the **Database Report** menu, a list of the files in the specified database is displayed on the `Display Files` screen:



Note: If a file was unsuccessfully loaded (ADALOD), stored (ADAORD) or restored (ADASAV) and the file number of the file is higher than the previous highest-loaded file number, then this file will not be shown until the next time the database is started. If you want to see the file specifics, run an ADAREP report.

```

16:13:21          ***** A D A B A S  BASIC  SERVICES  *****          2014-05-02
DBID 1955          - Display Files -          PDRF032
-----
Fnr  File Name      Loaded      Top-ISN      Max-ISN      Extents      Ind.      %Used
      YY-MM-DD
-----
  1  EMPLOYEES      09-02-17      1107         1695         1  1  1  1  NNISNNN  77  92
  2  SECURITY       12-09-12           2         2543         1  1  1  1  NNNSNNN  12   5
  3  MISCELLANEOUS  09-02-17      1779         2543         1  1  1  1  NNISNNN  86  53
  6  EXPANDED       09-02-17      1107         1600         1  1  1  1  NNISNXN  74  46
  7  EXPANDED       09-02-17      3107         3600         1  1  1  1  NNISNXN  74  46
  9  TEST-9         10-08-06           0         1695         1  1  1  1  NNNSNNN   0   0
 10  TRIGGER-FILE   09-02-17           1         1695         1  1  1  1  NNISNNN  23  10
 11  NAT-SYSTEM     09-02-17      99317        100063        1  1  1  1  NNISNNU  52  74
 12  NAT-USER       09-02-17       940         30527         1  1  1  1  NNISNNN  80  43
 13  NAT-FDIC       09-02-17        47          5087         1  1  1  1  NNISNNN  33  14
 14  SPAN-TEST-14  13-08-30           1         1695         1  1  1  1  NNNSNNN  55   5
 19  CHECKPOINT     10-12-14      25334        26287         1  1  1  2  NNNSNNN   2  86
 20  FILE-1955-20  09-03-04        16          1695         1  1  1  1  NNNSNNN   0  20
 21  FILE-1955-21  09-03-04         7          1695         1  1  1  1  NNNSNNN   0  10
-----
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help      Repos      Exit      Extents    --      -      +      Menu      ←
    
```

The **PF2 (Reposition)** key displays a window in which you can enter a new starting value for the file list. When you enter a file number, the `Display Files` list begins with that file.

If the extents (NI, UI, AC, and DA) listed on this screen exceed 99 and you want to see their actual values or if you would like to see the value of any secondary AC extent, press the PF4 (Extents) key. The window changes slightly to show the expanded values of the extents, although, due to screen space, the indicators are removed.

The Display Files screen provides the following information for each file:

- file number and file name;
- date the file was loaded into the database;
- highest ISN currently in use in the file and the highest ISN allowed in the file;
- number of logical extents currently assigned: by Associator (*N* ormal index; *U* pper index; *A* ddress converter) and *D* ata Storage.
- block padding factor percentage defined for the Associator and for Data Storage;
- indicators as follows:

Indicator	Description
A	ADAM option: A = ADAM ISN- or descriptor-selected file; N = non-ADAM file.
C	coupled (C) or non-coupled (N) file.
I	ISNs are reusable (I) or not (N).
S	Data Storage blocks are reusable (S) or not (N).
E	data files are ciphered/encrypted (E) or not (N).
X	files are expanded (X) or normal (N).
U	USERISN option: U = option is in effect for the file; N = option is not in effect.

- percentage of allocated space currently used by the file in the Associator and in Data Storage.

The equivalent direct command is

`DISPLAY FILE`

Display Information for a Specific File

When a valid file number is specified on the **Database Report** menu, the following Display File Layout screen appears for that file (some of the items shown on the following sample screen only appear if those features are activated or used):

Reviewing the Database Report

```
16:17:01          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
DBID 1955          - Display File Layout -                               PDRF043
*****
* File 3          * MISCELLANEOUS
*****

Records loaded ..... 1779          Date loaded ..... 2009-02-17 19:08:00
TOP ISN ..... 1779          Date of last update .. 2010-12-14 11:30:19
Max ISN expected ... 2543          Max Compr Rec Lngth .. 5060
Minimum ISN ..... 1          Asso/Data Padding .... 10%/10%
Size of ISN ..... 3 Bytes          Highest Index Level .. 3
Number of Updates .. 0          RPLUPDATEONLY. No
ISN Reusage ..... Yes          USERISN ..... No    PGMREFRESH ..... No
Space Reusage ..... Yes          MIXDSDEV ..... No    NOACEXTENSION .. No
ADAM File ..... No          Spanned rec .. No    MU/PE indices .. 1
Ciphred File ..... No          Replication .. No    Privileged Use . No
Coupled Files ..... None
Blk per DS Extent .. 0          Logged DSF Changes ... DS AC Index
Blk per UI Extent .. 0          Total Changed Blks ... 87
Blk per NI Extent .. 0          Multi Client File .... 0
                                Press Enter to display more information
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit          Refresh          Menu          ↵
```

```
16:17:18          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
DBID 1955          - Display File Layout -                               PDRF043
*****
* File 3          * MISCELLANEOUS
*****
                                Page 2

Last format AC ISN .. 2543
File readonly mode .. No          Date FDT modified .... 2009-08-25 02:05:08
FDT deleted field ... No
File has l/c fields . No
FDT has F,8 field ... No
FDT w/datetime mask . No
FDT w/system fields . No          SYFMAXUV value ..... 0

Free space available for file extents: At least 134 Extents

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit          Refresh          Menu          ↵
```

```
16:17:40          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
DBID 1955          - Display File Layout -                               PDRF043
```

File has LOB Fields, Related file number 0

```
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit       Refresh          Menu          ↵
```

```
16:17:57          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
DBID 1955          - Display File Layout -                               PDRF052
File 3
```

	I	Dev	Li	Space allocated	I	From	To	I	Unused		
	I	Type	Ty	Blocks / Cyls.	I	RABN	RABN	I	BLOCKS / Cyls.		
----	I		I	-----	I	-----	-----	I	-----		
	I		I		I			I			
ASSOI	3390	ACI		3 0	I	5227 -	5229	I	0		0
ASSOI	3390	UII		5 0	I	5261 -	5265	I	0		0
ASSOI	3390	NII		31 0	I	5230 -	5260	I	5		0
	I		I		I			I			
DATAI	3390	DSI		100 0	I	71 -	170	I	47		0

```
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit       Refresh          Menu          ↵
```

The information for the file can be refreshed by pressing PF4. You can display additional information about UES codes, coupling, LOB file/fields and space allocations by pressing Enter.

The equivalent direct command is:

`DISPLAY FILE file-number`

The Display File Layout screen displays the following kinds of information for the file:

- the file number and name;
- the number of records currently contained in the file;
- ISN information: the highest ISN currently used in the file; the highest ISN planned for the file (see the ADALOD utility's MAXISN parameter); the lowest ISN that can be assigned to a record in the file (see the ADALOD utility's MINISN parameter); whether 3- or 4-byte ISNs are used for the file; and whether ISNs can be reused.
- the total number of updates since the file was last loaded;
- other file option settings: whether Data Storage space can be reused; whether the file was loaded with the ADAM option, the cipher option, the USERISN option; whether the file is physically coupled to another file; whether Data Storage extents can be on different device types; whether the file can be refreshed using the E1 command; whether the file permits the MAXISN setting to be increased.
- the number of blocks allowed per Data Storage, upper index, and normal index extent;
- the date and time the file was last loaded;
- the date and time of the last update to the file;
- the maximum compressed record length permitted for the file (see the ADALOD utility's MAXRECL parameter);
- the padding factor for the Associator and for Data Storage;
- the highest index level currently active for the file;
- whether the file may be updated only by the Event Replicator Server as part of Adabas-to-Adabas replication or by other means as well (RPLUPDATEONLY);
- whether or not index compression is turned on for the file;
- whether universal encoding support (UES) is being used;
- whether the file contains spanned records;
- the number of MU/PE indices in the file;
- whether replication has been activated for the file;
- the DSF changes being logged for the file;
- the total number of blocks in the file that have been changed by updates since the file was last loaded;
- the length of the owner ID for multiclient files.
- the maximum number of occurrences of MU system fields that can be stored in the file.

If the file is a spanned file, the following additional information will be displayed in the sequence of Display File Layout screens:

```

19:03:36          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
DBID 1955          - Display File Layout -                               PDRF043

TOP AC2 ISN ..... 4
Max AC2 ISN ..... 1695
Min AC2 ISN ..... 1
Last formatted AC2 ISN ... 1695

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit       Refresh   Span cnt          Menu          ↵
    
```

When universal encoding support (UES) is being used, the following additional information will be displayed in the sequence of Display File Layout screens:

```

15:33:00          ***** A D A B A S  BASIC  SERVICES *****          2009-08-25
DBID 1955          - Display File Layout -                               PDRF012

Universal Encoding Support enabled for this file

Encoding Keys:
File Alpha Code ..... 37
File Wide Code ..... 4095
User Wide Code ..... 4095
    
```

If LOB flags are set, the following additional information will be displayed in the sequence of Display File Layout screens:

Reviewing the Database Report

```
16:52:35          ***** A D A B A S  BASIC  SERVICES *****      2009-08-25
DBID 1955          - Display File Layout -                          PDRF042
```

```
LOB File, Related file number  29
```

```
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help                Exit       Refresh                Menu      ↵
```

or

```
16:17:40          ***** A D A B A S  BASIC  SERVICES *****      2014-05-02
DBID 1955          - Display File Layout -                          PDRF043
```

```
File has LOB Fields, Related file number  29
```

```
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help                Exit       Refresh                Menu      ↵
```

If the file is part of an expanded file chain, the following information will be displayed at the top of the first Display File Layout screen:

```
>> Part of Expanded File Chain      <<
>> Anchor file          = 6          <<
>> Last file of Expanded File Chain << ↵
```

Displaying General Database Layout

Option **G (General database layout)** on the **Database Report** menu displays general database information on the Display General DB-Layout screen.

The equivalent direct command is

```
DISPLAY DBLAYOUT
```

```
19:14:01          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
DBID 1955          - Display General DB-Layout -                          PDRG012

Database Name ..... WIS1955
Database Number ..... 1955
Database Version ..... 8.3
Database Load Date ..... 2010-12-14 11:29:33

System Files ..... 19 , 2 , 10 , 0 , 0 , 0 , 0
Maximum Number of Files .. 1000
Number of Files Loaded ... 33
Highest File Loaded ..... 400
Trigger File Number ..... 10

Size of RABN ..... 3 Bytes
Current Log Tape Number .. 429
Delta Save Facility ..... Inactive          Replication Facility ..... Yes
Recovery Aid Facility ... Inactive
Universal Encoding Sup. .. Inactive

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help                Exit                Menu                ↵
```

You can display additional information about UES codes, coupling, and space allocations by pressing **Enter**.

The Display General DB-Layout screen displays the following information for the file:

- the name and number of the database;
- the version level of the Adabas database software;
- the date and time the database was loaded;
- the numbers of Adabas system files allocated to the database;

- the maximum number of files permitted for the database; the total number of files currently loaded; and the highest file number currently in use;
- whether 3- or 4-byte RABNs are being used for the file;
- the number of the most recent data protection log tape for the database;
- whether the Adabas Delta Save Facility and/or the Adabas Recovery Aid (ADARAI) are active or inactive for the database.
- whether universal encoding support (UES) is being used.

When universal encoding support (UES) is being used, pressing ENTER from the initial Display General DB-Layout screen lists the current code values:

```

15:51:22      ***** A D A B A S  BASIC  SERVICES  *****      2006-07-20
DBID 105          - Display General DB-Layout -                PDRG002

Universal Encoding Support Enabled

UES Encoding Keys:
Alpha File Encoding ..... 37
Wide File Encoding ..... 4095
Alpha ASCII Encoding ..... 437
Wide User Encoding ..... 4095
    
```

In any case, pressing Enter from the initial Display General DB-Layout screen displays the following space allocation and usage information:

```

19:14:42      ***** A D A B A S  BASIC  SERVICES  *****      2014-05-02
DBID 1955          - Display General DB-Layout -                PDRG012

      IDeviceI      Total Number of      I      Extents      in Block      I DD-Names I
      I Type I      Blocks / Cyls. I      From      To      I      I
-----I-----I-----I-----I-----I-----I-----I-----I
      I      I      I      I      I      I      I      I      I
ASSO I 3390 I      53982      200 I      1      53982 I DDASSOR1 I
      I      I      I      I      I      I      I      I      I
DATA I 3390 I      44990      300 I      1      44990 I DDDATAR1 I
DATA I 3390 I      44999      300 I      44991      89989 I DDDATAR2 I
      I      I      I      I      I      I      I      I      I
WORK I 3390 I      8091      60 I      1      8091 I DDWORKR1 I

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit          Menu          ↵
    
```



```

19:15:53          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
DBID 1955          - List File Extents on VOLSER -                      PDRLO22

VOLSER = SMSZ11

I ASSO/ I   From      I   To          I Device I File  I Table  I
I DATA I   Rabn        I   Rabn          I Type  I Nr.   I Type  I
I-----I-----I-----I-----I-----I-----I-----I
I ASSO  I           5031 I           5048 I  3390  I    0  I  DSST  I
I       I           5049 I           5066 I  3390  I    0  I  DSST  I
I       I           5099 I           5100 I  3390  I    1  I   AC   I
I       I           5101 I           5185 I  3390  I    1  I   NI   I
I       I           5186 I           5198 I  3390  I    1  I   UI   I
I       I           5199 I           5201 I  3390  I    2  I   AC   I
I       I           5202 I           5221 I  3390  I    2  I   NI   I
I       I           5222 I           5226 I  3390  I    2  I   UI   I
I       I           5227 I           5229 I  3390  I    3  I   AC   I
I       I           5230 I           5260 I  3390  I    3  I   NI   I
I       I           5261 I           5265 I  3390  I    3  I   UI   I
I       I           5266 I           5267 I  3390  I    6  I   AC   I

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help                Exit                Menu      ↵
    
```

Displaying ASSO/DATA/WORK Block (RABN)

Option **R (Display ASSO/DATA block (RABN))** on the **Database Report** menu invokes the Read ASSO/DATA Block screen.

The equivalent direct command is

```

DISPLAY RABN
    
```

```

19:16:23          ***** A D A B A S BASIC SERVICES *****          2014-05-02
DBID 1955          - Read ASSO/DATA Block -                          PDRR002

Type .. _          RABN No .... _____ Offset .. 0000
                   Hex RABN ... 00000000
0000 00000000 00000000 00000000 00000000
0000 00000000 00000000 00000000 00000000
0000 00000000 00000000 00000000 00000000
0000 00000000 00000000 00000000 00000000
0000 00000000 00000000 00000000 00000000
0000 00000000 00000000 00000000 00000000
0000 00000000 00000000 00000000 00000000
0000 00000000 00000000 00000000 00000000
0000 00000000 00000000 00000000 00000000
0000 00000000 00000000 00000000 00000000
0000 00000000 00000000 00000000 00000000
0000 00000000 00000000 00000000 00000000
0000 00000000 00000000 00000000 00000000
0000 00000000 00000000 00000000 00000000
0000 00000000 00000000 00000000 00000000
0000 00000000 00000000 00000000 00000000
Enter RABN details and press 'Enter' to display
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit          Menu          ↵

```

On this screen, enter a RABN type ("A" for Associator or "D" for Data Storage) and a RABN number (in either decimal or hexadecimal format) to display a screen similar to the following:

```

19:18:28          ***** A D A B A S BASIC SERVICES *****          2014-05-02
DBID 1955          - Read ASSO/DATA Block -                          PDRR002

Type .. A (ASSO)   RABN No .... 5150_____ Offset .. 00F0
                   Hex RABN ... 0000141E
00F0 0000E90D C4D44000 00000000 0062000F * Z?DM      Â ? *
0100 02020000 F3000136 0DC4D440 00000000 * ?? 3 ???DM *
0110 00006200 0F030100 00F60DC4 D4400000 * Â ??? 6?DM *
0120 00000000 62100F03 01000120 0DC4D440 * Â???? ???DM *
0130 00000000 00006250 0F050100 018B0DC4 *      Â&??? ?>>?D *
0140 D4400000 00000000 64000F03 010000E2 * M      À ??? S *
0150 0DC4D440 00000000 00006400 0F040100 * ?DM    À ??? *
0160 018B0DC4 D4400000 00000000 64100F02 * ?>>?DM À ??? *
0170 01000120 0DC4D440 00000000 00006450 * ? ???DM  Â& *
0180 0F010100 00DE0DC4 D4400000 00000000 * ??? ?DM *
0190 64600F01 0100018D 0DC4D440 00000000 * À-??? ?ý?DM *
01A0 00006480 0F010100 012D0DC4 D4400000 * ÀØ??? ???DM *
01B0 00000000 65000F03 010000D2 0DC4D440 *      Á ??? K?DM *
01C0 00000000 00006540 0F010200 012F0001 *      Á ??? ?? ? *
01D0 7E0DC4D4 40000000 00000065 500F0101 * =?DM    Á&??? *

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit          RABN+1          -          +          Menu          ↵

```

Option **R** displays two-doubleword-per-screen rows of the specified RABN block from the Associator or Data Storage in hexadecimal format. Both the hexadecimal data and its alphanumeric equivalent are displayed. If the block is not assigned, zeros are displayed.

The blocks are displayed in the length of the Associator or Data Storage block length.

You can scroll through the RABN display using the PF7 (scroll backward) and PF8 (scroll forward) keys. When using DISPLAY RABN, the offset switches to FFxx when you page past end-of-block. The display just continues to show the next block, until the offset reaches FFFF, when it returns to the first page.

You can display information for the next highest RABN (that is, the current RABN number plus one) by pressing PF4.

If the ADARUN AOSLOG parameter is set to "YES" and you access this screen, a message is printed to DDPRINT that includes the SECUID, type of RABN (ASSO, DATA or WORK), and the RABN number. This message looks like this:

```
***** A O S / UTILITY OPERATOR COMMAND ***** SECUID=secuid
yyyy-mm-dd hh:mm:ss DISPLAY type RABN rabn ↵
```

Displaying Unused Storage

Option **U** (**Display unused storage**) on the **Database Report** menu displays a table of unused storage within the database. The Display Unused Storage screen appears.

The equivalent direct command is

```
DISPLAY UNUSED
```

```

19:18:49          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
DBID 1955          - Display Unused Storage -          PDRU012

      I Device I      Total Number of      I Extent      in Blk.  I
      I Type  I      Blocks      /  Cyls.  I from      -      until  I
-----I-----I-----I-----I-----I-----I-----I-----I
DATA  I 3390 I          10          0 I      50783 -      50792 I
      I 3390 I          37490         249 I      52500 -      89989 I
-----I-----I-----I-----I-----I-----I-----I-----I
ASSO  I 3390 I          31          0 I      20889 -      20919 I
      I 3390 I          29291         108 I      24692 -      53982 I

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit      DSpace          Menu      ←
  
```

Separately for the Associator and Data Storage extents, the table shows the device type where the unused blocks are located, the number of unused storage blocks and cylinders, and the range of unused block numbers.

Displaying Used Storage

Option **V (Display used storage (DSPACE))** on the **Database Report** menu displays how much space is defined and used for the Associator (ASSO) and Data Storage (DATA) areas of your databases.. The Display Used Space screen appears.

The equivalent direct command is

```

DISPLAY DSPACE
  
```

Reviewing the Database Report

```
19:19:11          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
DBID 1955          -  Display Used Space  -          PDRV002

----- ASSO -----
Percent.. 45%
Bytes
  Used ..          62,735,040
  Alloc .          137,330,208
Blocks
  Used ..          24,660
  Alloc .          53,982
Cylinders
  Used ..           92
  Alloc .           200

----- DATA -----
Percent.. 58%
Bytes
  Used ..          265,804,296
  Alloc .          455,704,296
Blocks
  Used ..          52,489
  Alloc .          89,989
Cylinders
  Used ..          350
  Alloc .          600

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit      Refresh          Menu          ↵
```

This screen shows how much space is used and defined for the Associator and Data Storage areas of your database.

10

Calculating Space Requirements

▪ Estimating Associator Space	195
▪ Estimating Sizes for Directory and Data Structures in a Cluster Environment	197
▪ Estimating Data Storage Space	201
▪ Estimating Space for the DD/FILEA Sequential Data Set	202
▪ Estimating Sort Data Set Space	203
▪ Estimating TEMP Data Set Space	207
▪ Estimating Work Data Set Space	211

Option **S (Space calculation)** on the **Main Menu** displays the **Space Calculation** menu:

```

15:59:09          ***** A D A B A S BASIC SERVICES *****          2014-05-02
- Space Calculation -          PSP0002

          Code      Service
          ----      -
          A         ASSO
          C         Cluster-Cache/Lock
          D         DATA
          F         DDFILEA
          S         SORT
          T         TEMP
          W         WORK
          ?         Help
          .         Exit
          ----      -

Code ..... _
Database ID ... 1955 (WIS1955)

Command ==>
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help           Exit           Menu           ↵
    
```

The space calculation function is a planning tool for adding new components or recalculating existing space requirements. Each calculation provides a block or cylinder estimate according to information you provide. In general, you must provide the:

- maximum estimated record count;
- average number of MU or PE occurrences, when used as descriptors;
- average descriptor, compressed record, or normal record length;
- estimated padding factor;
- device type where the Adabas component being estimated resides.

In many cases, the results are "best guess" estimates; other than a device type, no defaults are assumed. Because no values are actually changed by the Space Calculation function, unrealistic estimates cause no harm.

Calculations are provided in both cylinders and blocks. In some cases, the block values are required by other Adabas Online System/Basic Services functions such as [Define New File](#) or [Modify File Parameters](#). All values are lost when you exit from the estimating function, regardless of the cause of the exit. You may want to write down any values you wish to use later.

By changing individual estimated values one at a time, you can see the effect on the calculated result. For example, you can change the device type without re-entering the other values; the revised estimate for that device appears when you press `Enter`.

There are equivalent direct commands for each space calculation function.

Space calculations are selectable by code and include:

Code	Function
A	<i>Estimating Associator Space</i>
C	<i>Estimating Sizes for Directory and Data Structures in a Cluster Environment</i>
D	<i>Estimating Data Storage Space</i>
F	<i>Estimating Space for the DD/FILEA Sequential Data Set</i>
S	<i>Estimating Sort Data Set Space</i>
T	<i>Estimating Temp Data Set Space</i>
W	<i>Estimating Work Data Set Space</i>

Estimating Associator Space

Option **A (ASSO)** on the **Space Calculation** menu calculates one of two Associator component values: the address converter (AC) space, or the normal (NI) and upper (UI) index space.

The equivalent direct command is

```
CALCULATE ASSO
```

The **ASSO Space Calculation** menu appears.

Calculating Space Requirements

```
15:59:35          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
                                     - ASSO Space Calculation -          PSPA002

                                     Code      Service
                                     ----      -
                                     A        Address Converter
                                     I        Normal/Upper Index
                                     ?        Help
                                     .        Exit
                                     ----      -

Code .....
Database ID ... 1955  (WIS1955)

Command ==>
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit                               Menu          ↵
```

AC space is based on the device type and the estimated number of records in the related Data Storage file.

```
15:59:53          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
DBID 1955          - Address Converter -          PSPAA02

Maximum number of records ... 0
ASSO Device-Type ..... 3390
Block Size ..... 2544

Required number of blocks ... 0
Required number of cyls. .... 0

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit                               Menu          ↵
```

NI/UI calculates index values for a *single* descriptor, requiring you to estimate such things as the average descriptor length, the number of multiple descriptors you expect to have, the total number of unique descriptor values for that field, an Associator padding factor, and a device type if other than the default.

```

16:00:14          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
DBID 1955          -   Normal/Upper Index  -                               PSPAI02

Computation for one Descriptor  -

Maximum number of records for the file ..... 0
Average number of DE-values per record ..... 1.0
Average length of DE-value in bytes ..... 0
Number of different DE-values in the file ..... 0

Padding factor for ASSO ..... 10 %
ASSO Device Type ..... 3390
ASSO Block Size ..... 2544

                                I Normal Index I Upper Index I
I-----
I Required number of blocks I          0 I          0 I
I Required number of cyls. I          0 I          0 I
I-----

Use ? for Help

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit          Menu
0              07,055      ←

```

Estimating Sizes for Directory and Data Structures in a Cluster Environment

Option C (**Cluster-Cache/Lock**) on the **Space Calculation** menu calculates the estimated sizes for directory and data structures in a cluster environment. The cache structure should be made large enough to provide sufficient space:

- for tracking all blocks kept in the buffer pools of all connected cluster nuclei (directory elements) and
- for keeping all changed blocks until they are written to the database (data elements).

The assignment of total cache space into directory and data elements is done via the `DIRRATIO` and `ELEMENTRATIO` ADARUN parameters.

Calculating Space Requirements

```

16:00:40          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
DBID 1955          -  Cache Structure Calculator  -                      PSPC002

Smallest block size in DB ..... 2544
Largest block size in DB ..... 5724
Buffer pool size (LBP) ..... 80896_____
Size proper for caching blocks .. 100000_____
Max nuclei in cluster ..... 3
Directory element size ..... 400
Cache structure size (in KB) .... _____

For minimum calculation, leave cache structure size field empty.
Modify values, press Enter to provide estimates below.

Cache CFM SIZE/INITSIZE ..... 2650          ( 2.5          MB)
ADARUN DIRRATIO ..... 67
ADARUN ELEMENTRATIO ..... 48
Cache directory elements ..... 135
Cache data elements ..... 97
Cache data element size ..... 1024

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit          Lock          Menu          ↵

```

Input fields:

Field	Description
Smallest block size	Value between 1024 and 32768. Default taken from current AOS DBid.
Largest block size	Value between 1024 and 32768. Default taken from current AOS DBid. If Smallest block size exceeds this value, then Smallest block size is swapped in.
Buffer pool size	Value between 80,000 and 999,999,999,999. Default taken from LBP parameter of current AOS Dbid.
Size proper for caching blocks	Value between 100000 - 999,999,999,999. Default taken from LBP parameter of current AOS Dbid, rounded down to nearest 100000. "Size proper" means that this does not include the overhead in the cache structure required for administering these blocks. Thus this value specifies how much space should be available in the cache structure for keeping changed blocks between buffer flushes and for buffering blocks so that the cluster nuclei do not have to read them from the database.
Max Nuclei in cluster	Value between 2 and 32. Defaults to 3.
Directory element size	Value between 100 and 999. Specifies how much space (including the overhead for the access paths) each directory element will take in the cache structure. Defaults to 400.
Cache Structure size	Blank for minimum calculation, or a value between 100 and 999,999,999 (KB). Although this value is given as an output field, you may want to propose a cache structure size, to see how to allocate the cache space (dir & data elements).

Output fields:

Field	Description
Cache CFRM SIZE/INITSIZE	The recommended cache structure SIZE or INITSIZE specification in the coupling facility resource management policy.
ADARUN DIRRATIO/ELEMENTRATIO	The recommended ADARUN parameter settings for the cluster nuclei.
Cache directory/data elements	The estimated directory and data element counts resulting from the SIZE/INITSIZE, DIRRATIO, and ELEMENTRATIO settings.
Cache data element size	This (accurate) value depends only on the largest Asso/Data/Work block size in the database.

By pressing PF4, you can use the Lock Structure Calculator.

Lock Structure Calculator

The Lock Structure Calculator screen calculates an estimated size for the Cache CFRM SIZE or INITSIZE specification in the coupling facility resource management policy.

The lock structure must be made large enough to provide sufficient space

- for keeping the lock record elements for all locks held at the same time, and
- for avoiding too much false contention on lock structure size as an input field.

The Number of lock table entries and record elements are shown for comparison with the related cluster nucleus message (ADAX70) and to aid users' own calculations.

Calculating Space Requirements

```
16:28:17          ***** A D A B A S  BASIC  SERVICES *****          2021-05-26
DBID 1958          -   Lock Structure Calculator   -                   PSPL002
```

```
Cluster/Parallel Services (C/P) ..... C
Max files in database (MAXFILES) ..... 100
Max number of parallel users (NU) ..... 200_____
Number of hold queue elements (NH) ... 1600
Number of threads (NT) ..... 5
Unique descriptor pool size (LDEUQP) .. 50000
Lock record element size ..... 400
Lock structure size (in KB) .....
```

For minimum calculation, leave lock structure size field empty.
Modify values, press Enter to provide estimates below.

```
Lock CFRM SIZE/INITSIZE ..... 3413          ( 3.3          MB)
Number of lock table entries ..... 32768
Number of lock record elements ..... 6831          Required min .. 6238
```

```
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help                Exit          Cache                Menu                ↵
```

Input fields:

Field	Description
Cluster/Parallel Services	Value is C or P, default taken from current DBID for SYSAOS.
Max files in database	Value between 3 and 5000. The same as MAXFILES parameter of ADADEF and ADAORD. Taken from the current AOS DBID.
Max number of parallel users	Value between 20 and 16,777,215. Default taken from NU parameter of current AOS DBID.
Number of hold queue elements	Value between 20 and 16,777,215. Default taken from NH parameter of current AOS DBID.
Number of threads (NT)	Value between 4 and 250. Default taken from NT parameter of current AOS DBID.
Unique descriptor pool size	Value between 1 and 999,999,999. Default taken from LDEUQP parameter of current AOS DBID.
Lock record element size	Value between 100 and 999. Specifies how much space (including the overhead for the access paths) each lock record element will take in the lock structure. Defaults to 400.
Lock structure size	Blank for minimum calculation, or a value between 100 and 9,999,999 (KB). Although this value is given as an output field, you may want to propose a lock structure size, to see the estimated number of lock table entries and lock table elements.

Output fields:

Field	Description
Lock CFRM SIZE/INITSIZE	The recommended lock structure SIZE or INITSIZE specification in the coupling facility resource management policy.
Number of lock table entries	The calculated count of lock table entries resulting from the SIZE/INITSIZE setting.
Number of lock record elements	The estimated count of lock record elements resulting from the SIZE/INITSIZE setting. One has to actually start a cluster nucleus with the specified parameters to see how many lock record elements it gets from the lock structure. The number on the right side is the minimum number of lock record elements that the starting cluster nuclei require to be available.

Estimating Data Storage Space

Option **D (DATA)** on the **Space Calculation** menu calculates Data Storage based on values you provide for estimated maximum record count, the average length of a compressed record, a Data Storage padding factor, and device type. Results are specified in both blocks and cylinders.

The equivalent direct command is

```
CALCULATE DATA
```

The Data Storage screen appears.

Calculating Space Requirements

```
16:04:06          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
DBID 1955          -  Data Storage  -          PSPD002
```

```
Maximum number of records for the file .. 0_____
Average compressed record length ..... 0
Padding factor for DATA ..... 10 %
DATA device-type / blk. size ..... 3390 / 5064
```

```
Required number of blocks ..... 0
Required number of cyls. .... 0
```

```
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help                Exit                Menu                ↵
```

Estimating Space for the DD/FILEA Sequential Data Set

Option **F (DDFILEA)** on the **Space Calculation** menu calculates the space required for the DD/FILEA sequential data set when it is used with the ADAORD utility. (The data set is also used with the ADALOD utility.)

The equivalent direct command is

```
CALCULATE DDFILEA
```

The DDFILEA Storage screen appears.

```

16:04:25          ***** A D A B A S BASIC SERVICES *****          2014-05-02
                  - DDFILEA Storage -                               PSPF012
                  Code Reorder                                     Maximum Space Required
                  -----
DB -Function   :   A   Asso
                  B   Data                                     Bytes .....
                  C   DB                                       Blocks ....
                  D   Restruct DB                               Cylinder ..
FILE -Function :   E   FAsso                                     Blocksize ..
                  F   FData
                  G   File
                  H   Restruct File
                  .   Exit
                  -----
Code ..... _
File .....
Device ... 3390
DB-ID .... 1955 (WIS1955)

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit          Menu          ↵

```

Estimating Sort Data Set Space

Option **S (SORT)** on the **Space Calculation** menu displays the **SORT Storage** menu:

```

16:04:43          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
                   -  SORT Storage  -                               PSPS002

                   Code      Service
                   ----      -
                   I         ADAINV
                   L         ADALOD load
                   U         ADALOD update
                   ?         Help
                   .         Exit
                   ----      -

Code ..... _
File Number ..
Database ID .. 1955  (WIS1955)

Command ==>
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help                Exit                                Menu                ↵

```

The functions on this menu are used to estimate the storage needed on the sort data set for the utility function chosen.

This section covers the following topics:

- [ADAINV Sort Size](#)
- [ADALOD LOAD Sort Size](#)
- [ADALOD UPDATE Sort Size](#)

ADAINV Sort Size

Option **I (ADAINV)** on the **SORT Storage** menu displays the **Sort Storage - ADAINV** screen. The storage needed on SORT for the ADAINV utility function is estimated using this screen.

```

16:05:04          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
                   -  SORT Storage          -  ADAINV  -          -          PSPSS22

File Number ..... 29
Number of records ( Default: TOPISN ) ..... (reduce number
Name of the field to be processed ..... if field is NU)
Average compressed descr. length (in Bytes)
of the biggest descriptor .....
Occurrences of periodic groups ..... 1
Occurrences of multiple fields ..... 1
SORT device-type ..... 3390
LWP-parameter ..... 1000000
Database-ID ..... 1955
Password (if required) .....
-----
Required number of blocks (minimum) .....
Required number of cyls. (minimum) .....

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit       Dis Field          Menu          ↵
    
```

PF4 (**Dis Field**) invokes a field selection window:

```

Please mark with 'X':

Selection      Field
Name          Length
-----
-             AA           4__
-             BB           4__
-             BC           4__
-             AE           4__
-             AF           4__
-             SF           8__
-             SH           16_
-             SS           16_
-             SG           3__
-             SQ           8__
-             XX           ___
-             RA           12_

Enter-----PF3-----PF7-----PF8-
           Back      <       >
    
```

ADALOD LOAD Sort Size

Option L (**ADALOD load**) on the **SORT Storage** menu displays the **Sort Storage - ADALOD LOAD** screen. .

For the ADALOD LOAD calculation, the default number of records is MAXISN rather than TOPISN as it is for the ADAINV function.

```

16:05:46          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
                   -  SORT Storage  - ADALOD LOAD  -  -              PSPSS22

File Number ..... 29
Number of records ( Default:  MAXISN  ) ..... 847          (reduce number
                                                                if field is NU)

Average compressed descr. length (in Bytes)
of the biggest descriptor .....
Occurrences of periodic groups ..... 1
Occurrences of multiple fields ..... 1
SORT device-type ..... 3390
LWP-parameter ..... 1000000
Database-ID ..... 1955
Password (if required) .....

-----
Required number of blocks (minimum) .....
Required number of cyls. (minimum) .....

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help           Exit           Menu           ↵
    
```

ADALOD UPDATE Sort Size

Option U (**ADALOD update**) on the **SORT Storage** menu displays the **Sort Storage - ADALOD UPDATE** screen. .

For the ADALOD UPDATE calculation, the default number of records is 0:

```

16:06:12          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
                   -  SORT Storage - ADALOD UPDATE - -              PSPSS22

File Number ..... 29
Number of records ( Default: 0      ) ..... (reduce number
                                                if field is NU)

Average compressed descr. length (in Bytes)
of the biggest descriptor .....
Occurrences of periodic groups ..... 1
Occurrences of multiple fields ..... 1
SORT device-type ..... 3390
LWP-parameter ..... 1000000
Database-ID ..... 1955
Password (if required) .....
-----
Required number of blocks (minimum) .....
Required number of cyls. (minimum) .....

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help                Exit                Menu                ↵

```

Estimating TEMP Data Set Space

Option **T (TEMP)** on the **Space Calculation** menu displays the **TEMP Storage** menu:

```
16:06:46          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
                   - TEMP Storage -                               PSPT002

                   Code      Service
                   -----
                   I         ADAINV
                   L         ADALOD load/update
                   U         ADALOD delete
                   ?         Help
                   .         Exit
                   -----

Code ..... _
File No. ....: 29
Database ID .. 1955 (WIS1955)

Command ==>
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit          Menu          ↵
```

The functions on this menu are used to estimate the storage needed on TEMP for the utility function chosen.

This section covers the following topics:

- [ADAINV TEMP Size](#)
- [ADALOD LOAD/UPDATE TEMP Size](#)
- [ADALOD DELETE TEMP Size](#)

ADAINV TEMP Size

Option I (ADAINV) on the **TEMP Storage** menu displays the TEMP Storage - ADAINV screen:

```

16:06:59          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
                   - TEMP Storage - ADAINV -                          -          PSPTI22

File Number ..... 29
Field-Name to be inverted ..
Average descriptor-length ..          ( Default = Field-Length )
Max. Number of records .....          ( Default = TOPISN          )
Occurrences/periodic groups. 1
Occurrences/multiple fields. 1
Device Type ..... 3390
No. of records to delete ...          ( ADALOD Delete only          )
DBID ..... 1955          (WIS1955)
Password (if required) .....

-----
Required TEMP-Blocks .....
          Cylinder ....

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit          Dis Field          Menu          ↵
    
```

PF4 (**Dis Field**) invokes a field selection window.

```

Please mark with 'X':

Selection      Field Name      Length
-----
-             AA             4__
-             BB             4__
-             BC             4__
-             AE             4__
-             AF             4__
-             SF             8__
-             SH             16_
-             SS             16_
-             SG             3__
-             SQ             8__
-             XX             ___
-             RA             12_

Enter-----PF3-----PF7-----PF8-
          Back      <      >
    
```

ADALOD LOAD/UPDATE TEMP Size

Option L (ADALOD load/update) on the TEMP Storage menu displays the TEMP Storage - ADALOD LOAD screen.

The TEMP Storage - ADALOD LOAD screen differs from the TEMP Storage - ADAINV screen in that a message is added reminding the user to multiply TOPISN by *all* occurrences of periodic groups and multiple value fields:

```

16:07:46          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
                  - TEMP Storage - ADALOD LOAD -                  -          PSPTI22

File Number ..... 29
Field-Name to be inverted ..
Average descriptor-length ..          ( Default = Field-Length )
Max. Number of records .....          ( Default = TOPISN          )
Occurrences/periodic groups. 1
Occurrences/multiple fields. 1
Device Type ..... 3390
No. of records to delete ...          ( ADALOD Delete only          )
DBID ..... 1955          (WIS1955)
Password (if required) .....

-----
Required TEMP-Blocks .....
          Cylinder ....

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit          Menu          ↵
    
```

ADALOD DELETE TEMP Size

Option U (ADALOD delete) on the TEMP Storage menu displays the TEMP Storage - ADALOD DELETE screen.

```

16:08:13          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
                   - TEMP Storage - ADALOD DELETE -          -          PSPTI22

File Number ..... 29
Field-Name to be inverted ..
Average descriptor-length ..          ( Default = Field-Length )
Max. Number of records .....          ( Default = TOPISN          )
Occurrences/periodic groups. 1
Occurrences/multiple fields. 1
Device Type ..... 3390
No. of records to delete ...          ( ADALOD Delete only          )
DBID ..... 1955          (WIS1955)
Password (if required) .....

-----
Required TEMP-Blocks .....
          Cylinder ....

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit          Menu          ↵

```

The TEMP Storage - ADALOD DELETE screen is identical to the TEMP Storage - ADAINV.

Estimating Work Data Set Space

Option **W (WORK)** on the **Space Calculation** menu displays the **Work Storage** screen.

The Work data set requires the most estimating. Although many initial values may be arbitrary, keep a record of them to ensure that subsequent tuning of the Work parameters has a realistic basis. Results comprise block estimates for the three parts of the Work area. A total of these values in blocks and cylinders is also provided.

Calculating Space Requirements

```
16:08:36          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
DBID 1955          - Work Storage -          PSPW002

Average compr. record length of an updated record ... 0
Average number of descr. updated per update cmd. .... 0
Average length of an updated descriptor value ..... 0

Average number of update cmds. per second ..... 0
Average duration of a transactions in seconds ..... 0

TOPISN of the biggest file in the database ..... 0

WORK device type / WORK blk. size ..... 3390 / 5724

Required space (blocks) :   Protection Area (LP) ....      0
-----
                          Intermediate ISN lists          0
                          Resulting ISN lists ....>      0
                          ? -----
                          Total (Blocks / Cyls.)....      0 / 0
                              + LTPET + LREPL

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit          Menu          ↵
```

11 Troubleshooting Options

■ Displaying Database Status Information	214
■ Displaying Active Targets	215
■ Forcing a Database Abend	216
■ Stopping a Utility	216

This chapter describes Adabas Online System troubleshooting options you can use to display diagnostic information.

Displaying Database Status Information

To display database status information for a specific database, select option **I** on the **Main Menu** (with the database ID specified) or enter the following direct command:

```
DISPLAY ADAINFO
```

The **Database Status Info** drop-down report appears:

```
--- Database Status Info ---  
  
DBID ..... 1955   1021  
DB Name ..... WIS1955  
Version ..... 8.3.8  
Start Date .. 2014-04-28  
Start Time .. 16:33:42  
DSF Status .. Active  
SPT Status .. Inactive  
CSH Status .. Inactive
```

↩

Status information includes:

- the database number and name
- the version of the Adabas software
- the date and time the database was started
- whether the Adabas Delta Save Facility, the Triggers and Stored Procedures Facility, and/or Adabas Caching Facility are active or inactive on the database.

Displaying Active Targets

From the main menu, the following direct command displays active targets for a specified database.

```
DISPLAY IDT
```

The Display Active Targets screen appears.

```
16:10:11          ***** A D A B A S  BASIC  SERVICES *****          2014-05-02
                  -  Display Active Targets  -

CPU ..... 0009A10E28180000          Entries for SVC No. .. 249
Default-DB .. 1955  (WIS1955)          Max. No. Of Entries .. 10
                                          Max. Active Entries .. 2

  M I Tgt-ID I Target Flag      I Target Mode      I CQH Flag I
-----
  I  1954  I Isolated-DB      I                      I    10  I
  I  1021  I Isolated-DB      I Local service      I    11  I
  I      I                      I                      I      I
  I      I                      I                      I      I
  I      I                      I                      I      I
  I      I                      I                      I      I
  I      I                      I                      I      I
  I      I                      I                      I      I
  I      I                      I                      I      I
  I      I                      I                      I      I
  I      I                      I                      I      I
  I      I                      I                      I      I
  I      I                      I                      I      I

Mark a DB-entry with 'X' to Select for processing

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help                Exit                Menu                ↵
```

The Target Flag column may have the following values:

Target Flag Value	Description
Communicator	Entire Net-Work node
Non-DB target	Entire System Server, XDCOM, or Entire Net-Work node
Isolated-DB	ADARUN parameter ISO=YES is used for the database

The Target Mode column may have the following values:

Target Mode Value	Description
AB required	attached buffers are required
IDTE forced	ADARUN parameter FORCE=YES is used during initialization
Anchor service	no command queue; anchor target only; e.g., buffer pool manager
Local service	ADARUN parameter LOCAL=YES; no remote calls

Forcing a Database Abend

The direct command, `CATCH RSP-CODE` forces an abend of the specified database. The syntax of the command is:

```
CATCH RSP-CODE
```

Stopping a Utility

Option **Q** on the **Main Menu** displays a window for stopping a batch utility job and resetting the DIB.

The equivalent direct command is:

```
RESET UTILITY-ABEND
```

The following pop-up screen appears:

```

Enter JOBNAME of Utility to
reset DIB and to Stop the user.

  Jobname ... _____
  Confirm ... _ (Y or N)

-PF1-----PF3-----PF12-----
      Exit      Menu
      ↵
    
```

Index

A

- abends
 - forcing, 216
- Adabas
 - event log, 45
- Adabas Online System (AOS)
 - accessing, 8
 - Demo version, 13
 - Main Menu, 9
- Adabas sessions
 - monitoring, 24
- ADAINV utility sort data set storage requirements, 204
- ADALOD LOAD utility sort data set storage requirements, 206
- ADALOD UPDATE utility sort data set storage requirements, 206
- ADAM file
 - specifying parameters, 124
- ADARUN parameters
 - displaying or modifying, 33
- Add Dataset screen, 141
- Add New Field(s) screen, 110
- Add/Delete PIN Modules screen, 155
- adding
 - ASSO or DATA storage extents, 141
 - fields, 110
 - PIN modules, 155
- Allocate/Deallocate CLOG/PLOG menu, 147
- Allocate/Deallocate File Space screen, 134
- allocating CLOG data sets, 147
- allocating PLOG data sets, 147
- alog
 - status, 160
- AOS
 - see Adabas Online System (AOS), 8
- ASSO Space Calculation menu, 195
- Associator
 - displaying defined and used space, 191
 - space calculation, 195

B

- Basic Services
 - entering direct commands, 12
 - error messages, 12
 - invoking functions, 11
 - logging on, 8
 - obtaining help information, 12
 - overview of functions, 9

specifying a database, 10

C

- Change Field Parameters screen, 112
- Checkpoint Maintenance menu, 102
- checkpoints
 - deleting, 104
 - listing, 102
 - maintaining, 102
 - types of, 103
- CLOG
 - dynamically allocating or deallocating data sets, 147
- clog
 - status, 160
- cluster
 - maintaining user table, 170
- cluster environments
 - estimating directory and data structure size, 197
- Cluster Usage screen, 91
- clusters
 - displaying members, 25
 - monitoring usage, 91
- command log
 - force a switch, 157
- command queue
 - displaying, 50
- Command Usage screen, 62
- commands
 - display usage per user, 55
 - monitoring overall usage, 62

D

- Data Integrity Block (DIB)
 - displaying entries, 143
 - resetting entries, 143
- data sets
 - resizing, 142
- Data Storage
 - displaying defined and used space, 191
 - space calculation, 201
- Data Storage screen, 201
- data structure size, 197
- database
 - displaying status information, 214
 - general layout, 185
 - maintenance, 139
 - physical location (volume serial number), 187
- Database Report

- reviewing, 173
- Database Report menu, 174
- Database Status Info drop-down report, 214
- databases
 - forcing an abend with response codes, 216
- dataset
 - status, 160
- DD/FILEA sequential data set
 - space calculation, 202
- DDFILEA Storage screen, 202
- deallocating CLOG data sets, 147
- deallocating PLOG data sets, 147
- Define FDT screen, 115
- Define File screen, 124
- Define SDT screen, 119
- defining
 - a new FDT, 115
 - files, 123
 - Special Descriptor Table (SDT), 119
- Delete Checkpoints screen, 104
- Delete Field screen, 116
- Delete File screen, 122
- deleting
 - a descriptor, 126
 - a field, 116
 - checkpoints, 104
 - file data, 133
 - files, 122
 - PIN modules, 155
- descriptors
 - deleting, 126
 - releasing, 120
 - undeleting, 127
- DIB
 - see Data Integrity Block (DIB), 143
- directory structure size, 197
- Display Active Targets screen, 215
- Display Cluster Members screen, 25
- Display Command Queue screen, 50
- Display Event Log Buffer screen, 45
- Display FDT screen, 175
- Display File Layout screen, 179
- Display Files screen, 178
- Display General DB-Layout screen, 185
- Display Locked Files screen, 159
- Display Maintenance Levels screen, 99
- Display Message Buffer screen, 152
- Display Parameters screen, 33
- Display PPT screen, 27, 78
- Display SDT screen, 177
- Display Unused Storage screen, 190
- Display Used Space screen, 191
- Display User Queue screen, 48
- Display Volser-Tab screen, 187
- Display/Modify Environment screen, 153
- displaying, 185
 - active targets, 215
 - ADARUN parameters, 33
 - command queue, 50
 - Database Report, 173
 - database status information, 214
 - database volume serial numbers, 187
 - DIB entries, 143
 - exit status, 154

- Field Definition Table (FDT), 175
- files with critical number of extents, 175
- hold queue, 51
- installed products, 44
- message buffer, 152
- PIN routines, 156
- queues, 47
- RABNs, 188
- snapshot statistics, 53
- Special Descriptor Table (SDT), 177
- unused storage, 190
- user queue elements, 48
- dumps
 - resetting status, 164

E

- estimating
 - Associator space, 195
 - cluster directory and data structure size, 197
 - Data Storage space, 201
 - DD/FILEA sequential data set size, 202
 - sort data set size, 203
 - Temp data set size, 207
- estimating Work data set space, 211
- event log
 - displaying, 45
- Event Replicator for Adabas
 - management, 81
- exits
 - displaying status, 154
 - modifying status, 154
- expanded files
 - maintaining, 135
- extended error handling parameters
 - setting, 153
- extents
 - add, 141
 - displaying critical, 175

F

- FDT
 - see Field Definition Table (FDT), 115
- FDT/SDT Definition/Modification menu, 109
- Field Definition Table (FDT)
 - defining new, 115
 - defining or modifying, 109
 - deleting a field, 116
 - displaying, 175
 - undeleting a field, 117
- fields
 - adding, 110
 - changing parameters, 112
 - deleting, 116
 - undeleting, 117
- file maintenance
 - deleting a descriptor, 126
 - undeleting a descriptor, 127
- File maintenance menu, 108
- File Usage screen, 63
- files
 - allocating or deallocating space, 134
 - defining, 123

- deleting, 122
- display, 178
- display usage by user, 58
- displaying status, 67
- displaying those with critical number of extents, 175
- inverting online, 118
- locking or unlocking, 158
- maintaining, 108
- maintaining expanded, 135
- modifying parameters, 127
- monitoring overall usage, 63
- refreshing to empty status, 133
- reordering, 131
- specifying ADAM file parameters, 124
- uncoupling, 143
- forcing
 - database abend, 216

G

- general database layout, 185

H

- high water marks
 - reviewing current settings for selected pools and queues, 65
- High Water Marks screens, 65
- Hold ISN Lock screen, 96
- hold queue
 - displaying, 51

I

- I/O by Volser screen, 74
- I/Os
 - reviewing by volser, 74
- In Parallel option, 111
- Increase/Decrease screen, 142
- interval
 - refreshing statistics, 52
- Interval Utilization menu, 60
- intervals
 - monitoring overall usage, 60
- inverting files online, 118

L

- List Checkpoints screen, 103
- List File Extents on VOLSER screen, 187
- List/Modify Exit Routines screen, 154
- List/Modify PIN Routines screen, 156
- listing
 - checkpoints, 102
- Lock Structure Calculator screen, 199
- Lock/Unlock Files menu, 158
- locking files, 158
- Logically Delete Undelete Descriptor screen, 125
- LWP
 - monitoring usage, 67

M

- Main Menu, 9
- maintaining
 - checkpoints, 102
 - user profiles, 28
 - user table, 170
- maintenance
 - display levels
 - using Adabas Basic Services, 99
- Manage Online Processes screen, 169
- managing
 - Event Replicator for Adabas, 81
 - online utilities, 169
- message buffer
 - displaying, 152
- Modify File Parameters screen, 127
- modifying
 - ADARUN parameters, 39
 - exit status, 154
 - field parameters, 112
 - PIN routines, 156
- monitoring
 - Adabas sessions, 24
 - interval usage, 60
- multiprocessing
 - monitoring sessions, 24

N

- nucleus
 - displaying file status, 67
- Nucleus File Status screen, 67

O

- online dumps
 - resetting status, 164
- Online Invert screen, 118
- Online Reorder File screen, 131
- online utilities
 - managing, 169

P

- physically uncoupling, 143
- PIN modules
 - adding, 155
 - deleting, 155
- PIN routines
 - displaying, 156
 - modifying, 156
- PLOG
 - dynamically allocating or deallocating data sets, 147
 - reviewing status, 68
- plog
 - status, 160
- PLOG Status screen, 68
- PPT
 - displaying, 78
- protection log
 - force a switch, 157
 - reviewing status, 68

Q

- Queue Displays menu, 47
- queues
 - displaying, 47

R

- RABNs
 - displaying, 188
- Read ASSO/DATA Block screen, 188
- recovering space, 143
- Refresh File screen, 133
- Refresh Statistics screen, 52
- refreshing
 - nucleus statistics, 52
- refreshing files, 133
- Release Descriptor screen, 121
- Release UQ screen, 120
- releasing
 - UQ descriptor, 120
- reordering files, 131
- resetting
 - online dump status, 164
- resetting DIB entries, 143
- resizing ASSO or DATA data sets, 142
- resources
 - obtaining current statistics, 53
- reviewing
 - event log, 45

S

- SDT
 - see Special Descriptor Table (SDT), 119
- Session
 - terminate
 - using Basic Services, 168
- session
 - reviewing status, 69
 - statistics, 81
- session monitoring
 - in a multiprocessing environment, 24
- Session Monitoring menu, 24
- Session Opercoms menu, 146
- Session Termination menu, 168
- Session Utilization menu, 81
- session utilization statistics, 81
- Snapshot Statistics menu, 53
- sort data set
 - ADAINV storage requirements, 204
 - ADALOD LOAD storage requirements, 206
 - ADALOD UPDATE storage requirements, 206
 - space calculation, 203
- Sort Storage - ADAINV screen, 204
- Sort Storage - ADALOD LOAD screen, 206
- Sort Storage - ADALOD UPDATE screen, 206
- Sort Storage menu, 203
- space
 - allocate or deallocate file, 134
 - calculate, 193
 - displaying Associator space, 191
 - displaying Data Storage space, 191
 - displaying unused, 190

- recovering, 143
- Space Calculation menu, 194
- Special Descriptor Table (SDT)
 - defining, 119
 - displaying, 177
- statistics
 - displaying, 54
 - refreshing interval statistics, 52
 - reviewing session utilization, 81
- Stop Users menu, 164
- stopping
 - users, 164
- system
 - reviewing status, 69
- System Status screen, 69

T

- targets
 - displaying active, 215
- TCP/IP
 - maintain URLs online, 59
- Temp data set
 - space calculation, 207
- TEMP Storage - ADAINV screen, 208
- TEMP Storage - ADALOD DELETE screen, 210
- TEMP Storage - ADALOD LOAD screen, 210
- Temp Storage menu, 207
- Thread Usage screen, 73
- threads
 - monitoring usage, 73
- troubleshooting options, 213

U

- uncoupling files, 143
- Undelete Field screen, 117
- undeleting
 - a descriptor, 127
 - a field, 117
- unlocking files, 158
- unused storage, displaying, 190
- UQ descriptor
 - releasing, 120
- URLs
 - maintaining TCP/IP online, 59
- user profiles
 - maintaining, 28
- user queue elements
 - displaying, 48
- user table
 - maintaining, 170
- User Table Maintenance menu, 170
- users
 - display command usage, 55
 - display file usage, 58
 - display resource usage, 54
 - stopping operation for, 164
- utilities
 - managing online, 169
- Utility
 - stop user and reset DIB
 - using Basic Services, 216

V

V* commands, 63

volume serial numbers, displaying, 187

W

work

 reviewing status, 76

Work data set

 space calculation, 211

work pool

 monitoring usage, 67

WORK Status screen, 76

Work Storage screen, 211

Workpool Usage screen, 67

Y

Y* commands, 63

