

Adabas System Coordinator

Adabas System Coordinator Operations and Programming Guide

Version 8.6.1

September 2025

This document applies to Adabas System Coordinator Version 8.6.1 and all subsequent releases.

Specifications contained herein are subject to change and these changes will be reported in subsequent release notes or new editions.

Copyright © 2025 Software GmbH, Darmstadt, Germany and/or its subsidiaries and/or its affiliates and/or their licensors.

The name Software AG and all Software GmbH product names are either trademarks or registered trademarks of Software GmbH and/or its subsidiaries and/or its affiliates and/or their licensors. Other company and product names mentioned herein may be trademarks of their respective owners.

Detailed information on trademarks and patents owned by Software GmbH and/or its subsidiaries is located at <https://softwareag.com/licenses>.

Use of this software is subject to adherence to Software GmbH's licensing conditions and terms. These terms are part of the product documentation, located at <https://softwareag.com/licenses> and/or in the root installation directory of the licensed product(s).

This software may include portions of third-party products. For third-party copyright notices, license terms, additional rights or restrictions, please refer to "License Texts, Copyright Notices and Disclaimers of Third-Party Products". For certain specific third-party license restrictions, please refer to section E of the Legal Notices available under "License Terms and Conditions for Use of Software GmbH Products / Copyright and Trademark Notices of Software GmbH Products". These documents are part of the product documentation, located at <https://softwareag.com/licenses> and/or in the root installation directory of the licensed product(s).

Use, reproduction, transfer, publication or disclosure is prohibited except as specifically provided for in your License Agreement with Software GmbH.

Document ID: COR-PROGRAMMING-861-20250929

Table of Contents

Preface	v
1 About this Documentation	1
Document Conventions	2
Online Information and Support	2
Data Protection	3
2 Starting the Adabas System Coordinator Daemon	5
3 Daemon Runtime Parameters	7
CT – Command Timeout Limit	8
DSPSCOPE – Dataspace Scope	9
ENCRYPTION - Activate Support for Encrypted Datasets	9
FORCE – Overwrite ID Table Entry	10
LOCAL - Define an Isolated Daemon	10
LU – Length of Intermediate User Buffer	11
MPMWTO – Display Information Messages	11
NABS – Number of Attached Buffers	11
NC - Number of Command Queue Elements	12
NXC - Number of Sysplex Command Queue Elements	12
PRODUCT - Identify the Services to be made Available	12
START– Cold start feature	13
ZIIP – Activate zIIP support for the System Coordinator Daemon	14
4 Daemon Operator Commands	15
5 Considerations and Configuration for using a Daemon	21
Single-seat current activity displays	22
Single-system dynamic transaction routing	23
Multi-system dynamic transaction routing	24
6 The Client Event Debug Monitor	27
Considerations before using the Debug Monitor	28
Setting Debug Monitor Controls	29
Activating the Debug Monitor	32
7 Using the Unified Trace	35
The Client Unified Trace	36
The Daemon Unified Trace	38
The Database Unified Trace	40
8 User Queue Elements (UQEs) for Configuration File Access	43
9 API To Retrieve Runtime Control Site Information	45
3GL API	46
Natural API	46
Return Codes	47
10 API To Modify Runtime Controls	49
3GL API	50
Natural API	51
Return Codes	51

Preface

This document provides information related to Adabas System Coordinator operations and programming.

The following topics are provided:

Operational Guidelines

[Starting the Adabas System Coordinator Daemon](#)

[Daemon Runtime Parameters](#)

[Daemon Operator Commands](#)

[Considerations and Configuration for using a Daemon](#)

[The Client Event Debug Monitor](#)

[Using the Unified Trace](#)

[User Queue Elements \(UQEs\) for Configuration File Access](#)

Programming Guidelines

[API To Retrieve Runtime Control Site Information](#)

[API To Modify Runtime Controls](#)

1 About this Documentation

- Document Conventions 2
- Online Information and Support 2
- Data Protection 3

Document Conventions

Convention	Description
Bold	Identifies elements on a screen.
Monospace font	Identifies service names and locations in the format <i>folder.subfolder.service</i> , APIs, Java classes, methods, properties.
<i>Italic</i>	Identifies: Variables for which you must supply values specific to your own situation or environment. New terms the first time they occur in the text. References to other documentation sources.
Monospace font	Identifies: Text you must type in. Messages displayed by the system. Program code.
{ }	Indicates a set of choices from which you must choose one. Type only the information inside the curly braces. Do not type the { } symbols.
	Separates two mutually exclusive choices in a syntax line. Type one of these choices. Do not type the symbol.
[]	Indicates one or more options. Type only the information inside the square brackets. Do not type the [] symbols.
...	Indicates that you can type multiple options of the same type. Type only the information. Do not type the ellipsis (...).

Online Information and Support

Product Documentation

You can find the product documentation on our documentation website at <https://documentation.softwareag.com>.

Product Training

You can find helpful product training material on our Learning Portal at <https://learn.software-ag.com>.

Tech Community

You can collaborate with Software GmbH experts on our Tech Community website at <https://tech-community.softwareag.com>. From here you can, for example:

- Browse through our vast knowledge base.
- Ask questions and find answers in our discussion forums.
- Get the latest Software GmbH news and announcements.
- Explore our communities.
- Go to our public GitHub and Docker repositories at <https://github.com/softwareag> and <https://hub.docker.com/publishers/softwareag> and discover additional Software GmbH resources.

Product Support

Support for Software GmbH products is provided to licensed customers via our Empower Portal at <https://empower.softwareag.com>. Many services on this portal require that you have an account. If you do not yet have one, you can request it at <https://empower.softwareag.com/register>. Once you have an account, you can, for example:

- Download products, updates and fixes.
- Search the Knowledge Center for technical information and tips.
- Subscribe to early warnings and critical alerts.
- Open and update support incidents.
- Add product feature requests.

Data Protection

Software AG products provide functionality with respect to processing of personal data according to the EU General Data Protection Regulation (GDPR). Where applicable, appropriate steps are documented in the respective administration documentation.

2 Starting the Adabas System Coordinator Daemon

Normally, there is one Adabas System Coordinator daemon per operating system image.

Ensure that the database containing the Adabas System Coordinator configuration file is active before starting the daemon.

The daemon must be started before any TP monitors or batch jobs that use its services.

The daemon should run at a higher priority than the databases and client jobs that use it.

3 Daemon Runtime Parameters

- CT – Command Timeout Limit 8
- DSPSCOPE – Dataspace Scope 9
- ENCRYPTION - Activate Support for Encrypted Datasets 9
- FORCE – Overwrite ID Table Entry 10
- LOCAL - Define an Isolated Daemon 10
- LU – Length of Intermediate User Buffer 11
- MPMWTO – Display Information Messages 11
- NABS – Number of Attached Buffers 11
- NC - Number of Command Queue Elements 12
- NXC - Number of Sysplex Command Queue Elements 12
- PRODUCT - Identify the Services to be made Available 12
- START– Cold start feature 13
- ZIIP – Activate zIIP support for the System Coordinator Daemon 14

The following parameters can be entered using DDCARD input. The PRODUCT parameter is mandatory. All other parameters are optional.

Parameter	Usage
CT	Command timeout limit.
DSPSCOPE	Specify the type of dataspace used by Adabas System Coordinator and Adabas Fastpath.
ENCRYPTION	Support encrypted daemon datasets.
FORCE	Overwrite ID table entry.
LOCAL	Define an isolated daemon.
LU	Length of intermediate user buffer.
MPMWTO	Display information messages.
NABS	Number of attached buffers.
NC	Number of command queue elements.
NXC	Number of sysplex command queue elements
PRODUCT	Identify the services to be made available. Mandatory.
START- Cold start feature	Delete shared memory from previous execution.
ZIIP	Activate zIIP support for the System Coordinator Daemon.

CT – Command Timeout Limit

Parameter	Use	Mimumum	Maximum	Default
CT	The maximum number of seconds (more precisely, units of 1.048576 seconds) that can elapse from the time a daemon request is completed until the results are retrieved by the sender through the interregion communication.	1	16,777,215	60

This parameter is used to prevent a request queue element (RQE) and attached buffer from being held indefinitely when a user with an outstanding request terminates abnormally.

Possible causes of a command timeout are

- address space is swapped out or cannot be dispatched;
- the task is cancelled or ABENDED;
- the task has low priority in a high-activity system.

DSPSCOPE – Dataspace Scope

Parameter	Use	Possible Values	Default
DSPSCOPE	Specify the type of dataspace used by Adabas System Coordinator and Adabas Fastpath.	ALL COMMON	ALL

From z/OS 2.4 and above, DSPSCOPE must be set to ALL to enable the continued use of dataspace due to z/OS enforcing the DIAGxx parmlib statement ALLOWUSERKEYCADS(NO).

This parameter is used by:

- The Adabas System Coordinator daemon when it is defined to use a dataspace for its shared memory latency/pulse services (refer to *Daemon latency/pulse services*).
- The Adabas Fastpath buffer when it is defined to use a dataspace (refer to the Dataspace Name Adabas Fastpath buffer parameter).

Important Note:

The following fixes must be applied and active in all components (client, daemon, database) across all systems (LPARs) before the use of DSPSCOPE=ALL is considered for any daemon within a group involving those systems:

Product	Version	Fix Number
Adabas System Coordinator	8.6 SP1	None
	8.3 SP1	MI831003, MI831004
Adabas Fastpath	8.6 SP1	None
	8.2 SP2	AW822058

ENCRYPTION - Activate Support for Encrypted Datasets

Parameter	Use	Possible Values	Default
ENCRYPTION	Specify whether to activate support for encryption.	YES NO	NO

The ENCRYPTION parameter controls whether the Adabas System Coordinator Daemon supports encrypted datasets.

-  **Note:** At ADA85 encryption requires the Adabas Encryption (AEZ) modules from the AEZ load library to be included in the Adabas System Coordinator (COR) Daemon STEPLIB concatenation above the Adabas modules. At ADA86 and above the Adabas Encryption modules are included in the Adabas load library. Adabas Encryption requires its license

module (AEZLIC) or file (DD-name DDLAEZ). If ENCRYPTION=YES and the AEZ license are missing or invalid, the COR Daemon will refuse to start.

If ENCRYPTION=NO is specified (the default), the Adabas System Coordinator Daemon does not support encrypted datasets. In this case, if a dataset is encrypted, the Adabas System Coordinator Daemon will terminate with an error when it attempts to open the dataset.

Setting ENCRYPTION=YES is required if one or more of the datasets accessed by the Adabas System Coordinator Daemon are encrypted (such as the Adabas Transaction Manager TMRFI recovery file).

If multiple daemons share an encrypted dataset in a group, then ENCRYPTION must be set to YES for all daemons in the group.

FORCE – Overwrite ID Table Entry

Parameter	Use	Possible Values	Default
FORCE	Specify whether or not this daemon is to force an entry into the active node list.	YES NO	NO

Possible values:

- FORCE=YES: Force an active entry, if one is available.
 FORCE=YES is usually not required. However, it may be needed if the previous daemon session ended abnormally, leaving the old entry in the active node list. Use this setting carefully.
- FORCE=NO: Causes an error if the node used by this daemon already appears in the active node list.

LOCAL - Define an Isolated Daemon

Parameter	Use	Possible Values	Default
LOCAL	Specify whether or not a daemon is to be isolated from other Entire Net-Work nodes.	YES NO	NO

Possible values:

- LOCAL=YES: Isolates this daemon from other Entire Net-Work nodes.
- LOCAL=NO: The daemon can receive calls from other Entire Net-Work nodes.

LU – Length of Intermediate User Buffer

Parameter	Use	Mimimum	Maximum	Default
LU	Set the size of the intermediate user buffer area.	4000	65,535	65,535

The size specified must be large enough to accommodate all control information for commands passed to the node.

An error occurs if the LU parameter specifies a value greater than the byte count implied by the NAB parameter. If you change either parameter value, you may have to change them both.

MPMWTO – Display Information Messages

Parameter	Use	Possible Values	Default
MPMWTO	Specify whether or not to display information level (I-level) messages.	YES NO	NO

By default, information level (I-level) messages are suppressed.

NABS – Number of Attached Buffers

Parameter	Use	Mimimum	Maximum	Default
NABS	Specify the number of attached buffers to be used.	0	500,000	16

An attached buffer is an internal buffer used for communication with the daemon.

For Adabas System Coordinator, this is an optional parameter that defines the number of attached buffers to be used for receiving requests from clients or from other daemon peers.

An attached buffer pool is allocated with a size equal to the value of the NABS parameter multiplied by 4096 bytes.

NC - Number of Command Queue Elements

Parameter	Use	Mimimum	Maximum	Default
NC	Set the maximum number of command queue elements.	20	32,767	100

The maximum number of command queue elements (CQEs) that can be processed simultaneously by this daemon.

NXC - Number of Sysplex Command Queue Elements

Parameter	Use	Mimimum	Maximum	Default
NXC	Set the maximum number of queue elements in the sysplex messaging command queue.	1	4096	256

This parameter is used only for multi-system daemons using XCF messaging, or for full Parallel Systems daemons using dynamic transaction routing (DTR). Although the default value will be sufficient for most sites, the number will dynamically expand as required when there is a high volume of XCF messages.

PRODUCT - Identify the Services to be made Available

Parameter	Use	Possible Values	Default
PRODUCT	Specifies which product services are to be made available by Adabas System Coordinator: <ul style="list-style-type: none"> ■ AAF: Adabas SAF Security ■ AFP: Adabas Fastpath Asynchronous Buffer Manager ■ ATM: Adabas Transaction Manager ■ AVI: Adabas Vista daemon component ■ DTR: Dynamic Transaction Routing Service 	AAF AFP ATM AVI DTR	none

This parameter is used once for each service that is to be made available by the daemon.

Possible values:

- PRODUCT=AAF:

Enable the daemon services necessary to support Adabas SAF Security for the protection of online administration of COR-based Add-on products.

- PRODUCT=AFP:

Enable the daemon services necessary to support the Adabas Fastpath Asynchronous Buffer Manager. This is mandatory for sites using Adabas Fastpath.

- PRODUCT=ATM:

Enable the daemon services necessary to support Adabas Transaction Manager. This is mandatory for sites using Adabas Transaction Manager.

- PRODUCT=AVI:

Enable the daemon services necessary to support Adabas Vista daemon-managed jobs such as those defined to use activity pulsing or those defined to run in dynamic transaction routing systems (eg. CICS/MRO, CICS/PLEX, and IMS).

- PRODUCT=DTR:



Note: PRODUCT=DTR previously replaced PRODUCT=CAS but parameter support for PRODUCT=CAS has been retained for backward compatibility.

This is an optional dummy parameter used simply to identify that dynamic transaction routing systems (eg. CICS/MRO, CICS/PLEX, and IMS) are being managed by this daemon.

START– Cold start feature

Parameter	Use	Possible Values	Default
START	<p>Normally, the daemon inherits and reuses shared memory allocations from a previous execution. Specify START=COLD to skip this recovery processing.</p> <p>Note: START=COLD is normally only used when advised by support to avoid start-up problems related to auto-recovery from previous executions.</p> <p>If there is a risk of daemons unnaturally terminating across an IPL then START=COLD should be used when restarting them.</p>	COLD	none

ZIIP – Activate zIIP support for the System Coordinator Daemon

Parameter	Use	Possible Values	Default
ZIIP	Specify whether or not zIIP support is to be activated for this Daemon.	YES NO	No

Possible values:

■ ZIIP=YES:

zIIP support for the Daemon is activated. The Daemon offloads CPU time from the general processors to System z Integrated Information Processors (zIIP). The purpose of this configuration is to reduce the CPU consumption on the general processors.

■ ZIIP=NO:

The default setting.

The Daemon runs without the option to offload CPU time to zIIPs.



Note: The use of ZIIP=YES requires the availability of the Adabas for zIIP license file (AZPAD). If the AZPAD license file is missing or found invalid, the Daemon will start but will run as if ZIIP=NO had been specified.

Dynamic Modification

If the Daemon was started with ZIIP=YES, the setting of the ZIIP parameter can be changed at runtime - that is, set to NO and subsequently back to YES - using the ZIIP= command from the operator console. If the Daemon was started with ZIIP=NO, the setting of the ZIIP parameter cannot be changed to YES later in this session.

Refer to [Daemon Operator Commands](#) for more information on the ZIIP= operator command.

4 Daemon Operator Commands

The following operator commands are available through the z/OS `Modify (F)` command.

Command	Description
ADAEND	<p>Terminates the daemon in an orderly manner.</p> <p>In order to avoid potential delays during the termination process, the following sequence of events is recommended:</p> <ol style="list-style-type: none">1. Shut down all active daemon-managed client jobs. This will result in the disconnection of these client jobs from the daemon.2. Issue ADAEND to the daemon (<code>//taskname,ADAEND</code>). This requests that the daemon shuts down in an orderly manner and in order to satisfy the request, the daemon will notify (if present) the daemon product components of Adabas Fastpath, Adabas SAF Security and Adabas Transaction Manager. Normally, these product components will immediately agree to the shutdown request however there may be circumstances which the product components identify which may result in a delay in the daemon shutdown. These are described below: <p>If Adabas Transaction Manager is present, incomplete distributed transactions will delay the shutdown process until all such transactions are complete (either through normal transaction completion or through completion due to the expiry of the Transaction Manager's Distributed Transaction Timeout). An ATM103 message will indicate the presence of any incomplete transactions. If necessary, the use of <code>ATM HALT //taskname,ATM HALT</code> will override this behaviour enabling the daemon shutdown process to continue. The incomplete transactions will remain in an incomplete status until such time as they can be completed (eg. when the daemon is restarted).</p> <p>If Adabas Fastpath is present, client jobs which are still active and connected will delay the shutdown process until all such jobs have disconnected. An AFP-0037-18 message is periodically issued for each job that is delaying the shutdown. Disconnection requires Adabas command activity within the client job or for the client job to be shutdown. However, after a suitable period of time has passed (a matter of minutes - to allow any in-flight commands to complete), Adabas Fastpath will override this behaviour enabling</p>

Command	Description
	<p>the daemon shutdown process to continue. An AFP-0069-18 message is periodically issued to indicate when the delay will be overridden and the daemon shutdown processing will continue.</p>
CAS DXCF	<p>Displays message count information for cross-daemon XCF messages. The following counts are displayed in response messages CAS021I, CAS022I;</p> <ul style="list-style-type: none"> ■ Msg-out: Total number of XCF messages sent by this daemon ■ Msg-in: Total number of XCF messages received by this daemon ■ Msg-rsp: Total number of message responses received ■ Msg-segs: Total number of message segments ■ Cq-Num: Number of queue elements in the Sysplex command queue. This will be equal to the command queue size specified, or defaulted, in the NXC parameter. ■ Cq-Hwm: Peak usage of the command queue. If this value is approaching the Cq-Num value it is advisable to increase the NXC value. ■ Cq-Full: Number of times a command queue full condition occurred. If greater than zero, increase the NXC value. ■ Cq-Post: Number of messages posted ■ RspPost: Number of responses posted <p>This command is not required during normal daemon operations, but its use may be requested by support personnel for diagnostic purposes.</p> <p>Note: XCF message counts will only be displayed if the daemon is running in “standard multi-system” or “parallel sysplex” mode.</p>
CAS DXCF RESET	<p>Displays message count information, as above, then resets all accumulated counters to zero.</p>
DPARM	<p>Displays the runtime parameters for this execution of the daemon.</p>
DRES	<p>Displays the allocated size, current usage and high-water mark for the following daemon resources:</p> <ul style="list-style-type: none"> ■ attached buffers <ul style="list-style-type: none"> ■ Size is controlled by the NABS DDCARD parameter ■ Current usage is not applicable ■ command queue <p>Size is controlled by the NC DDCARD parameter</p> ■ XCF command queue <ul style="list-style-type: none"> ■ Only applicable to z/OS daemons running in multi-systems XCF groups ■ Size is controlled by the NXC DDCARD parameter ■ Daemon threads

Command	Description
	<p>Current usage and high-water mark are not applicable</p> <ul style="list-style-type: none"> ■ Shared memory <ul style="list-style-type: none"> ■ Size is controlled by the daemon “Shared memory area size (k)” parameter ■ Only applicable if the daemon “Shared memory area size (k)” parameter is not 0 ■ Shared threads <ul style="list-style-type: none"> ■ Only applicable for IMS services ■ For IMS, size is not applicable ■ CF cache <p>Only applicable for daemon groups defined with a System Type of IBM Parallel Sysplex.</p> <p>The information is also written to the daemon’s output listing at daemon termination.</p>
<p>DSTAT [,DISK SERVICES]</p>	<p>Displays statistical information relating to the daemon.</p> <p>DSTAT displays the following:</p> <ul style="list-style-type: none"> ■ Number of threads ■ Thread size ■ Connected Jobs <p>The number of connected jobs defined to use daemon managed latency and/or activity pulsing.</p> <ul style="list-style-type: none"> ■ Connected Services (single) <p>The number of connected single-system dynamic transaction routing services.</p> <ul style="list-style-type: none"> ■ Connected Services (multi) <p>The number of connected multi-system dynamic transaction routing services.</p> <p>DSTAT,DISK displays read and write statistics when the daemon is defined to use the Crash Recovery Disk File.</p> <p>DSTAT,SERVICES lists the names of all connected dynamic transaction services along with statistics describing the number of times client sessions have been routed between the involved jobs (System Moves) and the relative number of Single(-system) and Multi(-system) moves.</p>
<p>DZSTAT [,ALL]</p>	<p>This operator command is valid for z/OS operating environments only.</p> <p>Use the DZSTAT command to a Daemon that was started with the Daemon parameter ZIIP=YES to display statistics about the execution of the Daemon in TCB mode and SRB mode and about the CPU time consumed on System z Integrated Information Processors (zIIP) and general processors (GP).</p> <p>The statistics displayed by DZSTAT correspond and are equivalent to the zIIP-related statistics at the end of the Daemon session statistics.</p>

Command	Description
	<ul style="list-style-type: none"> ■ current execution mode: “SRB” (execution on zIIP enabled) or “TCB” (execution on zIIP disabled) ■ general processors (GP) and System z Integrated Information Processors (zIIP) in the system ■ CPU time consumed by the Daemon enclave on GPs and zIIPs ■ TCB/SRB mode switches and parallel requests to the TCB <p>If DZSTAT,ALL is specified, the following additional statistics will be displayed:</p> <ul style="list-style-type: none"> ■ “Extended statistics” about internal pause and release operations ■ “Scheduling by type of work” statistics about reasons for switching modes or issuing parallel requests <p>Refer to Monitoring zIIP Usage in the <i>Adabas System Coordinator for zIIP</i> documentation for detailed information about the various statistical figures.</p>
<p>HALT</p>	<p>The HALT operator command is only appropriate after</p> <ul style="list-style-type: none"> ■ normal termination has already been requested via ADAEND. ■ normal termination is stalled. <p>HALT causes the forced termination of the daemon by making it ignore the orderly shutdown of the daemon components (Fastpath, Transaction Manager, Coordinator, etc). This forced termination will result in all of the resources allocated by the daemon being unilaterally freed, including any and all memory shared between the daemon and client jobs. Any further ADABAS activity by connected client job(s) will result in unpredictable results due to the freeing of these resources.</p> <p>We recommend HALT only in emergency situations when advised by support because the results for clients that remain active will be unpredictable if they issue an ADABAS call subsequent to daemon termination.</p>
<p>LICREFRESH</p>	<p>Use the LICREFRESH command to:</p> <ul style="list-style-type: none"> ■ Reload all appropriate license modules or reread all license files from the libraries identified by their respective DD JCL statements in the startup job for the Daemon. ■ Display and check the current license(s).
<p>ZIIP={ YES NO }</p>	<p>This operator command is valid for z/OS operating environments only.</p> <p>Use the ZIIP operator command to turn on or off the use of System z Integrated Information Processors (zIIP) in the Daemon.</p> <p>Issuing ZIIP=YES will tell the Daemon to run in SRB mode when possible and enable the use of zIIPs.</p> <p>Issuing ZIIP=NO will tell the Daemon to stay in TCB mode and disable the use of zIIPs.</p>

Command	Description
	The ZIIP operator command may only be used in a Daemon started with the Daemon parameter ZIIP=YES.

5 Considerations and Configuration for using a Daemon

- Single-seat current activity displays 22
- Single-system dynamic transaction routing 23
- Multi-system dynamic transaction routing 24

A daemon is required for Adabas Fastpath and Adabas Transaction Manager and is optional for Adabas SAF Security. There are other reasons for using a daemon:

As you will see, the daemon is a critical component and a failure can have a serious effect on the whole system. You can prevent a daemon failure by configuring your daemon jobs to use continuous operation.

Single-seat current activity displays

You can define jobs to send activity pulses to their local daemon which, for any appropriately defined job, enables current activities to be displayed in the *Current Activity Displays* option of the SYSCOR Natural application.

- [Daemon configuration](#)
- [Client configuration](#)

Daemon configuration

Single-seat current activity displays are only possible if the daemon is defined to use shared memory:

```
Run-mode: Daemon (node 2650)
Group: WORKSHOP   Daemon: ICFDCOR5   SVC: 254   Node: 2650   System: Multi
Recovery
  Continuous Operation (Y/N).....: Y
Daemon latency/pulse services
  Shared memory area size (k).....: 100000   Minimum (k): 0_____
  Dataspace name (if used)...: #COR5DSP
```

Here we specify that a 100 megabyte dataspace is to be used. If an area size is specified, then a dataspace name must also be specified.

The shared memory area size required is dependent on a number of factors: the products you have installed, the work profile of your applications, the number of sessions. As a rule of thumb, start off at 2k per session and monitor shared memory usage with the DRES daemon operator command.

If a session is unable to allocate shared memory, it will operate as normal but you will not be able to view its current activities.

Client configuration

You must also specify that activity pulsing is required in the client runtime controls of each job:

```
Activity pulse every.....: 5000__ commands or 60__ seconds
Group name.....: WORKSHOP Daemon connection messages (Y/N): N
```

The above controls define how frequently sessions in the job should update their shared memory area (in this example every 5000 commands or 60 seconds) and also the group name of the local daemon to which activity pulses will be sent.

Single-system dynamic transaction routing

Adabas System Coordinator and its associated products need to maintain context information about client sessions. In some systems – IMS and CICS/MRO - client sessions can “jump” from one job to another and Adabas System Coordinator must ensure that the context information “jumps” with them.

This is achieved by configuring the daemon to use shared memory and configuring the clients to use daemon latency.

- [Daemon configuration](#)
- [Client configuration](#)

Daemon configuration

The daemon should be defined to use continuous operation and shared memory:

```
Run-mode: Daemon (node 2650)
Group: WORKSHOP Daemon: ICFDCOR5 SVC: 254 Node: 2650 System: Multi
Recovery
Continuous Operation (Y/N).....: Y
Daemon latency/pulse services
Shared memory area size (k).....: 600000 Minimum (k): 0_____
Dataspace name (if used)...: #COR5DSP
```

Here we specify that a 600 megabyte dataspace is to be used.

The shared memory area size required is dependent on a number of factors: the products you have installed, the work profile of your applications, the number of sessions. As a rule of thumb, start off at 50k per session and monitor shared memory usage with the DRES daemon operator command.

If a session is unable to allocate shared memory, the daemon will use its local memory. However, this will incur a performance overhead and so its use should be avoided if possible.

Client configuration

Define the job as one of the DTR types, which enforce Daemon latency:

```
Type: CICS (DTR)   Name: WKS-DTR_
Operation: Normal autodetect: X Enable without products: _ Disable all: _
API runtime overrides....: N (Y/N)   Threadsafe operation...: N (Y/N)
Use additional exits.....: N (Y/N)
Maximum idle time (sec)..: 300_____ Non-terminal idle time.: _____
Generate RSP009/79 (Y/N)..: Y (until 0_____ seconds elapse)
Messages - Local.....: Console Y and/or DDMSG file _
      Or - Daemon routing: _
Latency - Local (Y/N)....: N

Latency - Daemon (Y/N)...: Y
      to disk.....: N
Activity pulse every.....: _____ commands or _____ seconds
Group name.....: WORKSHOP   Daemon connection messages (Y/N): N
```

and specify the group name of the daemon.

Multi-system dynamic transaction routing

Adabas System Coordinator and its associated products need to maintain context information about client sessions. In some systems – CICSplex for example - client sessions can “jump” from one system image to another and Adabas System Coordinator must ensure that the context information “jumps” with them.

This is achieved by configuring the daemon group as multi-system, with a daemon member using shared memory present in each system where a CICSplex member is active, and a Sysplex Cache Structure shared by all daemon group members.

CICS regions that form a CICSplex must be defined within a service configured using the CICS (DTR) client runtime control job-type, with the client runtime controls “Latency – Daemon (Y/N)” set to Y and “Enable CICSplex DTR” set to Y.

The daemon group will then coordinate the management of the client context each time the client “jumps”.

- [Daemon configuration](#)

- Client configuration

Daemon configuration

The daemon group should be defined to be a multi-system image group:

```

17:23:35                Modify                2015-02-06
                System Coordinator Group      C11230M1

                Group Name: WORKSHOP          SVC ID: 254__

System Type:  _  Standard single-system image...
(Mark one)   _  There is only one daemon in the group.
              X  Standard multi-system images - XCF...
              _  This enables multiple XCF group daemons.
              _  Standard multi-system images - Net-Work...
              _  This enables multiple Net-Work group daemons.

Command ==>
PF1 Help          PF3 Exit          PF5 Upd          PF9 More
    
```

PF9 shows more parameters for the System Coordinator Group:

```

17:26:10          Additional Group Parameters    2025-07-24
                System Coordinator Groups      C11230M2

Messages - daemon..... Console: Y and/or DDMSG file: N
Messages - databases... Console: Y and/or DDMSG file: N

Full crash recovery disk file (Y/N): N
Sysplex Cache Structure Name: RDU_CACHE2_____

Command ==>
                PF3 Quit          PF5 Upd
    
```

A Sysplex Cache Structure Name should be provided.

The cache structure should already be created and sized based on the following calculation:

Size of cache (k) = (Max no. of concurrent CICS terminal sessions in all CICSplex's)/4

The daemon members should be defined to use continuous operation and shared memory:

```
Run-mode: Daemon (node 2650)
Group: WORKSHOP Daemon: ICFDCOR5 SVC: 254 Node: 2650 System: Multi
Recovery
Continuous Operation (Y/N).....: Y
Daemon latency/pulse services
Shared memory area size (k).....: 600000 Minimum (k): 0_____
Dataspaces name (if used)..: #COR5DSP
```

Here we specify that a 600 megabyte dataspaces is to be used.

The shared memory area size required is dependent on a number of factors: the products you have installed, the work profile of your applications, the number of sessions. As a rule of thumb, start off at 50k per session and monitor shared memory usage with the DRES daemon operator command.

If a session is unable to allocate shared memory, the daemon will use its local memory. However, this will incur a performance overhead and so its use should be avoided if possible.

Client configuration

Define the job as one of the DTR types, which enforce Daemon latency:

```
Type: CICS (DTR) Name: WKS-DTR_
Operation: Normal autodetect: X Enable without products: _ Disable all: _
API runtime overrides....: N (Y/N) Threadsafe operation...: N (Y/N)
Use additional exits.....: N (Y/N)
Maximum idle time (sec)..: 300_____ Non-terminal idle time.: _____
Generate RSP009/79 (Y/N)..: N (until 0_____ seconds elapse)
Messages - Local.....: Console Y and/or DDMSG file _
Or - Daemon routing: _
Latency - Local (Y/N)....: N

Latency - Daemon (Y/N)...: Y Enable CICSplex DTR....: Y (Y/N)
to disk.....: N
Activity pulse every.....: _____ commands or _____ seconds
Group name.....: WORKSHOP Daemon connection messages (Y/N): N
Environment.....: _____ Level.....: _____
Read CORIN file (Y/N)....: N Review.: N Client Monitor.: N
```

and ensure the daemon group name is specified and "Enable CICSplex DTR" is set to Y.

6 The Client Event Debug Monitor

- Considerations before using the Debug Monitor 28
- Setting Debug Monitor Controls 29
- Activating the Debug Monitor 32

The client event debug monitor is used to troubleshoot problems with Adabas System Coordinator or with other Adabas products that work closely with it. Normally it is only used under guidance from Customer Support, however, as you will see by reading on, you might find it useful when troubleshooting your own systems too.

The debug monitor will write diagnostic information to a file (CORDUMP) based upon the settings that you make. By default, the debug monitor is inactive.

Considerations before using the Debug Monitor

- [Enabling CORDUMP](#)
- [Runtime Overheads](#)
- [Event Reporting and Output](#)
- [Monitoring Exceptions](#)

Enabling CORDUMP

The CORDUMP file must be available to the job being monitored and sized according to the amount of output requested. This can be done using the job's JCL.

Additional information regarding the attributes of the CORDUMP file is available on the Adabas System Coordinator Debug Event Monitor Controls online help screen.

Runtime Overheads

The debug monitor has minimal CPU runtime overhead.

Event Reporting and Output

When a monitored event occurs, information is written to the CORDUMP file based on the output options set. Careful consideration should be given to the setting of these options to avoid excessive output being written. For some events it may be necessary to capture significant amounts of information, clients running in the monitored job may therefore experience a delay in processing during the capture of this information.

Refer to [Setting Debug Monitor Controls](#) for an explanation of all the debug monitor controls.

Monitoring Exceptions

Generally, the debug monitor can be used to report on the majority of events, however there are certain exceptions:

- [Excluded Events](#)
- [CICS Threadsafe](#)

Excluded Events

Some internal processing errors may be reported as a Response 101 with sub-codes which are not eligible for reporting by the debug monitor. If you are unsuccessfully trying to report on a sub-code for Response 101 please check the messages and codes for the particular sub-code to see if it is excluded from this feature.

CICS Threadsafe

The debug monitor is automatically disabled for CICS jobs running in threadsafe mode. In order to use the debug monitor for these jobs, set the Adabas System Coordinator client runtime control "Threadsafe operation" to "N" and then set it back after you have finished.

Setting Debug Monitor Controls

The debug monitor controls are part of Adabas System Coordinator's Client Runtime Controls.

In SYSCOR, modify your client runtime controls; press PF9 ('More') then select option 2 ('Debug Settings') which presents the following screen:

The Client Event Debug Monitor

```

18:45:13      ***** A D A B A S   SYSTEM COORDINATOR 8.3.1 *****      2010-12-15
              - Debug Event Monitor Controls -                          UISCJBM1

Debug all sessions (Y/N) .....: Y      Maximum debug reports .....: _____
Response code: ___ Sub-code : _____ or mark for generic monitor : _
Optionally for database ....: _____ and file number .....: _____
Additional debug monitor (Y/N), use only as directed by Support:
System Coordinator .....: N      Adabas Transaction Manager ..: N
Adabas Fastpath .....: N      Adabas Vista .....: N

Report content in order of output amount, mark one:
None .....: X      Client session only .....: _
All sessions for the client : _      All sessions for the job .....: _
All memory for the job .....: _
Additional report content (Y/N):
CIB .....: Y      CAB .....: Y      ID table .....: Y
Registers on entry : Y      TP areas .....: Y      Stack .....: Y

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help           Exit           Upd

```

A description of each parameter follows:

Parameter	Use	Values	Default
Debug all sessions (Y/N)	<p>Defines the scope of the debug monitoring.</p> <p>When activated, the default, "Y", will result in all sessions being monitored immediately from the start of job.</p> <p>Specifying "N" will defer any monitoring until individual sessions have been activated. Refer to Activating the Debug Monitor for more information on this selective capability.</p>	Y N	Y
Maximum debug reports	<p>Limits the number of times the monitored event will cause a report to be written to the CORDUMP file.</p> <p>The default, "0", means no reports will be written. Usually a value of 1 is sufficient for most events.</p> <p>Caution: Specifying an excessive value could severely impact system performance.</p>	0 - 65535	0
Response code / Sub-code, or mark for generic monitor	<p>Defines the event to be monitored:</p> <ul style="list-style-type: none"> ■ A specific response code without sub-code ■ A specific response code and sub-code 	<p>Response code: 0 – 999</p> <p>Sub-code: 0 – 65535</p>	0

Parameter	Use	Values	Default
	<ul style="list-style-type: none"> ■ A generic monitor for non-zero response codes (excludes 0, 3, 9, 148, etc. - a full list can be found in the help screens) 		
Optionally for database / file number	<p>From time to time support may supply a diagnostic fix in order to generate additional reports to the CORDUMP file.</p> <p>These parameters provide control at the job level for such reports for the following products:</p> <ul style="list-style-type: none"> ■ Adabas System Coordinator ■ Adabas Transaction Manager ■ Adabas Fastpath ■ Adabas Vista <p>The default, "N", means no additional reporting.</p> <p>Note: These defaults should only be changed under guidance from support.</p>	<p>Database: 0 – 65535</p> <p>File: 0 - 65535</p>	0
Additional debug monitor (Y/N)	<p>From time to time support may supply a diagnostic fix in order to generate additional reports to the CORDUMP file. These parameters provide control at the job level for such reports for the following products:</p> <ul style="list-style-type: none"> ■ Adabas System Coordinator ■ Adabas Transaction Manager ■ Adabas Fastpath ■ Adabas Vista <p>The default, "N", means no additional reporting.</p> <p>Note: These defaults should only be changed under guidance from support.</p>	Y N	N
Report content (in order of output amount)	<p>Defines the type of information generated each time a monitored event causes a report to be written to the CORDUMP file:</p> <ul style="list-style-type: none"> ■ None ■ Client session only ■ All sessions for the client ■ All sessions for the job ■ All memory for the job <p>The most commonly used option is 'All memory for the job' because this guarantees all available diagnostic information will be written.</p>	See description	None

Parameter	Use	Values	Default
Additional report content (Y/N)	<p>Each time a monitored event causes a report to be written to the CORDUMP file, the following areas are included by default (regardless of the report content parameter):</p> <ul style="list-style-type: none"> ■ CIB ■ CAB ■ ID table ■ Registers on entry ■ TP areas ■ Stack <p>There is usually no reason to change these defaults except under guidance from support.</p>	Y N	Y

Activating the Debug Monitor

- [Activation at Job Start](#)
- [Activation for an Individual Session](#)

Activation at Job Start

At job start, if “Maximum debug reports” is > 0 and the debug monitor control “Debug all sessions” is “Y”, then debug monitoring will be automatically activated.

Activation for an Individual Session

At job start, if “Maximum debug reports” is > 0 and the debug monitor control “Debug all sessions” is “N”, then debug monitoring will be deferred until it is manually activated for a selected client session, as follows:

1. Display the summary of session information for a job. Refer to Display Session Information within Current Activity Displays for information on how to do this.

7 Using the Unified Trace

- The Client Unified Trace 36
- The Daemon Unified Trace 38
- The Database Unified Trace 40

The unified trace is used to troubleshoot problems with the System Coordinator or with Adabas products that work closely with it. Normally it is only used under guidance from Customer Support. However, as you will see by reading on, you might find it useful when troubleshooting your own systems too.

The default is that it is inactive.

The unified trace can be activated in the client, daemon, or database based upon the settings that you make.

The Client Unified Trace

The client unified trace settings are defined in client runtime controls. They can be configured statically (through the Maintenance function of SYSCOR) or dynamically (through the Current Activity Display function of SYSCOR). For random problems experienced by your commercial users it may be necessary to configure the settings statically (subject to the Trace size warning – see below), however in some cases it is possible to reproduce the problem in controlled circumstances. In this case you can configure the settings dynamically for the specific client session(s).

To configure the required trace settings, modify your selected client controls in SYSCOR (either statically or dynamically); press PF9 then select option 3 (unified trace settings) which presents the following screen:

```

16:42:40 ***** A D A B A S   SYSTEM COORDINATOR 8.3.1 (I001) ***** 2012-08-23
                - Unified Trace Settings -                               U1SCTRM1

Trace collection settings
Trace collection (Y/N).....: N
Local trace memory (k).....: 0___      0=none,minimum=32,maximum=1024
Trace recording settings
Write a copy to local trace file....: _      Mark for local trace file
Forward to the daemon trace file....: _      Mark for daemon trace file
Synchronous writes.....: _      Mark to limit to synchronous
Single writes activation point.....: _____ No buffering after n commands
Flush for significant session events: _      Mark to flush on CL (etc)
Dynamic options
Limited debug trace:
Response code trace activation.....: 0___
Sub-code.....: 0___
Generic error response codes (Y/N)..: N
Debug event activation (Y/N).....: N

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help           Exit           Upd
    
```

- [Trace collection](#)
- [Local trace memory](#)
- [Dynamic options](#)

Trace collection

Trace data will be collected only when this parameter is set to Y and a local trace memory size has been specified. Once started, data is collected into the trace buffer and, when full, will wraparound overwriting the oldest content and maintaining the newest content. The period of time for which trace data remains in memory is therefore dependent on the size of the trace buffer. The content of the trace buffer can be displayed through SYSCOR Current Activity Display and for information on how to do this refer to Expand Adabas client sessions.

Local trace memory

This specifies the amount of memory (in k) to be used for the unified trace buffer and is allocated at the individual session level.



Caution: When statically defining the trace size for a job's runtime controls through the SYSCOR Maintenance function, due consideration must be given to the trace size as it may have a significant impact on the job's memory consumption. Such consideration is far less significant for a trace size specified dynamically to an individual session through the SYSCOR Current Activity Display function.

In addition to collecting and displaying the most recent trace activity, additional options are available for managing the data within the trace buffer:

Write a copy to local trace file



Note: This option is only selectable for job types Batch and TSO.

You can optionally choose to flush collected trace data to a local sequential file (COTRC). This file must be defined to the job's execution control script. If using COTRC you must add the Adabas load library to the job's loading environment.

Forward to the daemon trace file



Note: This option is only selectable for jobs that have been defined to use the COR daemon.

You can choose to flush collected trace data to a daemon trace file. Refer to [The Daemon Unified Trace](#) for information on how to implement a daemon trace file.

Synchronous writes



Note: This option is only applicable if "Write a copy to local trace file" or "Forward to the daemon trace file" has been selected.

By default, the flushing of collected trace data is done asynchronously. Select this option if you prefer this to be done synchronously.

Single writes activation point



Note: This option is only applicable if “Write a copy to local trace file” or “Forward to the daemon trace file” has been selected.

When a session’s activity reaches the number of commands specified here, the current trace content will be flushed out and thereafter trace entries will be written one at a time as each one is completed. No buffering will occur.

Flush for significant session events



Note: This option is only applicable if “Write a copy to local trace file” or “Forward to the daemon trace file” has been selected.

Selecting this option will cause additional flushing of the collected trace data at predefined events (for example at CL command time).

Dynamic options

By far the most common event that needs to be traced is an unexpected Adabas response code. You can choose to stop further trace collection following one of these events:

- a specific response code without a subcode
- a specific response code with a specific subcode
- a generic response code (this control relates to all response codes except those which do not indicate an error of significance. For example, response codes 0, 3, 9 and 148, a full list can be found in the help screens).

Once collection has stopped, the trace buffer in memory remains displayable for as long as the session remains active. If you selected one of the options to additionally write to disk then the current trace buffer is also written out to disk for more permanent analysis.

The Daemon Unified Trace

The daemon unified trace settings are defined in daemon parameters. In SYSCOR, list the daemons in your daemon group then modify the appropriate daemon which presents the following screen:

```

15:21:11 ***** A D A B A S   SYSTEM COORDINATOR 8.3.1 (I001) ***** 2012-08-24
          - Adabas System Coordinator Daemon Parameters -          C11261M1
Run-mode: Pulsing (node 2650)
Group: WORKSHOP   Daemon: ICFDCOR5   SVC: 254   Node: 2650   System: Multi
Recovery
  Continuous Operation (Y/N).....: N
Daemon latency/pulse services
  Shared memory area size (k).....: 10240___   Minimum (k): 0_____
    Dataspace name (if used)..: _____
  Daemon memory area size (k).....: 10240___   Minimum (k): 0_____

Unified trace settings
  Trace collection (Y/N).....: N
  Local trace memory (k).....: 0___ (0=none minimum=32 maximum=1024)
  Use trace file (Y/N).....: N
  Wraparound trace file when full..: N
Debug settings
  CORDUMP for transient situations.: N   Number of outputs: 0___

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help           Exit           Upd                               Menu

```



Caution: *Daemon trace collection to the trace file quickly fills the file and can cause information forwarded by client jobs to be lost. This is why the default for the daemon trace is to be inactive, so that it can be used sparingly by activating it dynamically for short periods.*

- [Trace collection](#)
- [Local trace memory](#)
- [Use trace file](#)
- [Wraparound trace file when full](#)

Trace collection

Trace data will be collected only when this parameter is set to Y and a local trace memory size has been specified. Once started, data is collected into the trace buffer and (optionally, a trace file – see below). When the trace buffer is full, it wraps around overwriting the oldest content and maintaining the newest content. The period of time for which trace data remains in memory is therefore dependent on the size of the trace buffer. The trace can be activated (and de-activated), and its content displayed, through SYSCOR Current Activity Display and for information on how to do this refer to the section on tasks for Coordinator daemon nodes in Network Discovery. In addition to collecting and displaying the most recent trace activity, all trace data can be written to disk.

Local trace memory

This specifies the amount of memory to be used for the unified trace and is allocated at the individual thread level. This size can also be changed through SYSCOR Current Activity Display and for information on how to do this refer to the section on tasks for Coordinator daemon nodes in Network Discovery.

Use trace file

You can choose to write collected trace data to a local BDAM file (COTRC). This file must be defined to the daemon's execution control script. This option can also be changed through SYSCOR Current Activity Display and for information on how to do this refer to the section on tasks for Coordinator daemon nodes in Network Discovery.

When this option is selected, the following type of trace data is written to the file:

- Daemon collected trace data (Local trace memory must be non-zero and the trace collection dynamically activated)
- Client forwarded trace data (for more information refer to [The Client Unified Trace](#)).

Wraparound trace file when full

When selected, this option will cause trace data to wraparound overwriting the oldest content and maintaining the newest content. This option can also be changed through SYSCOR Current Activity Display and for information on how to do this refer to the section on tasks for Coordinator daemon nodes in Network Discovery.

The Database Unified Trace

The database unified trace settings share the same configuration as the daemon unified trace settings which are defined in daemon parameters. In SYSCOR, list the daemons in your daemon group then modify the appropriate daemon which presents the following screen:

```

15:21:11 ***** A D A B A S   SYSTEM COORDINATOR 8.3.1 (I001) ***** 2012-08-24
          - Adabas System Coordinator Daemon Parameters -          C11261M1
Run-mode: Pulsing (node 2650)
Group: WORKSHOP   Daemon: ICFDCOR5   SVC: 254   Node: 2650   System: Multi
Recovery
  Continuous Operation (Y/N).....: N
Daemon latency/pulse services
  Shared memory area size (k).....: 10240___   Minimum (k): 0_____
    Dataspace name (if used)..: _____
  Daemon memory area size (k).....: 10240___   Minimum (k): 0_____

Unified trace settings
  Trace collection (Y/N).....: N
  Local trace memory (k).....: 0___ (0=none minimum=32 maximum=1024)
  Use trace file (Y/N).....: N
  Wraparound trace file when full..: N
Debug settings
  CORDUMP for transient situations.: N   Number of outputs: 0___

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help           Exit           Upd                               Menu

```

The shared configuration is described here:

- [Trace collection](#)
- [Local trace memory](#)
- [Use trace file](#)
- [Wraparound trace file when full](#)

Trace collection

Trace data will be collected only when this parameter is set to Y and a local trace memory size has been specified. Once started, data is collected into the trace buffer and (optionally, a trace file – see below). When the trace buffer is full, it wraps around overwriting the oldest content and maintaining the newest content. The period of time for which trace data remains in memory is therefore dependent on the size of the trace buffer. The trace can be activated (and de-activated), and its content displayed, through SYSCOR Current Activity Display and for information on how to do this refer to the section on tasks for Adabas nodes in Network Discovery. In addition to collecting and displaying the most recent trace activity, all trace data can be written to disk.

Local trace memory

This specifies the amount of memory to be used for the unified trace and is allocated at the individual thread level. This size can also be changed through SYSCOR Current Activity Display and for information on how to do this refer to the section on tasks for Adabas nodes in Network Discovery.

Use trace file

You can choose to write collected trace data to a local BDAM file (COTRC). This file must be defined to the database's execution control script. This option can also be changed through SYSCOR Current Activity Display and for information on how to do this refer to the section on tasks for Adabas nodes in Network Discovery.

Wraparound trace file when full

When selected, this option will cause trace data to wraparound overwriting the oldest content and maintaining the newest content. This option can also be changed through SYSCOR Current Activity Display and for information on how to do this refer to the section on tasks for Adabas nodes in Network Discovery.

8

User Queue Elements (UQEs) for Configuration File Access

The vast majority of parameter settings for all Adabas client-based add-ons are defined in the configuration file. Therefore it is extremely easy to modify runtime settings without having to locate the JCL for all client jobs, databases, etc. that run in your system. This is a major advantage over embedding runtime settings inside JCL because client job JCL is mostly unavailable to the administrators to freely make changes. The configuration file must be accessed at runtime by Adabas System Coordinator client jobs during start up to pick up runtime settings. Adabas System Coordinator generates commands to the configuration file using special Adabas sessions (UQEs). This is now an advantage because in previous releases there was at least one UQE for each batch job step that ran in your systems (this is a very, very large number in most systems). Each of these UQEs would be created and deleted with very few commands issued for them. Now the identity of the UQE is set so that it equates to a job's process identity and consequently these sessions are reused by all batch job steps that use the same process identity (regardless of job name). The result is that the total number of these UQEs is now (approximately) equal to the number of process identities in your system that are used for Adabas work (which is a much smaller number than before) - therefore the constant create UQE, delete UQE activity that went unnoticed inside Adabas in previous releases now doesn't happen at all.

9 API To Retrieve Runtime Control Site Information

- 3GL API 46
- Natural API 46
- Return Codes 47

Adabas System Coordinator allows storing of site-specific data in runtime controls. The contents and format of the data are entirely under your control. A typical use for it might be to define your own runtime controls (for example dynamic Natural parameters). The data can be retrieved using the supplied APIs. Two APIs are provided; one for 3GL and Assembler programs and one for Natural programs.

3GL API

The 3GL API is contained in the supplied COR3GLI load module. There are also some supplied source members showing how to use the API:

- APIINF01: example of using the API in environments other than CICS
- APIINF02: example of using the API in CICS
- COR3GLIA: a parameter data area for calling COR3GLI

> To use the 3GL API:

- 1 Allocate storage for the parameter data area (1792 bytes).
- 2 Initialize the storage to binary zeroes.
- 3 Set the interface version (field name INFVRS in COR3GLIA) and function (INFFNC).
- 4 Under CICS, set the name of the Adabas link module to be used (INFCICN). The link module must be capable of accepting parameter lists via the COMMAREA. If not under CICS, INFCICN must contain binary zeroes or spaces.
- 5 If using the reentrant ADALNKR, allocate a modified area and set its address (INFAMOD).
- 6 Link this program together with COR3GLI and, if not under CICS, your Adabas interface module, for example ADAUSER.
- 7 After calling COR3GLI, INFRC will contain 0000 and INFDATA will contain the site information for this session; or, INFRC will contain a non-zero return code and INFRT will contain an explanatory message.

Natural API

The Natural API is contained in library SYSCOR, subprogram CORNATI. There are also some supplied source members in SYSCOR, showing how to use the API:

- APIINF-P: example of calling CORNATI
- CORNATIA: parameter data area for calling CORNATI

➤ **To use the Natural API:**

- 1 Ensure that subprogram CORNATI is available, by copying it to your Natural library or adding SYSCOR to your library's steplibs in Natural Security.
- 2 Set CORNATI-VERSION and CORNATI-FUNCTION.
- 3 Call CORNATI.
- 4 After calling CORNATI, CORNATI-RC will contain 0000 and CORNATI-SITEINFO will contain the site information for this session; or, CORNATI-RC will contain a non-zero return code and CORNATI-RT will contain an explanatory message.

Return Codes

These are the non-zero return codes which may be set:

Return Code	Description
0001	Invalid interface version (must be 01)
0002	Invalid function (must be GETINFO)
0003	System Coordinator not available
0004	System Coordinator internal error
0005	System Coordinator internal error
0006	Adabas interface not linked (3GL API only)
0008	No site information for this session

10

API To Modify Runtime Controls

- 3GL API 50
- Natural API 51
- Return Codes 51

Adabas System Coordinator uses runtime controls to determine execution behavior. Applications can modify some of these runtime controls dynamically, via API. Two APIs are provided; one for 3GL and Assembler programs and one for Natural programs. Currently the only runtime controls that can be modified are the z/OS-only controls *Review* and *Client Monitor*.

3GL API

The 3GL API is contained in the supplied COR3GLI load module. There are also some supplied source members showing how to use the API:

- APIREV01: example of using the API in environments other than CICS
- APIREV02: example of using the API in CICS
- COR3GLIA: a parameter data area for calling COR3GLI

➤ To use the 3GL API:

- 1 Allocate storage for the parameter data area (1792 bytes).
- 2 Initialize the storage to binary zeroes.
- 3 Set the interface version (field name INFVRS in COR3GLIA) and function (INFFNC).
- 4 Set the product code (INFCPROD) for which controls are to be modified (currently, this must be 'COR').
- 5 Set the names (INFCNAME) of the runtime controls to be modified ('REVIEW' and/or 'REVIEW-CLIENT'), together with the required value (INFCVAL, 'Y' or 'N').
- 6 Under CICS, set the name of the Adabas link module to be used (INFCICN). The link module must be capable of accepting parameter lists via the COMMAREA. If not under CICS, INFCICN must contain binary zeroes or spaces.
- 7 If using the reentrant ADALNKR, allocate a modified area and set its address (INFAMOD).
- 8 Link this program together with COR3GLI and, if not under CICS, your Adabas interface module, for example ADAUSER.
- 9 After calling COR3GLI, INFRC will contain 0000 and the new controls will be in effect for this session; or, INFRC will contain a non-zero return code and INFRT will contain an explanatory message.

Natural API

The Natural API is contained in library SYSCOR, subprogram CORNATI. There are also some supplied source members in SYSCOR, showing how to use the API:

- APIREV-P: example of calling CORNATI
- CORNATIA: parameter data area for calling CORNATI

➤ To use the Natural API:

- 1 Ensure that subprogram CORNATI is available, by copying it to your Natural library or adding SYSCOR to your library's steplibs in Natural Security.
- 2 Set CORNATI-VERSION and CORNATI-FUNCTION.
- 3 Set the product code (CORNATI-CONTROL-PRODUCT) for which controls are to be modified (currently, this must be 'COR').
- 4 Set the names (CORNATI-CONTROL-NAME) of the runtime controls to be modified ('REVIEW' and/or 'REVIEW-CLIENT'), together with the required value (CORNATI-CONTROL-VALUE, 'Y' or 'N').
- 5 Call CORNATI.
- 6 After calling CORNATI, CORNATI-RC will contain 0000 and the new controls will be in effect for this session; or, CORNATI-RC will contain a non-zero return code and CORNATI-RT will contain an explanatory message.

Return Codes

These are the non-zero return codes which may be set:

Return Code	Description
0001	Invalid interface version (must be 01)
0002	Invalid function (must be CONTROLS)
0003	System Coordinator not available
0004	System Coordinator internal error
0005	System Coordinator internal error
0006	Adabas interface not linked (3GL API only)
0010	Invalid product code (must be COR)
0011	Invalid control name (must be REVIEW or REVIEW-CLIENT)
0012	Invalid control value (must be Y or N)

