

# Natural

## Installation for z/OS

Version 9.2.4

October 2025

This document applies to Natural Version 9.2.4 and all subsequent releases.

Specifications contained herein are subject to change and these changes will be reported in subsequent release notes or new editions.

Copyright © 1979-2025 Software GmbH, Darmstadt, Germany and/or its subsidiaries and/or its affiliates and/or their licensors.

The name Software AG and all Software GmbH product names are either trademarks or registered trademarks of Software GmbH and/or its subsidiaries and/or its affiliates and/or their licensors. Other company and product names mentioned herein may be trademarks of their respective owners.

Detailed information on trademarks and patents owned by Software GmbH and/or its subsidiaries is located at <https://softwareag.com/licenses>.

Use of this software is subject to adherence to Software GmbH's licensing conditions and terms. These terms are part of the product documentation, located at <https://softwareag.com/licenses> and/or in the root installation directory of the licensed product(s).

This software may include portions of third-party products. For third-party copyright notices, license terms, additional rights or restrictions, please refer to "License Texts, Copyright Notices and Disclaimers of Third-Party Products". For certain specific third-party license restrictions, please refer to section E of the Legal Notices available under "License Terms and Conditions for Use of Software GmbH Products / Copyright and Trademark Notices of Software GmbH Products". These documents are part of the product documentation, located at <https://softwareag.com/licenses> and/or in the root installation directory of the licensed product(s).

Use, reproduction, transfer, publication or disclosure is prohibited except as specifically provided for in your License Agreement with Software GmbH.

**Document ID: NATMF-INSTALL-ZOS-924-20251013**

## Table of Contents

Preface .....	vii
1 About this Documentation .....	1
Document Conventions .....	2
Online Information and Support .....	2
Data Protection .....	3
I Installation Process and Major Natural Features on z/OS .....	5
2 Installation Process and Major Natural Features on z/OS .....	7
General Prerequisites and System Support .....	8
Installation Medium .....	9
Installation Method .....	10
System Maintenance Aid (SMA) .....	10
Sample Installation Jobs .....	11
Installation Job Identification .....	11
Overall Installation Procedure .....	12
Installation Verification .....	12
INPL Utility .....	12
Natural Nucleus Components .....	12
Natural System Files .....	16
II Installing Natural on z/OS .....	19
3 Installing Natural on z/OS .....	21
Prerequisites .....	22
Installation Medium .....	22
Installation Procedure .....	24
Installation Verification .....	37
III Installing ICU for Adabas & Natural on z/OS .....	39
4 Installing ICU for Adabas & Natural on z/OS .....	41
Prerequisites .....	42
Installation Medium .....	42
Installation Procedure .....	42
Installation Verification .....	47
Using ICS31 in Natural subtask (needs APF-authorized ICS load library) .....	48
IV Installation for REQUEST DOCUMENT, PARSE JSON, and PARSE XML Statements on z/OS .....	49
5 Installation for REQUEST DOCUMENT, PARSE JSON, and PARSE XML Statements on z/OS .....	51
Prerequisites .....	52
Installation Procedure .....	53
Installation Verification .....	55
V Installing Entire System Server Interface on z/OS .....	57
6 Installing Entire System Server Interface on z/OS .....	59
Prerequisites .....	60
Default or Customized Installation .....	60

Assemble the Parameter Module for the Entire System Server Interface Component .....	63
Link the Entire System Server Interface to the Nucleus .....	63
Installing and Activating the Write-to-Spool Feature .....	64
Install the Entire System Server in Single-User Mode .....	66
VI Installing Software AG Editor on z/OS .....	69
7 Installing Software AG Editor on z/OS .....	71
Prerequisites .....	72
Support of a Parallel Sysplex Environment .....	72
Installation Procedure .....	72
Installation Verification .....	77
VII Installing Natural CICS Interface on z/OS .....	79
8 Installing Natural CICS Interface on z/OS .....	81
Prerequisites .....	82
Installation Medium .....	82
Prefix Used for Natural CICS Interface Components .....	83
Installation Procedure .....	83
CICS Startup Parameters .....	89
CICS Resource Definitions .....	94
Installation Verification .....	106
VIII Installing Natural Com-plete/SMARTS Interface on z/OS .....	107
9 Installing Natural Com-plete/SMARTS Interface on z/OS .....	109
Prerequisites .....	110
Installation Medium .....	110
Installation Procedure .....	111
Installation Verification .....	115
IX Installing Natural IMS TM Interface on z/OS .....	117
10 Installing Natural IMS TM Interface on z/OS .....	119
Prerequisites .....	120
Installation Medium .....	120
Installation Procedure .....	121
Prepare, Convert, Assemble and Link the License File for Natural for IMS for zIIP .....	121
Common Installation Steps .....	122
Installing the Batch Message Processing BMP Environment .....	124
Installing the Message-Oriented NTRD Environment .....	126
Installing the Dialog-Oriented MPP Environment .....	128
Installing the Natural Development/Natural Web I/O Interface Server .....	132
Installing the Server Environment .....	133
Customizing the IMS TM Environment .....	135
Installation Verification .....	139
X Installing Natural TSO Interface on z/OS .....	141
11 Installing Natural TSO Interface on z/OS .....	143
Prerequisites .....	144
Installation Medium .....	144

Installation Procedure .....	145
Installation Verification .....	147
XI Installing Natural for Db2 on z/OS .....	149
12 Installing Natural for Db2 on z/OS .....	151
Prerequisites .....	152
Installation Medium .....	152
Installation Procedure .....	153
Common Installation Steps .....	153
Installation Steps Specific to CICS .....	160
Installation Steps Specific to Com-plete .....	164
Installation Steps Specific to IMS TM .....	164
Installation Steps Specific to TSO .....	166
Installation Verification .....	167
Natural Parameter Modifications for Natural for Db2 .....	170
Special Requirements for Natural Tools for Db2 .....	174
Natural for Db2 Server Stub .....	176
XII Installing Natural for Db2 for zIIP on z/OS .....	183
13 Installing Natural for Db2 for zIIP on z/OS .....	185
Installation Medium .....	186
Prerequisites .....	186
Installation Procedure .....	188
NDZ Server Installation Steps .....	188
Add NDZ Support to Natural Batch Nucleus .....	191
XIII Installing Natural for VSAM on z/OS .....	193
14 Prerequisites .....	195
15 Installing Natural for VSAM on Adabas System Files on z/OS .....	197
Installation Medium .....	198
Installation Procedure .....	198
Installation Verification .....	202
16 Installing Natural for VSAM on VSAM System Files on z/OS .....	203
Installation Medium for VSAM .....	204
Installation Procedure for VSAM .....	205
Installation Verification on VSAM System Files .....	213
Restrictions .....	213
XIV Installing Natural Messaging on z/OS .....	215
17 Installing Natural Messaging on z/OS .....	217
Installation Medium .....	218
Installation Procedure .....	218
XV Installing Natural Security on z/OS .....	223
18 Installing Natural Security on z/OS .....	225
Prerequisites .....	226
Installation Medium .....	226
Installation Procedure .....	227
Installation Verification .....	230
XVI Installing Natural SAF Security on z/OS .....	231

19 Installing Natural SAF Security on z/OS .....	233
Prerequisites .....	234
Installation Medium .....	234
Installation Procedure .....	235
Installation Verification .....	241
XVII Installing Natural Advanced Facilities on z/OS .....	243
20 Installing Natural Advanced Facilities under CICS on z/OS .....	245
Prerequisites for CICS .....	246
Installation Medium for CICS .....	246
Installation Procedure for CICS .....	247
21 Installation Verification for Natural Advanced Facilities under CICS on z/OS .....	253
System Testing .....	254
NATSPPOOL Reason Codes .....	256
NATSPPOOL Initialization Console Messages .....	257
NATSPPOOL Print Server Messages .....	258
NATSPPOOL Abend Codes .....	258
22 Installing Natural Advanced Facilities under IMS TM on z/OS .....	259
Prerequisites for IMS TM .....	260
Installation Medium for IMS TM .....	260
Installation Procedure for IMS TM .....	260
XVIII Installing Natural Optimizer Compiler on z/OS .....	265
23 Installing Natural Optimizer Compiler on z/OS .....	267
Prerequisites .....	268
Installation Medium .....	268
Installation Procedure .....	268
Installation Verification .....	270
XIX Installing Natural Connection on z/OS .....	271
24 Installing Natural Connection on z/OS .....	273
Prerequisites .....	274
Installation Medium .....	274
Installation Procedure .....	275
Installation Verification .....	276
XX Installing Natural Review .....	277
25 Installing Natural Review .....	279
Prerequisites .....	280
Storage Requirements .....	280
Installation Medium .....	281
Installation Procedure .....	281
Installation Verification .....	289
XXI Installing Natural for zIIP on z/OS .....	293
26 Installing Natural for zIIP on z/OS .....	295
Prerequisites .....	296
Installation Procedure .....	296
Installation Verification .....	298

---

# Preface

---

This documentation describes the installation of base Natural and Natural add-on products on z/OS.

<b>Basic Information:</b> <ul style="list-style-type: none"><li>■ <a href="#">Installation Process and Major Natural Features</a></li></ul>
<b>Base Natural:</b> <ul style="list-style-type: none"><li>■ <a href="#">Installing Natural</a></li></ul>
<b>Base Natural - Optional Components:</b> <ul style="list-style-type: none"><li>■ <a href="#">Installing ICU for Adabas &amp; Natural</a></li><li>■ <a href="#">Installation for REQUEST DOCUMENT, PARSE JSON, and PARSE XML Statements</a></li><li>■ <a href="#">Installing Entire System Server Interface</a></li><li>■ <a href="#">Installing Software AG Editor</a></li></ul>
<b>TP Monitor Interfaces:</b> <ul style="list-style-type: none"><li>■ <a href="#">Installing Natural CICS Interface</a></li><li>■ <a href="#">Installing Natural Com-plete/SMARTS Interface</a></li><li>■ <a href="#">Installing Natural IMS TM Interface</a></li><li>■ <a href="#">Installing Natural TSO Interface</a></li></ul>
<b>Database Management System Interfaces:</b> <ul style="list-style-type: none"><li>■ <a href="#">Installing Natural for Db2</a></li><li>■ <a href="#">Installing Natural for Db2 for zIIP</a></li><li>■ <a href="#">Installing Natural for VSAM</a></li><li>■ <a href="#">Installing Natural Messaging</a></li></ul>
<b>Other Natural Add-On Products:</b> <ul style="list-style-type: none"><li>■ <a href="#">Installing Natural Security</a></li><li>■ <a href="#">Installing Natural SAF Security</a></li><li>■ <a href="#">Installing Natural Advanced Facilities</a></li><li>■ <a href="#">Installing Natural Optimizer Compiler</a></li><li>■ <a href="#">Installing Natural Connection</a></li></ul>

- [Installing Natural Review](#)
- [Natural for zIIP](#)



# 1

## About this Documentation

---

■ Document Conventions .....	2
■ Online Information and Support .....	2
■ Data Protection .....	3

## Document Conventions

---

Convention	Description
<b>Bold</b>	Identifies elements on a screen.
Monospace font	Identifies service names and locations in the format <i>folder.subfolder.service</i> , APIs, Java classes, methods, properties.
<i>Italic</i>	Identifies:  Variables for which you must supply values specific to your own situation or environment. New terms the first time they occur in the text. References to other documentation sources.
Monospace font	Identifies:  Text you must type in. Messages displayed by the system. Program code.
{ }	Indicates a set of choices from which you must choose one. Type only the information inside the curly braces. Do not type the { } symbols.
	Separates two mutually exclusive choices in a syntax line. Type one of these choices. Do not type the   symbol.
[ ]	Indicates one or more options. Type only the information inside the square brackets. Do not type the [ ] symbols.
...	Indicates that you can type multiple options of the same type. Type only the information. Do not type the ellipsis (...).

## Online Information and Support

---

### Product Documentation

You can find the product documentation on our documentation website at <https://documentation.softwareag.com>.

### Product Training

You can find helpful product training material on our Learning Portal at <https://learn.software-ag.com>.

### Tech Community

You can collaborate with Software GmbH experts on our Tech Community website at <https://tech-community.softwareag.com>. From here you can, for example:

- Browse through our vast knowledge base.
- Ask questions and find answers in our discussion forums.
- Get the latest Software GmbH news and announcements.
- Explore our communities.
- Go to our public GitHub and Docker repositories at <https://github.com/softwareag> and <https://hub.docker.com/publishers/softwareag> and discover additional Software GmbH resources.

## Product Support

Support for Software GmbH products is provided to licensed customers via our Empower Portal at <https://empower.softwareag.com>. Many services on this portal require that you have an account. If you do not yet have one, you can request it at <https://empower.softwareag.com/register>. Once you have an account, you can, for example:

- Download products, updates and fixes.
- Search the Knowledge Center for technical information and tips.
- Subscribe to early warnings and critical alerts.
- Open and update support incidents.
- Add product feature requests.

## Data Protection

---

Software AG products provide functionality with respect to processing of personal data according to the EU General Data Protection Regulation (GDPR). Where applicable, appropriate steps are documented in the respective administration documentation.



# I Installation Process and Major Natural Features on z/OS

---



## 2 Installation Process and Major Natural Features on z/OS

---

■ General Prerequisites and System Support .....	8
■ Installation Medium .....	9
■ Installation Method .....	10
■ System Maintenance Aid (SMA) .....	10
■ Sample Installation Jobs .....	11
■ Installation Job Identification .....	11
■ Overall Installation Procedure .....	12
■ Installation Verification .....	12
■ INPL Utility .....	12
■ Natural Nucleus Components .....	12
■ Natural System Files .....	16

This document provides general information on the prerequisites and processes required to install base Natural and Natural add-on products. In addition, it describes installation tools and major Natural components required for installation.

**Notation** *vrs* or *vr*:

When used in this document, the notation *vrs* or *vr* represents the relevant product version (see also Version in the *Glossary*).

## General Prerequisites and System Support

---

Before beginning the installation process, consider the following:

- Be sure to read the current Natural for z/OS *Release Notes* for information on software and hardware requirements, known issues and changes to the documentation. These *Release Notes* apply to base Natural and Natural add-on products.
- A supported version of the operating system on which Natural is to run must be installed. For the supported operating systems and versions, refer the **Product Version Availability** section at <https://empower.softwareag.com/>.
- A supported version of the TP monitor/online interface used with Natural must be installed. For the supported versions, refer to *TP Monitors/Online Interfaces* in the current Natural for z/OS *Release Notes*.
- A supported version of Adabas must be installed to store the Natural system files. See also [Natural System Files](#).

For the supported versions, refer to *Database Management Systems* in the current Natural for z/OS *Release Notes*.

- A supported version of each database management or file system used to store the user data processed with Natural must be installed.

For the supported versions, refer to *Database Management Systems* in the current Natural for z/OS *Release Notes*.



**Note:** For information regarding product compatibility with IBM platforms and any IBM requirements, see <https://www.softwareag.com/ibm>.



## Installation Medium

The installation medium (for example, tape or CD-ROM) contains all data sets required to install base Natural for z/OS and the Natural add-on products.

The software required for the optional Natural components are contained in the data sets supplied for base Natural. The software required for the Natural add-on products are contained in separate product data sets which are listed in the product-specific sections of the *Installation for z/OS* documentation. In addition to the product data sets, the installation medium can contain the latest fix updates for the supplied products.

The names of the product data sets begin with a product code that identifies each product, as in the following table:

Product Code	Product Name
NAF	Natural Advanced Facilities
NAT	Natural
NAZBT	Natural Batch for zIIP
NAZCI	Natural for CICS for zIIP
NAZCO	Natural for Com-plete for zIIP
NCF	Natural Com-plete/SMARTS Interface (corresponds to Natural Com-plete Interface)
NCI	Natural CICS Interface
NDB	Natural for Db2
NDZ	Natural for Db2 for zIIP
NII	Natural IMS TM Interface
NOC	Natural Optimizer Compiler
NSC	Natural Security
NSF	Natural SAF Security
NTC	Natural Connection
NTI	Natural TSO Interface
NVS	Natural for VSAM
RNM	Natural Review

## Product Delivery Report

Each installation medium is delivered with a Product Delivery Report providing the following information:

- A list of all data sets contained on the medium.
- The sequence in which the data sets are located on the medium.
- Attribute descriptions of each data set.

## Installation Method

---

The installation is performed by installation jobs that contain the JCL required to identify the job to the operating system and run the job.

There are two methods for creating and running the installation jobs:

- using the jobs generated by System Maintenance Aid (SMA), or
- using the jobs created from the sample installation jobs provided.

The *Installation for z/OS* documentation solely describes the installation procedure for the jobs generated by SMA. If you do not use SMA for installation, refer to the example installation jobs supplied on the installation medium.

SMA is supplied with base Natural.

## System Maintenance Aid (SMA)

---

For each step of the installation procedure, System Maintenance Aid (SMA) generates an installation job according to your specifications in SMA. You then submit and run the generated job.

Before you can start generating the jobs, you have to load the `SMT111.TABS` data set from the installation medium into the SMA system file. `SMT111.TABS` contains the tables SMA requires to build the jobs.

SMA is supplied with base Natural. For instructions on loading the data set and using SMA, refer to the *System Maintenance Aid* documentation.

## Readme File

For installation guidance and information on new or changed SMA parameters and Natural features, you can view the product-specific Readme files by using the appropriate SMA function.

### ➤ To view a product-specific Readme

- From the product list on an SMA **Maintenance** screen, execute the RM (**Show Readme File**) command for the required product(s).

## Sample Installation Jobs

---

The sample installation jobs that can be used as an alternative to SMA are provided in a PDS library contained on the data set *product-code-vrs.JOBS* (for example, NAT828.JOBS) shipped on the installation medium. All sample installation jobs provided are listed and described in the README document that accompanies the shipment.

You need to adapt the sample installation jobs to your requirements.

## Installation Job Identification

---

Each installation job indicates the **product code** and version (for example, NAT828) of the corresponding product (for example, Natural).

Each step of the installation procedure is identified by a job name (for example, I050) and one or more steps (for example, Steps 0100 and 0101 for Job I050) that indicate the tasks performed by the job. The job name can have a prefix such as a **product code** (for example, NATI050). The prefix can be specified with the SMA parameter JOB-PREFIX (the default prefix is SMA).

A sample installation job from the PDS library can also have a suffix letter which indicates a variant of the job. For example: Job I060L is a variant of Job I060 and used if support of the IBM Language Environment (LE) is required. In SMA, the same variant is executed with Job I060 and the appropriate SMA parameter setting.

## Overall Installation Procedure

---

The installation process comprises the following:

1. Creating the Natural system files.
2. Creating the Natural parameter module.
3. Creating the Natural nucleus.
4. Loading the Natural objects.
5. Installing the optional Natural components.
6. Installing the Natural add-on products.

## Installation Verification

---

Verify the successful completion of the installation by starting Natural and testing the system functions as described in the relevant sections of the *Installation for z/OS* documentation.



**Note:** If Natural Security is installed, certain Natural functions and libraries can be restricted to specific users.

## INPL Utility

---

The installation instructions frequently refer to the Natural INPL utility which is used to load the data sets (for example, `NATVRS.INPL`) contained on the Natural installation medium into the [Natural system files](#). The INPL utility is invoked with the Natural system command `INPL`. For detailed information on the INPL utility, refer to the *Utilities* documentation.

## Natural Nucleus Components

---

The Natural nucleus consists of two functional parts: the environment-independent nucleus and the environment-dependent nucleus.



**Note:** If you maintain different versions of Natural, you must use distinctive names for the nuclei to identify each version.

This section covers the following topics:

- Environment-Independent Nucleus
- Environment-Dependent Nucleus
- Modules for Static Linking
- Modules for Dynamic Loading
- Modules Called Dynamically

## Environment-Independent Nucleus

The environment-independent nucleus contains components that are independent of the operating system or TP system (online interface) being used. The same instance of the environment-independent nucleus can be used in different online and batch environments in different address spaces. The environment-independent nucleus is reentrant.

The environment-independent nucleus can reside in the extended link pack area (ELPA) where it can be shared between different address spaces.

A module (such as the environment-independent nucleus) loaded into the ELPA is protected against modification. Therefore, tests for modifications of the environment-independent nucleus should be performed in a separate environment. You can use the operator command SETPROG to load a modified environment-independent nucleus into the ELPA.

If the environment-independent nucleus resides in the ELPA, multiple batch jobs or TP regions (for example, CICS) share the same instance of the environment-independent nucleus. This results in a significant reduction of paging activities and virtual storage consumption.

## Modules for Linking

The following modules must be linked to the environment-independent nucleus:

- Modules for base Natural
- Environment-independent modules of Natural add-on products
- Environment-independent user-supplied modules

When using System Maintenance Aid (SMA), the required modules are linked to the environment-independent nucleus during the appropriate installation job/step. Modules that can optionally be linked are mentioned in the *Installation Procedure*.

The installation of the environment-independent nucleus is described in *Link the Nucleus* in the *Installation Procedure*.

## Specifying the Nucleus Name

The name of the environment-independent nucleus to be used is specified with the Natural profile parameter NUCNAME in the Natural parameter module during the installation of the environment-dependent nucleus. You can specify NUCNAME as a dynamic parameter in the primary parameter input, but you cannot specify NUCNAME in the input strings of the Natural profile parameter PROFILE or SYS.

The Natural parameter module is described in *Building a Natural Parameter Module* in the *Operations* documentation. NUCNAME, PROFILE and SYS are described in the *Parameter Reference* documentation.

If you maintain different versions of Natural, we recommend that you use distinctive names for the nucleus to clearly identify each version and environment, for example: NAT828 for the environment-independent nucleus, NAT828C for the environment-dependent nucleus for a CICS interface, and NAT828B for the batch environment.

## Environment-Dependent Nucleus

The environment-dependent nucleus contains components that depend on the operating or TP system being used.

In addition to the environment-independent nucleus, every single address space in which Natural runs requires an environment-dependent nucleus containing modules that perform actions specific to the operating or TP system. The environment-dependent nucleus assumes control from the operating or TP system at the start of a Natural session, loads the environment-independent nucleus and passes control to it.

## Modules for Linking

The following modules must be linked to the environment-dependent nucleus:

- Environment-specific Natural interface modules
- Environment-specific work file and print file modules
- Environment-specific Natural parameter module (see also *Building a Natural Parameter Module* in the *Operations* documentation)
- Environment-dependent modules of Natural add-on products
- Adabas link routine (ADALNK or ADAUSER)
- Environment-dependent user-supplied modules defined as CSTATIC in the Natural parameter module. The Natural profile parameter CSTATIC is described in the *Parameter Reference* documentation.

When using System Maintenance Aid (SMA), the required modules are linked to the environment-dependent nucleus during the appropriate installation job/step. Modules that can optionally be linked are mentioned in the *Installation Procedure*.

The installation of the environment-dependent nucleus is described in *Link the Nucleus* in the *Installation Procedure*.

## Modules for Static Linking

Both the Natural configuration module `NATCONFIG` (described in the *Operations* documentation) and the Natural parameter module contain the Natural-supplied list of additional modules to be statically linked to the nucleus.

The Natural parameter module also contains the user-supplied list of additional modules to be statically linked to the nucleus as specified with the Natural profile parameter `CSTATIC`.

Each entry of these lists consists of a program name and a V-type address constant which must be resolved by linking the corresponding module to the Natural parameter module.

The Natural-supplied list provided with `NATCONFIG` is used if the Natural parameter module is not linked to the environment-independent nucleus. If modules are statically linked to the environment-independent nucleus, a Natural parameter module that defines all these modules must also be linked to the environment-independent nucleus.

Optionally, you can specify an alternative Natural parameter module by using the Natural profile parameter `PARM` (described in the *Parameter Reference* documentation). An alternative parameter module takes precedence over a parameter module that is linked to either the environment-independent or the environment-dependent nucleus.

## Merging Module Lists

During initialization of a Natural session, up to three lists of statically-linked modules (specified with the Natural profile parameter `CSTATIC`) are merged:

- Base list for the merge is the list of the Natural parameter module specified with the Natural profile parameter `PARM`;
- V-type address constants not resolved in this list are resolved using the Natural parameter module linked to the environment-dependent nucleus;
- V-type address constants not yet resolved are resolved using the Natural parameter module linked to the environment-independent nucleus.

If a user-supplied module is to be statically linked to the environment-independent nucleus, it must be specified in the Natural parameter module linked to the environment-independent nucleus as well as in the Natural parameter module specified with the Natural profile parameter `PARM`.

## Modules for Dynamic Loading

When initializing a Natural session, you can also dynamically load the modules (supplied with the product or user-defined) that have been defined for static linking. For information on whether the module of a Natural add-on product is suitable for dynamic loading, read the documentation for your specific Natural add-on product.

For information on defining external names for static non-Natural programs and dynamic linking and controlling these programs, see the Natural profile parameters `RCA` and `RCALIAS` described in the *Parameter Reference* documentation.

## Modules Called Dynamically

If a module is not defined for static linking, Natural attempts to load and execute the module using environment-dependent functions (for example, `EXEC CICS LINK` under CICS) when the corresponding Natural `CALL` statement is executed.

## Natural System Files

---

The Natural system files are stored in an Adabas database.

The table below lists and describes the Natural system files that are usually available in a Natural environment. The availability of the system files and the data contained in the files depends on the products installed in addition to base Natural.

The settings for the system files are defined with Natural profile parameters of the same names (exception: scratch-pad file). You can follow the hyperlinks in the table below to read details about these parameters in the *Parameter Reference* documentation.

System File	Supplied with	File Contents
FNAT	Base Natural	All objects required for Natural system applications.
FUSER	Base Natural	User-specific objects required for user-defined applications.
FPROF	Base Natural	Parameter profiles specified by the profile parameter <code>PROFILE</code> , provided no database information is supplied as subparameter of <code>PROFILE</code> .
Scratch-pad file	Base Natural	Data that is not stored explicitly as a Natural object in another system file. See also <i>Natural Scratch-Pad File</i> in the <i>Operations</i> documentation.
FDIC	Base Natural	Natural Data Definition Modules (DDMs).  If Predict is installed, <code>FDIC</code> also contains data for the Predict dictionary system.



System File	Supplied with	File Contents
		If the Natural Development Server is installed, FDIC also contains application data and holds object locking information.
FREG	Base Natural	Registry data that is not stored explicitly in another system file.
FSEC	Natural Security	Control information required for security definitions.
FSP00L	Natural Advanced Facilities	Control and spooling information required to output a report on a screen or printer and obtain print statistics.

It is also possible to store Natural system files in a VSAM file system if **Natural for VSAM** is installed. The *Installation for z/OS* documentation describes the installation steps that apply when using an Adabas database for storage.

### Defining a Scratch-Pad File

Like all other system files, the scratch-pad file is a logical file. The logical file number of the scratch-pad file is 212.

Since there is no mnemonic for the scratch-pad file such as FNAT and FUSER or FDIC, it has to be defined:

- either statically by using the macro NTLFILE in the Natural parameter module or
- dynamically by using the Natural profile parameter LFILE.

#### Examples of NTLFILE and LFILE Definitions:

LFILE Parameter:

```
LFILE=(212,physical-dbid,physical-fnr,password,cipher-key)
```

NTLFILE Macro:

```
NTLFILE 212,physical-dbid,physical-fnr,password,cipher-key
```



## II Installing Natural on z/OS

---



# 3

## Installing Natural on z/OS

---

■ Prerequisites .....	22
■ Installation Medium .....	22
■ Installation Procedure .....	24
■ Installation Verification .....	37

This document describes the steps for installing Natural (product code NAT) on z/OS.

**Related Topic:**

For information on how to run Natural in a z/OS environment, see the *Operations* documentation.

**Notation *vrs* or *vr*:**

When used in this document, the notation *vrs* or *vr* represents the relevant product version (see also Version in the *Glossary*).

## Prerequisites

---

See [General Prerequisites and System Support](#).

## Installation Medium

---

The **installation medium** contains the following data sets required for product installation:

Data Set Name	Contents
ICS <i>vrs</i> .LOAD	Load modules for ICU for Adabas & Natural (ICS)
ICS <i>vrs</i> .SRCE	Source modules for ICU for Adabas & Natural (ICS)
MLC <i>vrs</i> .JOBS	Sample installation jobs for the z/OS license check software  The placeholder <i>vrs</i> in the library name represents the version of the license check software, which is not necessarily the same as the version of Natural.  For detailed information on the license check software, see <i>Mainframe Product Licensing</i> .
NAT <i>vrs</i> .LICS	Load modules for the z/OS license check software containing the LICUTIL license utility  The placeholder <i>vrs</i> in the library name represents the version of the license check software, which is not necessarily the same as the version of Natural.  For detailed information on the license check software and the LICUTIL utility, see <i>Mainframe Product Licensing</i> .
NAT <i>vrs</i> .LOAD	Load modules
	Product license file for Natural  For information on the license file and product licensing, see <i>Mainframe Product Licensing</i> .
NAZ <i>vrs</i> .LICS	Product license file for Natural Batch for zIIP  This license file is also valid the Natural TSO Interface.

Data Set Name	Contents
	For information on the license file and product licensing, see <i>Mainframe Product Licensing</i> .
NATvrs.SRCE	Source modules and macros
NATvrs.SYSF	Natural system file definitions
NATvrs.OBJS	Object modules
NATvrs.JOBS	Sample installation jobs
NATvrs.INPL	Natural objects with examples

## Copying Data Sets to a z/OS Disk

Copy the data sets from the supplied installation medium to your disk before you perform the individual installation procedure for each component to be installed.

The way you copy the data sets depends on the installation method and the medium used:

- If you use System Maintenance Aid (SMA), refer to the copy job instructions provided in the *System Maintenance Aid* documentation.
- If you are not using SMA and want to copy the data sets from CD-ROM, refer to the README.TXT file on the CD-ROM.
- If you are not using SMA and want to copy the data sets from tape, follow the instructions in this section.

This section explains how to copy all data sets from tape to disk.

- [Step 1: Copy Data Set COPY.JOB from Tape to Disk](#)
- [Step 2: Modify hilev.COPY.JOB on Your Disk](#)
- [Step 3: Submit COPY.JOB](#)

### Step 1: Copy Data Set COPY.JOB from Tape to Disk

- Modify the following sample job according to your requirements:

```
//SAGTAPE JOB SAG,CLASS=1,MSGCLASS=X
//* -----
//COPY EXEC PGM=IEBGENER
//SYSUT1 DD DSN=COPY.JOB,
// DISP=(OLD,PASS),
// UNIT=(CASS,,DEFER),
// VOL=(,RETAIN,SER=tape-volser),
// LABEL=(2,SL)
//SYSUT2 DD DSN=hilev.COPY.JOB,
// DISP=(NEW,CATLG,DELETE),
// UNIT=3390,VOL=SER=disk-volser,
// SPACE=(TRK,(1,1),RLSE),
// DCB=*.SYSUT1
```

```
//SYSPRINT DD SYSOUT=*  
//SYSIN DD DUMMY  
//
```

where:

*tape-volser* is the VOLSER of the tape, for example: T12345,  
*hilev* is a valid high-level qualifier, and  
*disk-volser* is the VOLSER of the disk.

- Execute the job to copy the data set `COPY.JOB` to your disk.

### Step 2: Modify `hilev.COPY.JOB` on Your Disk

- Modify `hilev.COPY.JOB` according to your requirements:

Set `EXPDT` to a valid expiration date, for example, 99365.

Set `HILEV` to a valid high-level qualifier, for example, `USERLIB`.

Set `LOCATION` to a storage location, for example, `STORCLAS=ABC` or `UNIT=3390,VOL=SER=USR123`.

### Step 3: Submit `COPY.JOB`

- Execute `hilev.COPY.JOB` to copy single, multiple, or all data sets to your disk.

## Installation Procedure

---

Be sure to read [Installation Process and Major Natural Features](#) before you start the installation procedure.

- Step 1: Allocate and Copy the SMA User Libraries
- Step 2: Prepare, Convert, Assemble and Link the License File
- Step 3: Link Natural Modules to an APF Library
- Step 4: Start the Global Buffer Pool
- Step 5: Load the FNAT System File Definition
- Step 6: Load the FUSER System File Definition
- Step 7: Load the Scratch-Pad File Definition
- Step 8: Load the FREG System File Definition
- Step 9: Load the FDIC System File Definition
- Step 10: Load the FSEC System File Definition
- Step 11: Build the Natural Configuration Module
- Step 12: Build the Natural-Specific IBM Language Environment Options
- Step 13: Build the Natural Parameter Module
- Step 14: Link the Nucleus
- Step 15: Load New Natural Objects and Natural Error Messages



- [Step 16: Create and Format the Roll File](#)
- [Step 17: Create and Start the Natural Roll Server](#)
- [Step 18: Create and Start the Natural Authorized Services Manager](#)
- [Step 19: Create and Start the Message Buffer Pool](#)
- [Step 20: Create Sample JCL for the Natural RPC Server](#)

## Step 1: Allocate and Copy the SMA User Libraries

(Job I002, Steps 0010, 0020)

- Allocate the user-specific source, load and save libraries of System Maintenance Aid (SMA) and copy them to the `LOAD.SAVE` library.

## Step 2: Prepare, Convert, Assemble and Link the License File

(Job I007, Steps 0101, 0102, 0104 and optional Steps 0111, 0112, 0114, and optional Steps 1201, 1202, 1204)

You must install a valid Natural license file. An additional license file is required if you want to install Natural Batch for zIIP to enable support of the IBM z/IIP (IBM System z Integrated Information Processor).

For detailed information on the license file and product licensing, see *Mainframe Product Licensing*.

1. Copy the license file from the supplied installation medium to disk or transfer it from the PC as described in *Transferring a License File from PC to a z/OS Host Using FTP* in *Mainframe Product Licensing*.
2. Check, convert, assemble, and link the license file:

Step 0101	Check license file <code>NATvrs.LICS</code> . This job runs the CHECK function of the LICUTIL license utility (see below).
Step 0102	Convert license file into an assembler source. This job runs the MAKE function of the LICUTIL license utility (see below).
Step 0104	Assemble and link the assembler source to generate load module <code>NATLIC</code> . This module is then linked to the nucleus in <a href="#">Job I060</a> .

The functions and option settings provided by LICUTIL are described in *Using the License Utility: LICUTIL* in *Mainframe Product Licensing*.

3. This step is only required if you want to install Natural Batch for zIIP for a batch, batch server or TSO environment.

Check, convert, assemble, and link the license file supplied for Natural Batch for zIIP:

Step 0111	Check license file <code>NAZvrs.LICS</code> . This job runs the CHECK function of the LICUTIL license utility.
Step 0112	Convert license file into an assembler source. This job runs the MAKE function of the LICUTIL license utility.
Step 0114	Assemble and link the assembler source to generate load module <code>NAZLIC</code> . This module is then linked to the nucleus in <a href="#">Job I060</a> .

4. This step is only required if you want to install the Natural Optimizer Compiler.

Check, convert, assemble, and link the license file supplied for the Natural Optimizer Compiler:

Step 1201	Check license file <code>NOCvrs.LICS</code> . This job runs the CHECK function of the LICUTIL license utility.
Step 1202	Convert license file into an assembler source. This job runs the MAKE function of the LICUTIL license utility.
Step 1204	Assemble and link the assembler source to generate load module <code>NOCLIC</code> . This module is then linked to the nucleus in <a href="#">Job I060</a> .

5. This step is only required if you want to install Natural for Db2.

Check, convert, assemble, and link the license file supplied for Natural for Db2:

Step 1601	Check license file <code>NDBvrs.LICS</code> . This job runs the CHECK function of the LICUTIL license utility.
Step 1602	Convert license file into an assembler source. This job runs the MAKE function of the LICUTIL license utility.
Step 1604	Assemble and link the assembler source to generate load module <code>NDBLIC</code> . This module is then linked to the nucleus in <a href="#">Job I060</a> .

### Step 3: Link Natural Modules to an APF Library

(Job I009, Steps 1200, 1210, 1220, 1230, 1232, 1240, 1250)

If you want to use one of the Natural components listed in the table below, link the appropriate Natural module to an Authorized Program Facility (APF) library.

The table below indicates when a component is required and the System Maintenance Aid (SMA) parameters used to specify the module names.

Step/Component to be Installed	Module	SMA Parameter
Step 1200: Global Buffer Pool <sup>1</sup>  See also <a href="#">Step 4: Start the Global Buffer Pool</a> .	NATGBP <i>vr</i>	NAT - GLOBAL - BP  or  EDT - GLOBAL - BP
Step 1210: Authorized Services Manager (ASM) <sup>1</sup>  You must use an ASM in the following cases: <ul style="list-style-type: none"> <li>■ The Natural profile parameter BPPROP is set to PLEX or GLOBAL or GPLEX (buffer pool propagation is used).</li> <li>■ Natural global buffer pools are allocated in the system key; see <a href="#">Step 4: Start the Global Buffer Pool</a>.</li> <li>■ Natural under CICS is used in a Parallel Sysplex environment (SIP function is required).</li> <li>■ Natural under IMS TM is used in terminal-oriented, non-conversational mode (SIP function is required).</li> <li>■ Natural under IMS TM is used, with the Accounting function writing SMF records.</li> <li>■ Enablement of zIIP support is required.</li> <li>■ Enablement of the Shared Memory Objects File Server of Natural for Db2 is required.</li> <li>■ Natural Development Server with SECURITY_CACHING=YES is used.</li> </ul> See also <a href="#">Step 19: Create and Start the Natural Authorized Services Manager</a> .	NATASM <i>vr</i>	NAT - ASM
Step 1220: Natural Roll Server <sup>1</sup>  You must use a Natural Roll Server in the following cases: <ul style="list-style-type: none"> <li>■ The server front-end of Natural RPC (Remote Procedure Call) is used.</li> <li>■ Natural under IMS TM runs in a Parallel Sysplex environment.</li> <li>■ Natural under CICS runs in a Parallel Sysplex or CICSplex environment.</li> </ul> See also <a href="#">Step 17: Create and Format the Roll File</a> and <a href="#">Step 18: Create and Start the Natural Roll Server</a> .	NATRSM <i>vr</i>	ROLLSRV
Step 1240: Message Buffer Pool <sup>1</sup>  See also <a href="#">Step 20: Create and Start the Message Buffer Pool</a> .	NATMBP <i>vr</i>	NAT - MTBP
Step 1250: Impersonation with the Natural RPC (Remote Procedure Call) <sup>2</sup>  See also <a href="#">Step 23: Create Sample JCL for the Natural RPC Server</a> .	RPC Server Front-End	NAT - RPC - FRONT

<sup>1</sup> described in the *Operations* documentation

<sup>2</sup> described in the *Natural RPC (Remote Procedure Call)* documentation

#### Step 4: Start the Global Buffer Pool

(Job I015, Steps 0100, 0101, 0102, 0104)

These steps are only required if you want to use a global buffer pool. For further information on the global buffer pool, see *Natural Global Buffer Pool* in the *Operations* documentation.

Installation of the Natural Authorized Services Manager (ASM) is mandatory if `ALLOWUSERKEYCSA(NO)` applies by default or has explicitly been specified in `SYS1.PARMLIB(DIAGxx)`. See also *Allocation of the Natural GBP* in the *Operations* documentation.

- Create the jobs required to start and stop a global buffer pool:

Step	Job	Function
0100	GBNASTRT	Start global buffer pool
0101	GBNASTOP	Stop global buffer pool
0102	GBEDSTRT	Start editor global buffer pool
0104	GBEDSTOP	Stop editor global buffer pool

- If you want to use a Natural global buffer pool, start the job `GBNASTRT` before using Natural.
- If you want to use an editor global buffer pool, start the job `GBEDSTRT` before using Natural.

#### Step 5: Load the FNAT System File Definition

(Job I050, Step 0100)

Skip this step if you want to use an existing Natural `FNAT` system file.

Load the new Natural `FNAT` system file definition:

1. Specify the database ID and file number of the Adabas file where to load the new `FNAT` system file definition by using the Adabas `ADALOD` utility.

In addition, you must specify this database ID and file number in the Natural parameter module as described in [Step 13: Build the Natural Parameter Module](#).

2. Load the `FNAT` system file definition contained in the `NATvrS.SYSF` data set by using the Adabas `ADALOD` utility.

The following `ADALOD` utility parameter must *not* be changed:

```
ISNREUSE=YES
```

The following ADALOD utility parameter setting is recommended:

```
USERISN=YES
```

If you reorganize an FNAT file or if you unload from or load data to the FNAT file (for example, by using ADAULD/ADALOD), you must specify the parameter USERISN=YES for the ADALOD utility to avoid Natural errors NAT7397 and NAT9988 which require that you re-INPL the Natural FNAT system file.

If you specify the parameter USERISN=YES when you load a new FNAT system file, and you unload data from this FNAT file, the ADALOD utility assumes USERISN=YES as a default setting when re-loading the data into the FNAT file.

## Step 6: Load the FUSER System File Definition

(Job I050, Step 0101)

Skip this step if you want to use an existing Natural FUSER system file.

Load the new Natural FUSER system file definition:

1. Specify the database ID and file number of the Adabas file where to load the new FUSER system file definition by using the Adabas ADALOD utility.

In addition, you must specify this database ID and file number in the Natural parameter module as described in [Step 13: Build the Natural Parameter Module](#).

2. Load the FUSER system file definition contained in the NATvrs.SYSF data set by using the Adabas ADALOD utility.

The following ADALOD utility parameter must *not* be changed:

```
ISNREUSE=YES
```

3. If you want to use existing Natural applications, copy all user-written objects to the empty FUSER.
4. If you want to use Natural Application Programming Interfaces (APIs), see *Using a Natural API* in the SYSEXT Utility documentation for further guidance.

## Step 7: Load the Scratch-Pad File Definition

(Job I050, Step 0102)

This step is only required if you want to use read-only system files. See also *Natural Scratch-Pad File* in the *Operations* documentation.

You can skip this step if you want to use an existing Natural scratch-pad file.

Load the new Natural scratch-pad system file definition:

1. Set the System Maintenance Aid (SMA) parameter NAT-SCRF to Y (Yes).
2. Specify the database ID and file number of the Adabas file where to load the scratch-pad file by using the Adabas ADALOD utility.

In addition, you must specify this database ID and file number in the Natural parameter module as described in [Step 13: Build the Natural Parameter Module](#).

3. Load the scratch-pad system file definition contained in the NAT<sub>vr</sub>s.SYSF data set by using the Adabas ADALOD utility.

The following ADALOD utility parameter must *not* be changed:

```
ISNREUSE=YES
```

## Step 8: Load the FREG System File Definition

(Job I050, Step 0104)

This step is only required if registry information must be available to control concurrent user sessions limited with the Natural profile parameter UCONMAX (see the *Parameter Reference* documentation).

You can skip this step if you want to use an existing Natural FREG system file.

Load the new Natural FREG system file definition:

1. Set the System Maintenance Aid (SMA) parameter NAT-FREG to Y (Yes).
2. Specify the database ID and file number of the Adabas file where to load the FREG system file by using the Adabas ADALOD utility.

In addition, you must specify this database ID and file number in the Natural parameter module as described in [Step 13: Build the Natural Parameter Module](#).

3. Load the FREG system file definition contained in the NAT<sub>vr</sub>s.SYSF data set by using the Adabas ADALOD utility.

The following ADALOD utility parameter must *not* be changed:

```
ISNREUSE=YES
```

### Step 9: Load the FDIC System File Definition

(Job I050, Step 0103)

Skip this step:

- if you want to install Predict. In this case, use the corresponding installation step described in the Predict *Installation* documentation.
- if you want to use an existing Natural FDIC system file.

Load the new Natural FDIC system file definition:

1. Specify the database ID and file number of the Adabas file where to load the new FDIC system file definition by using the Adabas ADALOD utility.

In addition, you must specify this database ID and file number in the Natural parameter module as described in [Step 13: Build the Natural Parameter Module](#).

2. Load the FDIC system file definition contained in the NAT $\nu$ rs.SYSF data set by using the Adabas ADALOD utility.

The following ADALOD utility parameter must *not* be changed:

```
ISNREUSE=YES
```

### Step 10: Load the FSEC System File Definition

(Job I050, Step 9900)

Skip this step, if you do not use Natural Security.

- If you use Natural Security, refer to [Installing Natural Security](#).

## Step 11: Build the Natural Configuration Module

(Job I055, Step 0110)

This step is only required if you need to change the delivered NATCONFIG module, for example, to adapt the NTDVCE macro definition to your requirements.

1. Change and assemble the source contained in the *hilev.NATvrs.SRCE* data set.
2. Link the resulting Natural configuration module NATCONFIG to the environment-independent nucleus (see [Step 14: Link the Nucleus](#)).

For more information on the configuration tables in NATCONFIG, refer to *Natural Configuration Tables* in the *Operations* documentation.

## Step 12: Build the Natural-Specific IBM Language Environment Options

(Job I055, Step 0120 or 0130)

Build the Natural-specific runtime options for the IBM Language Environment (LE).

Step 0120 is only required if you need to adapt the LE options at the .MVSDEF label in the delivered NATLEOPT module to your requirements.

1. Set the System Maintenance Aid (SMA) parameter NAT-LEOPT to Y (Yes); the default setting is N (No).
2. Change the required LE options in the NATLEOPT source module contained in the NATvrsSRCE data set at the .MVSDEF label.
3. Assemble and link the NATLEOPT source module contained in the NATvrsSRCE data set.
4. Link the resulting NATLEOPT module to the environment-dependent nucleus (see [Step 14: Link the Nucleus](#)).

Step 0130 is only required if you have any non-Natural programs running in 24-bit addressing mode:

1. Set the SMA parameter NAT-LEOPT-AMODE24 to Y (Yes); default is N (No).
2. Assemble the NATLEOPT module contained in the NATvrsSRCE data set.
3. Link the resulting NATLEOPT module to the environment-dependent nucleus (see [Step 14: Link the Nucleus](#)).



## Step 13: Build the Natural Parameter Module

(Job I060, Steps 0010, 0015)

Build the Natural parameter module for batch mode.

1. Modify the settings of the Natural profile parameters supplied with this job, if required. The parameters and corresponding macros (if applicable) are described in the *Parameter Reference* documentation. The most important parameter/macro settings are described below.
  - Configure the z/OS batch interface: Modify the settings of the parameters supplied with the NTOSP macro to meet your requirements. For descriptions of these parameters, see the corresponding dynamic profile parameter OSP.
  - Adapt the following parameters:

```
FNAT=(database-id,file-number)
FUSER=(database-id,file-number)
FDIC=(database-id,file-number)
```

where *database-id* and *file-number* are either the database ID and file number you specified when loading the new FNAT, FUSER and FSEC system files (see [Step 5](#), [Step 6](#) and [Step 9](#), respectively), or the database ID and file number of your existing Natural system files.

These parameters are supplied with the NTPRM macro described in the *Operations* documentation.

- If you want to limit the number of concurrent users with the Natural profile parameter UCONMAX, proceed as follows:

Supply the following parameter with the NTPRM macro:

```
FREG=(database-id,file-number)
```

where *database-id* and *file-number* are either the database ID and file number you specified when loading the new Natural FREG system file (see [Step 8](#)), or the database ID and file number of your existing Natural FREG system file.

- If you want to use read-only system files, proceed as follows:

Supply the following parameter with the NTPRM macro:

```
ROSY=ON
```

Specify the NTLFILE macro (see the parameter LFILE):

```
NTLFILE 212,database-id,file-number
```

where *database-id* and *file-number* are the database ID and file number you specified when loading the new Natural scratch-pad file (see [Step 7](#)), or the database ID and file number of your existing Natural scratch-pad file.

- If you want to use a Natural global buffer pool, perform the following steps:

Specify the `NTBPI` macro (see the `BPI` parameter):

```
NTBPI TYPE=NAT,NAME=gbp-name
```

where *gbp-name* is the name of the Natural global buffer pool to be used.

Supply the following parameter with the `NTPRM` macro:

```
SUBSID=subsystem-name
```

where *subsystem-name* is the name of the Natural subsystem specified when creating the global buffer pool.

Make sure that the [System Maintenance Aid \(SMA\)](#) parameter `NAT-GLOBAL-BP` is set to Y (Yes). This is the default setting.

For detailed information on the Natural global buffer pool, see *Natural Global Buffer Pool under z/OS* in the *Operations* documentation.

2. Assemble and link the Natural parameter module.

## Step 14: Link the Nucleus

(Job I060, Steps 0020, 0105)

1. If you want Natural to run in the IBM Language Environment (LE), set the [System Maintenance Aid \(SMA\)](#) parameter `NAT-LE` to Y (Yes). The default setting is N (No).
2. Link the [environment-dependent nucleus](#) (Step 0020) for batch Natural.

The list of modules to be linked for the environment-dependent nucleus is supplied with Step 0020.

Do *not* link the environment-dependent nucleus with the linkage editor option `RENT`.

If you want Natural to run in the IBM Language Environment (LE), specify `ENTRY LESTART` instead of `ENTRY CMSTART`.

3. Link the [environment-independent nucleus](#) (Step 0105).

The list of modules to be linked for the environment-independent nucleus is supplied with Step 0105.

Ensure that the Natural profile parameter `NUCNAME` (see the *Parameter Reference* documentation) specified in the Natural parameter module contains the name of the module resulting from this link step.

## Step 15: Load New Natural Objects and Natural Error Messages

(Job I061, Step 0100)

- Load the Natural objects and Natural error messages from the `NATvrs.INPL` data set into the Natural system files by using the Natural [INPL utility](#).

The Natural error messages comprise short and long message texts and the German (`ULANG=2`) short message texts. You can use the `ERRUPPER` program of the Natural `SYSERR` utility to convert the message texts to upper case.

For details on the `ULANG` profile parameter and `ERRUPPER`, see the *Parameter Reference* and the *Utilities* documentation, respectively.

## Step 16: Create and Format the Roll File

(Job I200, Step 0101)

This step is only required if you want to use the Natural Roll Server. For information on the different types of roll files, see *Roll File and LRB* in the *Operations* documentation, and *Natural under CICS* and *Natural under IMS TM* in the *TP Monitor Interfaces* documentation.

- If you use the roll file of a previous version, it is sufficient to execute the `NATRSRFI RESET` function. See *Formatting the Roll File* in the *Operations* documentation.
- If you use a new roll file, create and start the job `FORMRF1` (supplied with Step 0101) before using Natural.

## Step 17: Create and Start the Natural Roll Server

(Job I200, Step 0102)

This step is only required if you want to use the Natural Roll Server described in *Natural Roll Server Operation* in the *Operations* documentation.

- Create and start the job `SAGRSM` (supplied with Step 0102) before using Natural. See *Starting the Roll Server* in the *Operations* documentation.

## Step 18: Create and Start the Natural Authorized Services Manager

(Job I200, Step 0103)

This step is only required if you want to use the Natural Authorized Services Manager (ASM) described in *Authorized Services Manager under z/OS* in the *Operations* documentation.

- Create and start the job SAGASM before using Natural.

## Step 19: Create and Start the Message Buffer Pool

(Job I200, Step 0107)

This step is only required if you want to use a message buffer pool described in *Message Buffer Pool* in the *Operations* documentation.

- Create and start the job SAGMTBP (supplied with Step 0107) before using Natural. See also *Operating the Message Buffer Pool* in the *Operations* documentation.

## Step 20: Create Sample JCL for the Natural RPC Server

(Job I200, Steps 0109, 0115, 0120)

These steps are only required if you want to use Natural RPC.

Sample Natural RPC server:

1. Set the parameters in the **System Maintenance Aid (SMA)** group `RPC` accordingly; in particular, set the parameter `NAT-RPC` to `Y` (Yes).

For further information, see *Starting a Natural RPC Server* and *Starting a Batch Server in a z/OS Environment* in the *Natural RPC (Remote Procedure Call)* documentation.

2. Create the `CMPRMIN` sample input to execute a Natural RPC server in batch mode (Step 0109).
3. Create the sample JCL to execute a standard Natural RPC server task without RPC server front-end (Step 0115).
4. Create the sample JCL to execute a Natural RPC server task by the RPC server front-end (Step 0120). This JCL is necessary for impersonation.

## Installation Verification

This section provides instructions for verifying the successful installation of Natural.

- [Test Batch Natural](#)
- [Test Online Natural](#)

### Test Batch Natural

You can use the following sample JCL to invoke Natural in batch mode and check whether the Natural system files are available:

```
//JOBNAME JOB ( , , , 999 ), CLASS=K, MSGCLASS=X, MSGLEVEL=(1,1)
//*
//NATBAT EXEC PGM=NATvr$BA, COND=(0,LT)
//STEPLIB DD DSN=NATURAL.BATCH.LIBRARY, DISP=SHR
// DD DSN=ADAvr$.LOAD, DISP=SHR
//DDCARD DD *
ADARUN DB=001, DE=3390, SVC=249, MODE=MULTI
//CMPRINT DD SYSOUT=X
//CMPRT01 DD SYSOUT=X
//CMWKFO1 DD DUMMY
//SYSOUT DD DUMMY
//CMSYNIN *
```

```
EDIT
WRITE 'TESTBAT'
END
.E
RUN
SAVE TESTBAT
FIN
//
```

This job starts Natural, creates the example program TESTBAT, and executes the program with the system command RUN.

### Test Online Natural

You can use the following verification procedure to test Natural system functions in online mode and check whether the Natural system files are available.

1. Log on to the Natural user library SYSTEM:

```
LOGON SYSTEM
```

2. Enter the following Natural system command:

```
MAINMENU
```

3. Select **Development Functions** and enter the following:

C in the **Code** field,  
P in the **Type** field, and  
TEST in the **Name** field.

4. In the editing area of the program editor, type the following:

```
WRITE 'HELLO'  
END
```

5. Save the source code and exit the program editor.

6. In the **Development Functions** menu, enter the following:

L in the **Code** field and  
TES\* in the **Name** field.

7. On the **LIST Objects in a Library** screen, enter the RU line command for the TEST program.

8. Enter the following Natural system command:

```
SYSDDM
```

9. In the SYSDDM utility menu, enter the following:

R in the **Code** field and  
EMPLOYEES in the **DDM Name** field.

10. After pressing ENTER, enter the following:

C in the **Code** field,  
the appropriate Natural system file number in the **FNR** field,  
the appropriate database ID in the **DBID** field, and  
Y in the **Replace** field.

The specified DDM has been adapted to your environment.

11. Repeat Steps 9 and 10 for the VEHICLES DDM.

12. You can check whether the DDMs EMPLOYEES and VEHICLES are now available in your environment by logging on to the Natural system library SYSEXSYN and executing the example programs (for example, AEDEX1R) with the system command RUN.

# III

## Installing ICU for Adabas & Natural on z/OS

---





# 4

## Installing ICU for Adabas & Natural on z/OS

---

■ Prerequisites .....	42
■ Installation Medium .....	42
■ Installation Procedure .....	42
■ Installation Verification .....	47
■ Using ICS31 in Natural subtask (needs APF-authorized ICS load library) .....	48

This document describes the steps for installing ICU for Adabas & Natural (ICS) on z/OS which allows Natural to convert code pages and support Unicode.

ICU for Adabas & Natural (ICS) requires the use of an ICS module and an ICU data library. In addition, you can use ICU data items to load ICU components that are not contained in the ICU data library. The ICS module does not have to be linked to the Natural nucleus if neither code page conversion nor Unicode support are required.

The use of ICU functionality increases the required Natural thread size.



**Note:** For increased flexibility, it is also possible to load the ICS module during initialization of the Natural session. A dynamically loaded ICS module overrides the statically linked ICS module. You can also load an ICU data library during initialization of the Natural session. A dynamically loaded ICU data library overrides any statically linked ICU data library.

The ICS module, the ICU data libraries and the ICU data items are explained in *Enabling Unicode and Code Page Support* in the *Unicode and Code Page Support* documentation.

**Notation** *vrs* or *vr*:

When used in this document, the notation *vrs* or *vr* represents the relevant product version (see also Version in the *Glossary*).

## Prerequisites

---

See [General Prerequisites and System Support](#) in the section *Overview of the Installation Process*.

## Installation Medium

---

The ICS module, the ICU data libraries and the ICU data items are contained on the `ICSvrs.LOAD` and `ICSvrs.SRCE` data sets supplied on the [installation medium](#) for base Natural.

## Installation Procedure

---

Be sure to read [Installation Process and Major Natural Features](#) before you start the installation procedure.

- [Step 1: Link the ICS Module](#)
- [Step 2: Link an ICU Data Library](#)
- [Step 3: Load the ICS Module at Session Start](#)
- [Step 4: Load an ICU Data Library at Session Start](#)

- [Step 5: Load ICU Data Items on Request in a Session](#)

## Step 1: Link the ICS Module

1. Add the following `INCLUDE` statement to the link instructions for the **environment-independent nucleus**:

```
INCLUDE ICSLIB(SAGICU)
```

For support of IBM architecture level 9, instead of `SAGICU`, you can use the alternative ICS module `SAGICUA9`:

- Set the **System Maintenance Aid (SMA)** parameter `NAT-ARCHLEVEL9` to `Y` (default is `N`).

Or:

- Add the following `INCLUDE` statement to the link instructions for the **environment-independent nucleus**:

```
INCLUDE ICSLIB(SAGICUA9)
```

- See also alternative ICS modules in the *Unicode and Code Page Support* documentation.



**Note:** The ICU data library `ICS58J` is contained in the ICS module `SAGICU` (or `SAGICUA9` respectively) and available by default.

2. Link the ICS module to the environment-independent nucleus as described in *Link the Nucleus* in *Installing Natural*.

## Step 2: Link an ICU Data Library

The provided data libraries are not supported with ICS 311. They will still be supported as part of the ICS Transition Version 222.

ICS 311 uses the entirety of ICU localization data as described in Step. 5.

This step is only required if you want to use another data library in addition to `ICS58J`.

1. Add one of the following `INCLUDE` statements to the link instructions for the **environment-independent nucleus** depending on the ICU data library to be used:

```
INCLUDE ICSLIB(ICSDT58E)
```

Or:

```
INCLUDE ICSLIB(ICSDT58X)
```

2. Link the ICU data library to the **environment-independent nucleus** as described in *Link the Nucleus* in *Installing Natural*.

If you link the ICSDT58X data library, link the **environment-independent nucleus** into a PDSE instead of a PDS to avoid IBM error IEW2641S.

### Step 3: Load the ICS Module at Session Start

1. Make sure that the ICS load library from the `ICSvrs.LOAD` data set is available to the execution JCL of your Natural or TP monitor interface. Depending on your environment, perform one of the following options:

- In batch mode, under TSO and in all IMS TM environments:

Add `ICSvrs.LOAD` to the STEPLIB concatenation of your execution JCL.

- Under CICS:

Add `ICSvrs.LOAD` to the DFHRPL concatenation of your CICS execution JCL.

- Under Com-plete:

Add `ICSvrs.LOAD` to the COMPLIB concatenation of your Com-plete execution JCL.

2. At the start of a Natural session, set the Natural profile parameter `RCA` as follows:

```
RCA=SAGICU
```

`RCA` is described in the *Parameter Reference* documentation.

The ICS module `SAGICU` is described in the *Unicode and Code Page Support* documentation.

Instead of the ICS module `SAGICU`, you can also load the ICS module `SAGICUA9`. In addition to `SAGICU`, this module supports IBM architecture level 9: see alternative ICS modules in the *Unicode and Code Page Support* documentation.

If you want to load `SAGICUA9`, use the following parameter setting:

```
RCA=SAGICU RCALIAS=(SAGICU,SAGICUA9)
```

The Natural profile parameter `RCALIAS` is described in the *Parameter Reference* documentation.

#### Step 4: Load an ICU Data Library at Session Start

The provided data libraries are not supported with ICS 311. They will still be supported as part of the ICS Transition Version 222.

ICS 311 uses the entirety of ICU localization data as described in Step. 5.

1. Make sure that the ICS load library from the `ICSvrs.LOAD` data set is available to the execution JCL of your Natural or TP monitor interface. Depending on your environment, perform one of the following options:

- In batch mode, under TSO and in all IMS TM environments:

Add `ICSvrs.LOAD` to the `STEPLIB` concatenation of your execution JCL.

- Under CICS:

Add `ICSvrs.LOAD` to the `DFHRPL` concatenation of your CICS execution JCL.

- Under Com-plete:

Add `ICSvrs.LOAD` to the `COMPLIB` concatenation of your Com-plete execution JCL.

2. At the start of a Natural session, set the Natural profile parameters `RCA` and `CFICU` for the ICU data library to be used:

For `ICS58E`:

```
RCA=ICS58E CFICU=(DATFILE=ICS58E)
```

For `ICS58X`:

```
RCA=ICS58X CFICU=(DATFILE=ICS58X)
```

`RCA` and `CFICU` are described in the *Parameter Reference* documentation.

## Step 5: Load ICU Data Items on Request in a Session

This step depends on the ICS version.

- [For ICS Transition Version 222](#)
- [For ICS 311](#)

### For ICS Transition Version 222

This step is optional and only required if you want to dynamically load an ICU data item on request during a Natural session instead of an entire ICU data library. For more information, see the *Unicode and Code Page Support* documentation.

1. Make sure that the ICS load library from the `ICSvrs.LOAD` data set is available to the execution JCL of your Natural or TP monitor interface. Depending on your environment, perform one of the following options:
  - In batch mode, under TSO and in all IMS TM environments:

Add `>ICSvrs.LOAD` to the STEPLIB concatenation of your execution JCL.
  - Under CICS:

Add `ICSvrs.LOAD` to the DFHRPL concatenation of your CICS execution JCL.
  - Under Com-plete:

Add `ICSvrs.LOAD` to the COMPLIB concatenation of your Com-plete execution JCL.
2. Depending on your TP environment and the setting of the Natural `CFICU` profile parameter, perform one of the following options:
  - Under CICS, with `CFICU=(DATITEM=NONE)` set:

Add one PPT entry for each ICU data item.

See also the [corresponding step](#) in *Installing Natural CICS Interface*.
  - Under Com-plete, with `CFICU=(DATITEM=NONE)` set:

Add `THREAD-ESQA-SIZE=15K` as a keyword parameter to the startup options for your Com-plete.

**For ICS 311**

1. You can specify the name of the dataset containing the ICU data items from ICSvrs.LOAD dynamically at the start of the session using the CFICU STEPLIB parameter .
  - See section *Data Scope and Data Handling* in *Unicode and Code Page Support*
  - Add the load library containing the data items to the execution JCL of your Natural or TP monitor interface as described in Step 2.
2. You can also statically add the load library containing the data items from the ICSvrs.LOAD data set to the execution JCL of your Natural or TP monitor interface.
  - In batch mode, under TSO and in all IMS TM environments:  
  
Add ICSvrs.LOAD to the STEPLIB concatenation of your execution JCL.
  - Under CICS:  
  
Add ICSvrs.LOAD to the DFHRPL concatenation of your CICS execution JCL.
  - Under Com-plete:  
  
Add ICSvrs.LOAD to the COMPLIB concatenation of your Com-plete execution JCL.

ICS uses both allocation methods to search for data items, starting (if given) from the CFICU STEPLIB dataset and the statically specified Natural Steplibs in the JCL.

## Installation Verification

---

After the last step of the installation procedure has been completed, proceed as follows:

1. Configure and activate your Unicode and code page environment by following the instructions in *Configuration and Administration of the Unicode/Code Page Environment* and *Profile Parameters and Macros* in the *Unicode and Code Page Support* documentation.

For information on the code pages and ICU data files available in your current Natural environment, you can use the SYSCP utility (described in the *Utilities* documentation).

2. After successful activation, you can execute the example programs described in the *Unicode and Code Page Support* documentation.

## Using ICS31 in Natural subtask (needs APF-authorized ICS load library)

---

Under the current implementation of NPR, the `PRD.ICSnnn.MVSLoad` must always be APF-authorized. This is independent of whether it is part of the STEPLIB concatenation or specified with the STEPLIB parameter of CFICU.

The scenarios for using ICS31 in a Natural subtask are:

- When running multiple Natural sessions / subtasks from an Entire System Server (NPR) node.
- When NOP, NOM, EOR are automated to be run by an ESS/NPR node.
- When running an NDV server.



# IV

## Installation for REQUEST DOCUMENT, PARSE JSON, and PARSE XML Statements on z/OS

---

---

# 5      Installation for REQUEST DOCUMENT, PARSE JSON, and PARSE XML Statements on z/OS

---

■ Prerequisites .....	52
■ Installation Procedure .....	53
■ Installation Verification .....	55

This document describes the installation steps for enabling the use of the Natural statements REQUEST DOCUMENT, PARSE JSON, and PARSE XML on z/OS.

### Related Topics:

For information on the functions provided by REQUEST DOCUMENT, PARSE JSON, and PARSE XML, see the following documents:

- *Statements for Internet Access and Parsing in the Programming Guide*
- PARSE JSON in the *Statements* documentation
- REQUEST DOCUMENT in the *Statements* documentation
- PARSE XML in the *Statements* documentation

## Prerequisites

---

The following requirements must be met to execute the REQUEST DOCUMENT and PARSE XML statements:

- An installed ICU library to convert data from one encoding to another (at least internally). For details, see the relevant section in the *Unicode and Code Page Support* documentation.
- A TCP/IP stack must be available and enabled for the execution environment.
- A DNS (Domain Name System) server or DNS services must be available in the execution environment to resolve internet addresses (`gethostbyname` function).

For Internet Protocol Version 6 (IPv6) support, the following additional prerequisites apply:

- An activated IPv6 stack must be available on the local host.
- The local network must support IPv6.
- An accessible and IPv6-capable DNS server must be available.
- For IPv6 internet communication, an IPv6 connection from the service provider must be available.
- If both IPv4 and IPv6 are used, a dual stack must be supported.
- IPv6 support must be configured with the appropriate keyword subparameters of the Natural profile parameter XML described in the *Parameter Reference* documentation.

To execute the PARSE JSON statement, you must install the ICU library to convert data from one encoding to another (at least internally). For details, see the relevant section in the *Unicode and Code Page Support* documentation.

See also [General Prerequisites and System Support](#) in the section *Overview of the Installation Process*.

## Installation Procedure

---

Be sure to read [Installation Process and Major Natural Features](#) before you start the installation procedure.

The installation procedure comprises the steps described below.

- [Step 1: Link the Module NATXML to the Nucleus](#)
- [Step 2: Enable the Environment-Dependent Nucleus for LE Execution](#)
- [Step 3: Link the Required Modules to the Nucleus](#)

### Step 1: Link the Module NATXML to the Nucleus

The module NATXML is required to execute the statements REQUEST DOCUMENT, PARSE JSON, and PARSE XML.

1. Set the [System Maintenance Aid \(SMA\)](#) parameter NATXML to Y (default is N).
2. The NATXML module is then linked to the [environment-independent nucleus](#) by using the following INCLUDE statement:

```
INCLUDE NATLIB(NATXML)
```

### Step 2: Enable the Environment-Dependent Nucleus for LE Execution

The REQUEST DOCUMENT, PARSE JSON, and PARSE XML statements require the IBM Language Environment (LE) for execution. If you want Natural to run in the IBM Language Environment (LE), perform the following steps:

1. Set the [System Maintenance Aid \(SMA\)](#) parameter NAT-LE to Y (Yes). The default setting is N (No).
2. Additionally, if you want to modify the LE options in the NATLEOPT source module or if you use non-Natural programs running in 24-bit mode, set the appropriate SMA parameter as described in [Build the Natural-Specific IBM Language Environment Options in Installing Natural](#).
3. Link the environment-dependent nucleus to support LE.

This applies to all batch and TP monitor system environments except Complete and CICS.

### Step 3: Link the Required Modules to the Nucleus

Link the modules indicated in this section to the nucleus depending on the environment to be used.

In the following instructions, *hilev* denotes a valid high-level qualifier.

- Batch and TSO
- CICS
- Com-plete
- IMS TM

#### Batch and TSO

- Add the LE library (usually *hilev*.SCEELKED) to the SYSLIB definition of the link step to resolve the references to LE functions.
- Link the LE and TCP/IP access modules to the **environment-dependent nucleus** by using the appropriate INCLUDE statements:

```
INCLUDE NATLIB(NAT2LE)  
INCLUDE NATOLIB(NAT2TCP)
```

- Do *not* specify the NCAL parameter for the link step.

#### CICS

- Add the LE library (usually *hilev*.SCEELKED) to the SYSLIB definition of the link step to resolve the references to LE functions.
- Add the CICS socket library (usually *hilev*.SEZARNT1, *hilev*.SEZATCP or *hilev*.SEZACMTX) to the SYSLIB definition of the link step to resolve the reference to the CICS socket module.
- Link the CICS socket module to the **environment-dependent nucleus** by using the appropriate INCLUDE statement:

```
INCLUDE NATLIB(NAT2LE)  
INCLUDE NCIOLIB(NCI2TCP)  
INCLUDE CICS SOCK(EZACIC17)
```

- Do *not* specify the NCAL parameter for the link step.
- Configure the CICS TCP/IP environment as described in the IP CICS Socket Guide by IBM.

## Com-plete

- Link the LE access module to the **environment-dependent nucleus** by using the appropriate `INCLUDE` statement:

```
INCLUDE NATLIB(NAT2LE)
```

- Copy the `NCFTCPvr` module from the Natural Com-plete Interface load library to the Com-plete load library.
- For support of the IBM TCP/IP stack, define the CDI (Communication Driver Interface) as described in *Standard CDI Definitions* in the *Com-plete* documentation.
- Add the `POSIX SERVER` statement to the Com-plete parameter module `SYSPARM`.

## IMS™

- Add the LE library (usually `hilev.SCEELKED`) to the `SYSLIB` definition of the link job to resolve the references to LE functions.
- Link the LE and TCP/IP access modules to the **environment-dependent nucleus** by using the appropriate `INCLUDE` statements:

```
INCLUDE NATLIB(NAT2LE)
INCLUDE NATOLIB(NAT2TCP)
```

- Do *not* specify the `NCAL` parameter for the link step.

## Installation Verification

After the last step of the installation procedure has been completed, proceed as follows:

1. Activate the statements in the runtime environment; see *Activation/Deactivation* in the section *Statements for Internet Access and Parsing* in the *Programming Guide*.

For information on the profile settings that enable the support of the `REQUEST DOCUMENT` and/or `PARSE XML` statement, see the following documents:

- *Profile Settings* in the section *Statements for Internet Access and Parsing* in the *Programming Guide*
  - Profile parameter `XML` in the *Parameter Reference* documentation
2. By default, the `PARSE JSON` feature is activated and can be utilized when you have all prerequisites met and properly installed.
  3. Try the example programs contained in the Natural system library `SYSEXV`.





## **V** Installing Entire System Server Interface on z/OS

---



# 6

## Installing Entire System Server Interface on z/OS

---

■ Prerequisites .....	60
■ Default or Customized Installation .....	60
■ Assemble the Parameter Module for the Entire System Server Interface Component .....	63
■ Link the Entire System Server Interface to the Nucleus .....	63
■ Installing and Activating the Write-to-Spool Feature .....	64
■ Install the Entire System Server in Single-User Mode .....	66

The Entire System Server Interface is required if the Entire System Server is to be used.

This document describes the steps for installing the Entire System Server Interface on z/OS. You can choose between default installation (recommended) and customized installation.

### Related Topic:

For information on installing and using the Entire System Server, refer to the relevant product documentation.

### Notation *vrs* or *vr*:

When used in this document, the notation *vrs* or *vr* represents the relevant product version (see also Version in the *Glossary*).

## Prerequisites

---

Before you can use the Entire System Server Interface, you must install a supported version of Entire System Server specified under *Product Versions Supported by Natural* in the current Natural for z/OS *Release Notes*.

See also [General Prerequisites and System Support](#) in the section *Overview of the Installation Process*.

## Default or Customized Installation

---

If you want to use the default value settings in the modules `ESYNODTB` and `NATPNIP` (used by the Entire System Server and Natural ISPF), proceed with [Link the Entire System Server Interface to the Nucleus](#).

If you do *not* want to use the default value settings, edit the modules `NATPNIP` and `ESYNODTB` described in this section.

- `NATPNIP`

## ■ ESYNODTB

### NATPNIP

The NATPNIP module contains the following parameters and default values:

```
NAMVIEWP BUFLN=12288,NUMREQ=5,MAXCBL=3000,MAXEDL=6000,EXTUSER=INIT-USER
```

The parameters are explained below:

BUFLN	Length of all Adabas buffers in bytes
NUMREQ	Number of possible nested FIND loops in Natural calling the Entire System Server
MAXCBL	Complex FIND buffer length
MAXEDL	<p>Editor session buffer length</p> <p>MAXEDL is used by the NSPF editor and incore database.</p> <p>The default value is 6000, which should be sufficient for an NSPF editor session and typical incore database applications. However, for large layouts within an incore database file that value might not be large enough and the following message is issued: NAT3077: Not enough space for extent. DB/FNR/Subcode :1:/:2:/:3:.. (see the <i>Messages and Codes</i> documentation).</p> <p>In this case, the value of MAXEDL has to be increased.</p>
EXTUSER	<p>External user ID passed to the Entire System Server for security checks</p> <p>See also EXTUSER in the following section.</p>

### EXTUSER

The parameter EXTUSER describes how to inherit security definitions from an external security system such as RACF, ACF2 and TOP-SECRET.

The appropriate parameter setting depends on whether a multi-user address space or a single-user address space is used in your environment:

- A multi-user address space provides the option to maintain different user security definitions, for example, one for a CICS and one for a Complete user).
- A single-user address space supports a subsystem, for example, a Natural subtask for Entire Output Management or Entire Operations Management, or a Natural RPC, Natural Web/IO Interface or batch server.

Recommended values for EXTUSER are:

EXTUSER=INIT-USER	<p>Recommended for a multi-user address space.</p> <p>The contents of the Natural system variable *INIT-USER must be identical to the user definition in the external security system (for example, RACF).</p> <p>The Entire System Server transfers the value of *INIT-USER to the external security system, and all calls to security restricted resources are handled under this user ID.</p> <p>In this case, the security definition from a CICS or Complete user (for example) is inherited by Entire System Server, and a new logon is not required. If the value of *INIT-USER is not found in RACF (for example), an error occurs indicating that a logon is required.</p> <p>(*INIT-USER is described in the <i>System Variables</i> documentation.)</p>
EXTUSER=USER	<p>Recommended for a multi-user address space in a Natural Security environment.</p> <p>Processing is similar to EXTUSER=INIT-USER except that the Natural system variable *USER (described in the <i>System Variables</i> documentation) is used.</p> <p>(*USER is described in the <i>System Variables</i> documentation.)</p>
EXTUSER=ADDRESS-SPACE	<p>Recommended for a TSO, batch or server environment.</p> <p>The security description of this address space is inherited for security evaluation.</p>

## ESYNODTB

The ESYNODTB module contains the following parameters and default values:

```
NAMXNOD ID=148,NAME=PRODUCTION-1
NAMXNOD ID=149,NAME=PRODUCTION-2
NAMXNOD ID=1490,NAME=DBID-ABOVE-255, LAST=Y
END
```

The parameters and default values are explained below:

ID	Entire System Server node number (also known as DBID)
NAME	Entire System Server node name
LAST	Indicator for last entry in table

## Optional Node Name for Entire System Server Calls

Calls to the Entire System Server from Natural are usually handled with the `NODE` parameter which specifies the node number to be used for the call, for example:

```
FIND ACTIVE-JOBS WITH JOB-NAME = 'ADA*' AND NODE = 148
```

If the node number is defined in the `ESYNODTB` module, alternatively, you can specify the logical name of the required Entire System Server with the `NODE-NAME` parameter, for example:

```
FIND ACTIVE-JOBS WITH JOB-NAME = 'ADA*' AND NODE-NAME = 'PRODUCTION-2'
```

## Assemble the Parameter Module for the Entire System Server Interface Component

### Natural ISPF

If Natural ISPF is used as the INCORE database:

- (Job I055, Step 1106)

Link the parameter module `NATPNIP`. In this case, the module `ESYNODTB` is not required.

### Entire System Server

If the Entire System Server is used:

- (Job I055, Steps 1106, 1107)

Assemble and link the modules `NATPNIP` (Step 1106), and, optionally `ESYNODTB` (Step 1107).

## Link the Entire System Server Interface to the Nucleus

(Job I060, Step 3720)

- Link the following Entire System Server Interface modules to either the **environment-independent nucleus** or the **environment-dependent nucleus** by using the corresponding `INCLUDE` statements:

INCLUDE NATLIB(NATPNIP)	Entire System Server Interface parameters
INCLUDE NATLIB(ESXNUC)	Entire System Server Interface module
INCLUDE NATLIB(ESYNODTB)	Optional, node table

## Installing and Activating the Write-to-Spool Feature

If you want to use the Write-to-Spool feature, either link the access method to your nucleus or load the method dynamically. See also the Natural parameters `RCA` and `RCALIAS`.

You can define and assemble the defaults for your nucleus by using the source member `NATPWSDF` before linking the defaults to the nucleus. You can find the source member `NATPWSDF` in the source library of Natural.

The default settings of source member `NATPWSDF` are as follows:

```
NAMPWSPL NODE=148,
PROGRAM=,
CLASS=A,
HOLD=YES,
CNTL=A,
FORM=,
RMT=,
FORMDEF=,
PAGEDEF=
```

The table below shows the modifiable parameters of source member `NATPWSDF` and a detailed description of these parameters:

Parameter	Description
Node	<p>NPR target node.</p> <p>The node number can consist of up to 5 digits.</p> <p>It addresses the destination started task of the Entire System Server and where the output is written.</p>
Program	<p>JES Writer which can contain up to 8 characters.</p> <p>JES provides control to the Writer program. If JES does not find it, it is ignored.</p> <p>Possible value: <code>*OUTPUT</code> means that the input from the Natural statement <code>DEFINE PRINTER</code> is used to be interpreted as JES Writer.</p>



Parameter	Description			
Class	<p>SYSOUT class within JES where the output has to be written. It can contain only one character or digit.</p> <p>It is a descriptor for further software (for example, Entire Output Management) to detect the output stream for processing.</p>			
Hold = yes/no	Specifies whether the output stream is to be held within the JES spool in case the task previously started by the Entire System Server terminates.			
CNTL	Represents the control character for the SYSOUT data set.			
	CNTL contains one character:			
	<table> <tr> <td>A</td><td>ASA control character</td></tr> <tr> <td>M</td><td>Machine control character</td></tr> </table>	A	ASA control character	M
A	ASA control character			
M	Machine control character			
FormRMT	<p>Describes the form control buffer for JES. This value is transferred to JES which handles the processing.</p> <p>RMT represents the JES remote user ID if SYSOUT has to be routed to a different JES system.</p> <p>You can find the name of the JES system in the destination field within the DEFINE PRINTER statement (for example, DEFINE PRINTER OUTPUT='DAEM').</p>			
Formdef Pagedef	Can contain up to 6 characters.			

After editing the NATPWSDF source member with customized values, you can assemble and link it. If you want to use the default settings, you can omit this step.

If you want to use the Write-to-Spool feature with statically linked access method at your site, relink the Natural module as follows:

```
INCLUDE NATLIB(NATPWSPL)    The Write-to-Spool access method for Natural
INCLUDE NATLIB(NATPWSDF)    The Write-to-Spool defaults
                             (your adapted parameter module)
```

If you want to use dynamic load, you can either use the delivered module NATPWSAM with default parameters or you can link your adapted parameter module:

```
INCLUDE NATLIB(NATPWSPL)
INCLUDE USRLIB(NATPWSPA)    Your adapted module
NAME NATWSPvr(R)            Your adapted Write-to-Spool module.
                             This name must be used in RCALIAS=(NATAM11,NATWSPvr).
```

For further information, see System Spool Access in the *Operations* documentation.

## Install the Entire System Server in Single-User Mode

---

(Optional installation for only batch mode or TSO.)

This section describes the advantages of Entire System Server in single-user mode and the steps required for installation.

- [Advantages of Single-User Mode](#)
- [Installation for Batch Mode](#)
- [Installation for TSO](#)

### Advantages of Single-User Mode

Running the Entire System Server in single-user mode is advantageous, for example, in the following cases:

- Executing long running batch jobs comprising a large number of calls to the Entire System Server.
- Performing test scenarios using a Natural session under TSO performing many calls to the Entire System Server, without disturbing the production environment.
- Exploring new Entire System Server functionality or versions.

From a Natural point of view, the Entire System Server single-user mode is accessible as Entire System Server node 148, irrespective of whether such a node does already exist on your machine or network.

The following is an example of a Natural program that is running in a single-user environment:

```
FIND ACTIVE-JOBS WITH NODE = 148 AND JOB-NAME = 'XCOM*'
```

This statement calls a single-user Entire System Server that runs within the same address-space. Calling a different Entire System Server node that runs elsewhere in the network is possible by using a different node number, as shown in the following example:

```
FIND ACTIVE-JOBS WITH NODE = 53 AND JOB-NAME = 'NUC*'
```

This statement calls a multi-user Entire System Server with node number 53 out of the same Natural program which called the single-user Entire System Server session.

## Installation for Batch Mode

1. Create a new PDS load library, which must be APF-authorized.
2. Copy all members of the Entire System Server load library into the new load library.
3. Link the module NATPSNGL, which handles Entire System Server single-user features, to the **environment-dependent nucleus** for batch Natural.

Alternatively, you can use the RCA parameter to dynamically load this module by setting RCA=NATPSNGL.

In both cases, the environment-dependent nucleus must be authorized by parameter AC=1 and linked into the new load library.

4. Add the mandatory cards PARMS and SYSPRINT to your JCL to handle the Entire System Server-relevant steps. In addition, you can add the optional cards ESYTRACE and CLOG.

//ESYTRACE	DD	SYSOUT=*	Internal trace
//SYSPRINT	DD	SYSOUT=*	Modules/Zap directory of Entire System Server
//CLOG	DD	DISP=SHR,DSN=xxx	Command log data set
//PARMS	DD	DISP=SHR,DSN=xxx	Entire System Server parameter

5. Add an Adabas load library to your JCL, which also has to be APF-authorized.
6. Edit your Entire System Server parameter member. Here, the parameter NODE will be ignored, since Natural routes any calls to node number 148 through to the single-user Entire System Server node.

## Installation for TSO

1. Add the name of the nucleus as AUTHPGM in the TSO definition member named IKJTS000. Usually, this member is in data set SYS1.PARMLIB.
2. Proceed analogously as described in the batch mode installation above.



# VI

## Installing Software AG Editor on z/OS

---

---

# 7

## Installing Software AG Editor on z/OS

---

■ Prerequisites .....	72
■ Support of a Parallel Sysplex Environment .....	72
■ Installation Procedure .....	72
■ Installation Verification .....	77

The Software AG Editor is an optional Natural component that is required by several Natural utilities (for example, SYSRPC and SYSBPM), Natural add-on products (for example, Natural ISPF) and other products (for example, Predict).

This document describes the steps for installing the Software AG Editor on z/OS.

### Related Topics:

- For operational information, see *Operating the Software AG Editor* in the *Operations* documentation.
- For information on the features and functions of the *Software AG Editor*, see the relevant section in the *Editors* documentation.

### Notation *vrs* or *vr*:

When used in this document, the notation *vrs* or *vr* represents the relevant product version (see also Version in the *Glossary*).

## Prerequisites

---

See [General Prerequisites and System Support](#) in the section *Overview of the Installation Process*.

## Support of a Parallel Sysplex Environment

---

The Software AG Editor must run without a buffer pool to support a Parallel Sysplex environment under CICS, that is, to be able to switch the z/OS host during a Natural session.

For this purpose, the Natural profile parameter `EDPSIZE` (described in the *Parameter Reference* documentation) is supplied where you can specify the size of an auxiliary editor buffer pool. All editor data is kept in the user storage thread. The total editor work space per user is limited by the `EDPSIZE` parameter. No editor work file is required. The recovery feature mechanism of the Software AG Editor is not supported.

## Installation Procedure

---

Be sure to read [Installation Process and Major Natural Features](#) before you start the installation procedure.

The [System Maintenance Aid \(SMA\)](#) parameter `SAG-EDITOR` is set to Y (Yes) by default to allow installation of the Software AG Editor.

- [Step 1: Adapt the Editor Buffer Pool Parameter Macro NTEDBP](#)



- [Step 2: Allocate the Editor Work File](#)
- [Step 3: Format the Editor Work File](#)
- [Step 4: Modify the Startup JCL and Subsystem Definitions](#)
- [Step 5: Build the Natural Parameter Module](#)
- [Step 6: Define the Global Editor Buffer Pool](#)
- [Step 7: Link the Software AG Editor to the Nucleus](#)

### Step 1: Adapt the Editor Buffer Pool Parameter Macro NTEDBP

1. Modify the editor buffer pool settings supplied with the NTEDBP macro in the Natural parameter module to meet your requirements. For a description of this macro, see the corresponding dynamic profile parameter EDBP.
2. Assemble the Natural parameter module and link it to the Software AG Editor work file formatting utility NATEDFM contained in the Natural load library. The Software AG Editor work file formatting utility is described in *Editor Work File* in the *Operations* documentation.

The editor buffer pool parameters contained in the Natural parameter module are stored in the editor buffer pool work file control record during formatting (see [Step 3: Format the Editor Work File](#)).

#### For the Initial Installation:

You can leave the defaults. In this case, it is not necessary to assemble and link the Natural parameter module.

### Step 2: Allocate the Editor Work File

(Job I008, Steps 1900, 1901, 1903, 1905)

Under Com-plete, this step is only required if you want to use a global editor buffer pool.

A VSAM RRDS is used as the editor work file. To best exploit the VSAM data set space, the record length should be defined 8 bytes less than the control interval length; see also *Editor Work File* in the *Operations* documentation.

- Depending on your TP monitor environment, execute the following steps to allocate the data set:

```
Step 1900 ALLOCATE EDITOR WORK FILE BATCH
      1901 ALLOCATE EDITOR WORK FILE CICS
      1903 ALLOCATE EDITOR WORK FILE TSO
      1905 ALLOCATE EDITOR WORK FILE GLOBAL
```

### Step 3: Format the Editor Work File

(Job I081, Steps 1900, 1901, 1903, 1905)

Under Com-plete, this step is only required if you want to use a global editor buffer pool.

1. Use the Software AG Editor work file formatting utility `NATEDFM` to format and load the control record in the editor work file.
2. Depending on your TP monitor environment, execute the following steps to format the data set:

```
Step 1900 FORMAT EDITOR WORK FILE BATCH
      1901 FORMAT EDITOR WORK FILE CICS
      1903 FORMAT EDITOR WORK FILE TSO
      1905 FORMAT EDITOR WORK FILE GLOBAL
```

You may receive error message `IEC070I 203-204`, which can be ignored.

### Step 4: Modify the Startup JCL and Subsystem Definitions

You can specify the data set for the work file by using the keyword subparameter `DSNAME` or `DDNAME` of the parameter macro `NTEDBP` (see *EDBP - Software AG Editor Buffer Pool Definitions* in the *Parameter Reference* documentation).

The data set name specified with `DDNAME` must correspond to the data set definition in your JCL.

#### ■ Under TSO and in Batch Mode:

Add a DD statement for the work file:

```
//CMEDIT DD DSN=data-set-name,DISP=SHR
```

where *data-set-name* is the name of the data set to be used for the work file.

You can skip this step if you have specified the correct data set name in the editor buffer pool's parameter macro in the Natural parameter module; Natural then allocates the file dynamically.

#### ■ Under Com-plete:

- If you want to use a global editor buffer pool, add a DD statement for the editor work file:

```
//dd-name DD DSN=data-set-name,DISP=SHR
```

where:

*dd-name* is the name of the work file to be used by the global editor buffer pool,

*data-set-name* is the name of the data set to be used for the work file.

In addition, the DD name has to be defined to Com-plete by using the UUTIL utility function FM (described in the relevant section of the *Com-plete* documentation).

- If you want to use a local editor buffer pool, define an SD file as the editor work file. The name of the SD file is indicated in the keyword subparameter DDNAME of the NTEDBP macro. Therefore, the keyword subparameter DSNNAME has no significance.

The number of work file records is set with the keyword subparameter RECNUM and the work file record length is set with the keyword subparameter LRECL of the NTEDBP macro.

For a local editor buffer pool, add the definitions of the editor buffer pool to the SERVER parameter of your startup parameters as indicated in [Define the Natural Com-plete/SMARTS Interface Server](#) in the section *Installing Natural Com-plete/SMARTS Interface*.

For explanations of the keyword subparameters and macros mentioned above, see *EDBP - Software AG Editor Buffer Pool Definitions* in the *Parameter Reference* documentation.

#### ■ Under CICS:

Add an entry in the CICS File Control Table (Job I005).

### Step 5: Build the Natural Parameter Module

(Job I080)

1. Add the following parameter to your Natural parameter module to specify the size of the editor area:

```
SSIZE=nn
```

where *nn* must be set to at least 54 (the default is 64).

2. The Software AG Editor requires either a local or a global editor buffer pool (see also *Natural Buffer Pools* in the *Operations* documentation).

Under IMS TM, the use of a global editor buffer pool is mandatory.

- If you want to use a local editor buffer pool, specify the NTBPI macro as follows:

```
NTBPI TYPE=EDIT
```

The size of the region must be large enough to allocate the local buffer pool.

For more information on NTBPI, see *NTBPI Macro Syntax* in the *Parameter Reference* documentation.

- If you want to use a global editor buffer pool, proceed as follows:

Specify the NTBPI macro as follows:

```
NTBPI TYPE=EDIT,NAME=gbp-name
```

where *gbp-name* is the name of the global editor buffer pool to be used.

Supply the following parameter with the NTPRM macro (described in the *Operations* documentation):

```
SUBSID=subsystem-name
```

where *subsystem-name* is the name of the Natural subsystem specified when creating the global buffer pool.

For detailed information on SUBSID, see *SUBSID - Subsystem ID* in the *Parameter Reference* documentation.

### 3. Assemble and link the Natural parameter module.

## Step 6: Define the Global Editor Buffer Pool

The global editor buffer pool can be shared by several regions. It is defined and started using the same procedure as for Natural global buffer pools; see *Natural Global Buffer Pool under z/OS* in the *Operations* documentation. The parameter setting `TYPE=EDIT` identifies the buffer pool as an editor buffer pool.

All users of the same global editor buffer pool must share the same editor work file; otherwise, an error occurs.

## Step 7: Link the Software AG Editor to the Nucleus

(Job I080)

- Link the following Software AG Editor module to either the **environment-independent nucleus** or the **environment-dependent nucleus** by using the corresponding `INCLUDE` statement:

```
INCLUDE NATLIB(NATEDT)
```

- Instead of linking the Software AG Editor module to the nucleus, you can dynamically load it during initialization of a Natural session. In this case, the `NATEDT` editor module must be linked as `EDITOR` load module and the Natural session must be started with the profile parameter setting `RCA=EDITOR` (see also *RCA - Resolve Addresses of Statically Linked Modules* described in the *Parameter Reference* documentation).

## Installation Verification

You can verify the successful installation of the Software AG Editor by performing the following:

- Invoke Natural and enter the following system command:

```
SYSEDT
```

The SYSEDT Utility Main Menu appears, which can be used to display all buffer pool parameters and usage statistics; see *SYSEDT Utility - Editor Buffer Pool Administration* in the *Utilities* documentation.

You can only test the full operation of the Software AG Editor if another product (for example, Natural ISPF or Predict) that uses Software AG Editor functionality is installed.



# VII

## Installing Natural CICS Interface on z/OS

---





# 8

## Installing Natural CICS Interface on z/OS

---

■ Prerequisites .....	82
■ Installation Medium .....	82
■ Prefix Used for Natural CICS Interface Components .....	83
■ Installation Procedure .....	83
■ CICS Startup Parameters .....	89
■ CICS Resource Definitions .....	94
■ Installation Verification .....	106

This document describes the steps for installing Natural CICS Interface (product code NCI) on z/OS.

### Related Topics:

For information on how to operate Natural in a CICS environment, see *Using Natural with TP Monitors* and *Natural under CICS* in the *TP Monitor Interfaces* documentation and the following topics:

- *NCISCPCB Generation Parameters*
- *CICSP - Environment Parameters for Natural CICS Interface* (NTCICSP macro) in the *Parameter Reference* documentation
- *Customization of VSAM RRDS Roll Files*
- *NCISCPRI Warnings and Error Messages*

### Notation *vrs* or *vr*:

When used in this document, the notation *vrs* or *vr* represents the relevant product version (see also Version in the *Glossary*).

## Prerequisites

---

A supported version of the following product must be installed before you can install the Natural CICS Interface:

- Adabas CICS Interface (product code ACI), version as specified under *Product Versions Supported by Natural* in the current Natural for z/OS *Release Notes*.

See also [General Prerequisites and System Support](#) in the section *Overview of the Installation Process*.

## Installation Medium

---

The **installation medium** contains the following data sets required for product installation:

Data Set Name	Contents
NCI <i>vrs</i> .LOAD	Load modules
NCI <i>vrs</i> .SRCE	Source modules and macros
NCI <i>vrs</i> .OBJ	Object modules
NCI <i>vrs</i> .JOBS	Sample installation jobs

Data Set Name	Contents
NCIvrS.LICS	Product license file for Natural for CICS for zIIP
	For information on the license file and product licensing, see <i>Mainframe Product Licensing</i> .

Copy the data sets into your environment as described in [Copying Data Sets to a z/OS Disk](#) in the section *Installing Natural*.

## Sample Jobs

Sample installation jobs are contained in the NATvrS.JOBS data set and are prefixed with the product code. The data set is provided on the installation medium supplied for base Natural.

## Prefix Used for Natural CICS Interface Components

When used in this document, *prefix* denotes a common Natural CICS Interface prefix of 1 to 5 characters, for example, NCIvr. This prefix is determined by the value of the parameter PREFIX in the NTCICSP macro of the Natural parameter module, for example, in [Step 5](#) of the *Installation Procedure*. NTCICSP and PREFIX are described in the *Parameter Reference* documentation.

*prefix* is followed by specific characters to make up the names of the following objects:

<i>prefix</i> CB	Natural CICS Interface system directory, for example, NCIvrCB
<i>prefix</i> R1 to <i>prefix</i> R9	Natural CICS Interface VSAM RRDS roll files (optional)
<i>prefix</i> XFA	Natural CICS Interface 3270 Bridge XFAINTU exit

## Installation Procedure

Before you start the installation procedure for the Natural CICS Interface, be sure to read the following:

- *System Control under CICS* in the *TP Monitor Interfaces* documentation
- [Installation Process and Major Natural Features](#)

The installation procedure consists of the steps below.

- [Step 1: Customize CICS](#)
- [Step 2: Prepare, Convert, Assemble and Link the License File for Natural for CICS for zIIP](#)
- [Step 3: Allocate the VSAM RRDS Roll Files for the Natural CICS Interface](#)
- [Step 4: Build the Natural CICS Interface System Directory Module](#)
- [Step 5: Build the Natural Parameter Module](#)

- [Step 6: Link the Environment-Dependent Nucleus](#)
- [Step 7: Link the Natural CICS Interface System Directory](#)
- [Step 8: Link the Natural CICS Interface External CALLNAT Interface Module](#)
- [Step 9: Link the Natural CICS Interface Node Error Program](#)
- [Step 10: Link the Natural CICS Interface XFAINTU Exit](#)
- [Step 11: Link the Natural CICS Interface zIIP Shutdown Statistics Program](#)
- [Step 12: Link the Natural RPC Server Front-End](#)
- [Step 13: Initialize the VSAM Roll Files](#)

## Step 1: Customize CICS

(Job I005, Steps 2211 - 2216, 2230 - 2235, 2240 - 2245)

1. Steps 2211 - 2216 and 2230 - 2235:

Create CICS RDO entries as described in [CICS Resource Definitions](#) and apply the batch resource definitions with the DFHCSDUP utility program.

2. Steps 2240 - 2245 (optional):

These steps are only required if you want to dynamically load an ICU data item without using the SVC instruction on request during a Natural session instead of an entire ICU data library:

Set `CFICU=(DATITEM=NONE)` and add one PPT entry for each ICU data item.

See also the corresponding step in *Installing ICU for Adabas & Natural*.

ICU data items and ICU data libraries are described in the *Unicode and Code Page Support* documentation.

## Step 2: Prepare, Convert, Assemble and Link the License File for Natural for CICS for zIIP

(Job I007, Steps 2201, 2202, 2204)

This step is optional and only required if you want to install Natural for CICS for zIIP.

You must install a valid Natural license file. An additional license file is required if you want to install [Natural for CICS for zIIP](#) to enable support of the IBM z/IIP (IBM System z Integrated Information Processor).

For detailed information on the license file and product licensing, see *Mainframe Product Licensing*.

1. Copy the license file from the supplied installation medium to disk or transfer it from the PC as described in *Transferring a License File from PC to a z/OS Host Using FTP* in *Mainframe Product Licensing*.
2. Check, convert, assemble and link the license file supplied for Natural for CICS for zIIP:

Step 2201	Check license file <code>NCIvrs.LICS</code> . This job runs the CHECK function of the LICUTIL license utility (see below).
Step 2202	Convert license file into an assembler source. This job runs the MAKE function of the LICUTIL license utility (see below).
Step 2204	Assemble and link the assembler source to generate load module <code>NCILIC</code> . This module is then linked to the nucleus in <a href="#">Job I080</a> .

The functions and option settings provided by LICUTIL are described in *Using the License Utility: LICUTIL in Mainframe Product Licensing*.

### Step 3: Allocate the VSAM RRDS Roll Files for the Natural CICS Interface

(Job I008, Step 2200)

This step must be performed only if VSAM roll files are used as CICS roll facility.

- Allocate the VSAM RRDS roll files for the Natural CICS Interface.

The Natural CICS Interface uses VSAM RRDS roll files for optimum performance, which means without CI/CA splits.

### Step 4: Build the Natural CICS Interface System Directory Module

(Job I070, Steps 2245, 2250)

- Edit, assemble and link the `NCISPCB` module.

The Natural CICS Interface system directory is generated by assembling and linking the source module `NCISPCB`.

A sample job is contained in the `NATvrs.JOBS` data set and a comprehensive sample source in the `NCIvrs.SRCE` data set.

For descriptions of the individual macros and parameters contained in `NCISPCB`, see *NCISPCB Generation Parameters* in the *TP Monitor Interfaces* documentation.

### Step 5: Build the Natural Parameter Module

(Job I080, Steps 2210, 2220)

Build the Natural parameter module for the Natural CICS Interface:

1. The `NTCICSP` macro in the Natural parameter module contains parameters specific to the Natural CICS Interface. You can generally use the default values for all parameters.

You can generally use the default values for all parameters. Modify only the values of those parameters whose default values do not suit your requirements. The only mandatory parameter without a default value is the common Natural CICS Interface prefix.

To simplify the Natural parameter module installation process, the source module `NTCICSP` contains the `NTCICSP` macro request with parameter `PREFIX=&SYSPARM`. Thus, when generating a parameter module for the Natural CICS Interface, assemble the Natural parameter module with the assembler option `SYSPARM=prefix` rather than editing the source module.

The individual `NTCICSP` macro parameters are described in *CICSP - Environment Parameters for Natural CICS Interface* in the *Parameter Reference* documentation.

2. Modify the settings of the supplied Natural profile parameters as required and in accordance with the settings you specified when building the Natural parameter module for batch mode during the *Installation Procedure* for base Natural.

Make sure that the profile parameters `FNAT` and `FUSER` are set to the same values you specified when loading the system file. The parameters and corresponding macros (if applicable) are described in the *Parameter Reference* documentation.

3. Assemble and link the Natural parameter module.



**Note:** The parameters specified with the `NTCICSP` macro are copied into the Natural CICS Interface system directory module `NCISCPB` (linked as described in [Step 7](#)) when this module is initialized by the first Natural session using it. To ascertain that parameter changes become effective immediately:

- build the Natural parameter module.
- link the environment-dependent nucleus as described in [Step 6](#).
- issue `CECI RELEASE PROGRAM(...)` for the Natural CICS Interface system directory module.
- issue `CEMT SET PROGRAM(...) NEWCOPY` for both the environment-dependent nucleus and the Natural CICS Interface system directory module.

## Step 6: Link the Environment-Dependent Nucleus

(Job I080, Step 2230)

- Link the [environment-dependent nucleus](#) for the Natural CICS Interface with the `NCINUC` module and the Natural parameter module built in [Step 5](#).

Include the CICS stub module `DFHELII` (do not use `DFHEAI`).

When linking the environment-dependent nucleus or its subcomponents, you may receive `IEW2646I` or `IEW2660W` messages, which can be ignored.

See also *Natural Nucleus under CICS* in the *TP Monitor Interfaces* documentation.

## Step 7: Link the Natural CICS Interface System Directory

(Job I080, Step 2250)

- Link the Natural CICS Interface system directory into your CICS user library under the module name `prefixCB` (see [Prefix Used for Natural CICS Interface Components](#)).

The Natural CICS Interface system directory must be linked with the `NORENT` option.

## Step 8: Link the Natural CICS Interface External CALLNAT Interface Module

(Job I080, Steps 2270, 2271)

This step must be performed only if you want to use the external `CALLNAT` interface module of the Natural CICS Interface.

For more information, see *Natural 3GL CALLNAT Interface - Purpose, Prerequisites, Restrictions* in the *Operations* documentation.

- Link the external `CALLNAT` interface module `NCIXCALL`.

See also *Natural Nucleus under CICS* in the *TP Monitor Interfaces* documentation.

Step 2270 is needed if the `NCIXCALL` module has been installed in the same CICS region with a previous Natural version. The previous Natural version `NCIXCALL` module must then be assigned a new name, for example `NCIXCIOV`. Thus, you can preserve the name of the `NCIXCALL` module used in the previous version and need not link it to all your 3GL programs using it.

Step 2271 links the module `NCIXCALL` for the current Natural version.

## Step 9: Link the Natural CICS Interface Node Error Program

(Job I080, Step 2275)

This step must be performed only if you want to use the node error program (NEP) of the Natural CICS Interface. See also *CICS Node Error Program Considerations for Natural* in the *TP Monitor Interfaces* documentation.

- Link the Natural CICS Interface module `NCIZNEP`.

See also *Natural Nucleus under CICS* in the *TP Monitor Interfaces* documentation.

## Step 10: Link the Natural CICS Interface XFAINTU Exit

(Job I080, Step 2280)

This step must be performed only if you want to use Natural with the CICS 3270 Bridge. See also *CICS 3270 Bridge Support* in the *TP Monitor Interfaces* documentation.

- Link the Natural CICS Interface module `NCIXFATU` under the name `prefixXFA` (see [Prefix Used for Natural CICS Interface Components](#)).

See also *Natural Nucleus under CICS* in the *TP Monitor Interfaces* documentation.

## Step 11: Link the Natural CICS Interface zIIP Shutdown Statistics Program

(Job I080, Step 2285)

This step must be performed only if you want to install [Natural for CICS for zIIP](#), and want to print Natural zIIP statistics when the CICS environment is shut down.

- Link the Natural CICS Interface zIIP shutdown statistics program.

## Step 12: Link the Natural RPC Server Front-End

(Job I080, Step 2290)

This step must be performed only if you want to use the Natural RPC server front-end under CICS.

- Link the Natural RPC server front-end module `NCIRSFE` under the defined name by using the `NCISFED` module.

## Step 13: Initialize the VSAM Roll Files

(Job I081, Step 2200)

This step must be performed only if VSAM roll files are used as CICS roll facility.

- Initialize the VSAM roll files.

This step must be repeated for all roll files used if roll files are the primary roll facility.

A VSAM RRDS file is a direct (random) access type file that must be formatted.

For the Natural CICS Interface VSAM roll files, formatting is done by the `NCISCPRI` batch program. To execute `NCISCPRI`, the Natural roll file to be initialized has to be assigned the file name `ROLL` in the JCL DD statement. No other parameter input is required for `NCISCPRI`; all data required for file initialization is obtained by `SHOWCB` VSAM macro calls.



For descriptions of the messages that can be output during this step, see *NCISCPRI Warnings and Error Messages* in the *TP Monitor Interfaces* documentation.

## CICS Startup Parameters

The Natural CICS Interface modules described in this section use startup parameters to initialize Natural CICS Interface components. The `EXEC CICS ASSIGN` command retrieves the value set by these startup parameters with the `INITPARM` option using the following syntax:

```
INITPARM=(module='parameter',...)
```

where:

*module* is the name of the module that uses a startup parameter. This is the name indicated in the individual module link steps described in this section.

*parameter* the name of the corresponding parameter.

The relevant Natural CICS Interface modules and corresponding parameters are described in the sections below.

- [NCIXCALL Module - External CALLNAT Interface](#)
- [NCIXFATU Module - CICS Global User Exit](#)
- [NCIZNEP Module - CICS Node Error Program](#)
- [NCIRSFE Module - Natural RPC Server Front-End](#)
- [Example of INITPARM](#)

### NCIXCALL Module - External CALLNAT Interface

*parameter* is the name of an `NCIXCALL` module from a previous Natural version (for example, `NCIXCIOV`), if available. The `NCIXCALL` module from the previous Natural version must be linked to assign it a new and different name (see [Step 8: Link the Natural CICS Interface External CALLNAT Interface Module](#)).

For more information, see *Natural 3GL CALLNAT Interface - Purpose, Prerequisites, Restrictions* in the *Operations* documentation.

## NCIXFATU Module - CICS Global User Exit

*parameter* is the name of the Natural CICS Interface Node Error Program linked in [Step 9: Link the Natural CICS Interface Node Error Program](#).

Even if you do not want to modify the default node error program (NEP) DFHZNEP provided by CICS that executes NCIZNEP and terminates a session when a user disconnects a terminal from the CICS region, you need to install and setup NCIZNEP.

The installation is described in [Step 9: Link the Natural CICS Interface Node Error Program](#) and the required startup parameters are described in [NCIZNEP Module - CICS Node Error Program](#).

For further information, see *CICS Node Error Program Considerations for Natural* in the *TP Monitor Interfaces* documentation. For more information on the NCIXFATU module, see *CICS 3270 Bridge Support* in the *TP Monitor Interfaces* documentation.

## NCIZNEP Module - CICS Node Error Program

For information on the NCIZNEP module, see *CICS Node Error Program Considerations for Natural* in the *TP Monitor Interfaces* documentation.

The individual NCIZNEP parameters are described in the following section:

### MSGTRAN - Internal Message Switching Transaction ID

This parameter specifies the transaction ID internally used by the Natural message switching and asynchronous session flushing facilities.

This parameter has the same meaning as the MSGTRAN parameter in NTCICSP (see the *Parameter Reference* documentation) and must be specified identically.

The transaction ID specified with this parameter must be different from any transaction ID used to invoke Natural, and it must be defined in CICS.

Possible values are:

Value	Explanation
<i>transaction-id</i>	<p>A CICS transaction ID for which the PROGRAM attribute specifies the name of the environment-dependent nucleus linked in <a href="#">Step 6: Link the Environment-Dependent Nucleus</a>.</p> <p>The Natural CICS Interface clean-up function is done by starting an asynchronous task to resume the terminal session and to terminate it logically. Therefore, normally the original transaction ID of the session is used. This original transaction ID cannot be used if there is a front-end program calling Natural, as most likely the front-end is not prepared for being invoked asynchronously without a terminal. In such situations, the message switching transaction ID of the Natural CICS Interface is used to deal with Natural directly.</p>

Value	Explanation
NMSG	This is the default value.

### NEPTRAN - Transaction ID for the NCIZNEP Module

This parameter specifies the transaction ID for the Natural/CICS Interface node error program (NEP) NCIZNEP in an MRO environment, when the parameter **PURGE** (see below) is set to YES.

Possible values are:

Value	Explanation
<i>transaction-id</i>	A CICS transaction ID for which the PROGRAM attribute specifies the name of the NCIZNEP module linked in <a href="#">Step 9: Link the Natural CICS Interface Node Error Program</a> .
NETR	This is the default value.

### PURGE - Purge Active Natural Task

This parameter defines how NCIZNEP is to treat Natural sessions currently active, when the Natural/CICS Interface node error program (NEP) is invoked.

Possible values are:

Value	Explanation
NO	This is the default value for compatibility reasons.  The active Natural task is not purged. The active task will continue to run until a terminal I/O later on will result in abend NT08 due to a CICS TERMERR condition, as the terminal no longer exists.
YES	The active Natural task is purged immediately.

In MRO environments, a node error program is triggered in the CICS TOR; as the Natural session most likely is active in a CICS AOR, the task purge cannot be done in the TOR. Therefore, a transaction ID is required (see [NEPTRAN](#) above) to start a “partner” NEP task in the AOR to do the task purge.



**Note:** PURGE=YES requires that the relevant Natural transactions are defined as purgeable (SPURGE(YES)).

### TSKEY - Prefix for Natural CICS Temporary Storage Key

This parameter defines the constant prefix of the temporary storage queue holding the Natural CICS Interface pseudo-conversational restart data.

Possible values are:

Value	Explanation
XXXX	XXXX defines the prefix for pseudo-conversational restart data.
NCOM	This is the default value.

This parameter has the same meaning as the second subparameter of the parameter TSKEY in the NCMDIR macro (see the *TP Monitor Interfaces* documentation) and must be specified identically.

## NCIRSFE Module - Natural RPC Server Front-End

### NATTRAN – CICS Transaction ID for Name of Environment-Dependent Nucleus

This parameter defines the CICS transaction ID that is used to retrieve the name of the environment-dependent nucleus linked in [Step 6: Link the Environment-Dependent Nucleus](#) if the name is not supplied as START data. The PROGRAM attribute of this transaction ID specifies the name of the environment-dependent nucleus.

Possible values are:

Value	Explanation
<i>transaction-id</i>	A CICS transaction ID for which the PROGRAM attribute specifies the name of the environment-dependent nucleus linked in <a href="#">Step 6: Link the Environment-Dependent Nucleus</a> .
NC83	This is the default value.

### MSGDEST – Message Destination for Natural RPC Server Front-End

This parameter defines the message destination for the Natural RPC server front-end.

Possible values are:

Value	Explanation
<i>message-destination</i>	A CICS message destination ID to which the messages of the Natural RPC server front-end are to be sent.
CSSL	This is the default value.

### TRACE – Issue Trace Requests on Entry and Return

This parameter defines whether CICS trace requests are issued on entry to and return from the NCIRSFE module.

Possible values are:

Value	Explanation
<i>destination-id</i>	CICS trace requests are issued on entry to and return from NCIRSFE.
CSSL	CICS trace requests are not issued.  This is the default value.

### GLOBAL – Establish Unique Natural RPC Server IDs

This parameter defines unique Natural RPC server IDs over more than one CICS region.

Possible values are:

Value	Explanation
NO	The Natural RPC server ID consists of the Natural RPC server front-end transaction ID padded with dollar signs (\$).  This is the default value.
YES	The Natural RPC server ID consists of the Natural RPC server front-end transaction ID appended to the CICS system ID, or in other words, to the local SYSID.

### Example of INITPARM

The following is an example of an INITPARM specification:

```
INITPARM=(
  NCIXCALL='NCIXCOLD',          * NCIXCALL module
  NCI22ATU='NCIZNEP',          * NCIXFATU module
  NCIZNEP='MSGTRAN=NMSG,TSKEY=NCOM,PURGE=YES', * NCIZNEP module
  NCI33SFE='NATTRAN=NC83,MSGDEST=CSSL'      * NCIRSFE module
)
```

The example above assumes the following:

- NCIXCALL is the name of the NCIXCALL module linked in [Step 8: Link the Natural CICS Interface External CALLNAT Interface Module](#).
- The NCIXCALL module from the previous Natural version has been linked to assign it the new name NCIXCOLD.
- NCIZNEP is the name of the NCIZNEP module linked in [Step 9: Link the Natural CICS Interface Node Error Program](#).
- NCI22ATU is the name of the NCIXFATU module linked in [Step 10: Link the Natural CICS Interface XFAINTU Exit](#).
- NCI33SFE is the name of the NCIRSFE module linked for the Natural RPC server in [Step 12: Link the Natural RPC Server Front-End](#).

## CICS Resource Definitions

This section describes the resource definitions required or recommended for customizing your CICS system.



**Note:** We generally recommend that you keep all Natural version-dependent components such as programs, transactions and files in a separate resource group. Such a group is represented by *natgroup* in this section.

- [Program Definitions](#)
- [Transaction Definitions](#)
- [File Definitions](#)
- [Transient Data Destinations](#)
- [Temporary Storage Queues](#)
- [Other Definitions](#)

### Program Definitions

To take full advantage of the CICS storage protection and transaction isolation facilities, it is strongly recommended that you specify `EXECKEY(USER)` as the default value for all programs. This section explains if `EXECKEY(CICS)` is required for a definition. In all other cases, use `EXECKEY(USER)`.

The following table provides information about the value combinations of the `API` and `CONCURRENCY` program attributes. The appropriate value combination must be specified consistently for all programs that call one another using direct branch (BASR) instructions:

Program attributes	Remarks
API(CICSAPI) CONCURRENCY(QUASIRENT)	Use these attributes if not all affected programs are threadsafe.
API(OPENAPI) CONCURRENCY(REQUIRED)	Use these attributes if you want to take advantage of the CICS open transaction environment (OTE) and can confirm that all affected programs are threadsafe.  For using the CICS OTE, adapt the program definitions as described in the following section. For general information on using Natural in the CICS OTE, see <i>CICS Open Transaction Environment Considerations</i> in the <i>TP Monitor Interfaces</i> documentation.  For further information, see also <i>Threadsafe Considerations</i> in the <i>TP Monitor Interfaces</i> documentation.
API(OPENAPI) CONCURRENCY(THREADSAFE)	Same as API(OPENAPI) CONCURRENCY(REQUIRED).

Program attributes	Remarks
API(CICSAPI) CONCURRENCY(REQUIRED)	This attribute combination is not supported by the Natural CICS Interface.
API(CICSAPI) CONCURRENCY(THREADSAFE)	This attribute combination is not supported by the Natural CICS Interface.
API(OPENAPI) CONCURRENCY(QUASIRENT)	This attribute combination is prohibited by CICS.

The value combination affects all user-written 3GL programs, as well as front-end programs that call the environment-dependent nucleus of Natural. The front-end programs can be delivered with Natural add-on products or be user-written. Examples of affected programs include NCIRSFE (Natural RPC server front-end), NATCNRFE (Natural Web I/O Interface Server CICS Adapter and Natural Development Server CICS Adapter), and the programs supplied with the Natural CICS Interface listed in the following section.

- [Environment-Dependent Nucleus](#)
- [Environment-Independent Nucleus](#)
- [Natural CICS Interface System Directory](#)
- [External CALLNAT Interface Module](#)
- [Routing Module for Quasi-Reentrant Standard Linkage Calls \(%P=SQ\)](#)
- [Node Error Program](#)
- [Global User Exit](#)
- [Natural RPC Server Front-End](#)
- [Natural zIIP Shutdown Statistics](#)

### Environment-Dependent Nucleus

- Add a program definition for the environment-dependent nucleus:

```
DEFINE PROGRAM(dep-nuc) GROUP(natgroup) LANGUAGE(ASSEMBLER)          *
      DESCRIPTION(ENVIRONMENT-DEPENDENT NUCLEUS)
```

where *dep-nuc* is the environment-dependent nucleus linked in [Step 6: Link the Environment-Dependent Nucleus](#).

The following attribute settings for the program definition are mandatory when using the CICS OTE and recommended otherwise:

```
DATALOCATION(ANY)
```

```
API(OPENAPI)
```

```
CONCURRENCY(REQUIRED)
```



**Note:** If you use the CICS OTE and your application issues many Db2 requests, using EXECKEY(CICS) may improve performance because it prevents CICS from switching from an L9 to an L8 open TCB and back again for every SQL call.

## Environment-Independent Nucleus

This definition is optional.

- Add a program definition for the **environment-independent nucleus**:

```
DEFINE PROGRAM(ind-nuc) GROUP(natgroup) LANGUAGE(ASSEMBLER) *  
    DESCRIPTION(NATURAL ENVIRONMENT-INDEPENDENT NUCLEUS)
```

where *ind-nuc* is the name of the **environment-independent nucleus** specified with the Natural profile parameter NUCNAME. The default name is INDNUC*vr*. You need not specify API, CONCURRENCY, DATALOCATION or EXECKEY for the environment-independent nucleus as all attributes of the environment-dependent nucleus are inherited since standard linkage conventions (direct branch using a BASR instruction) are used.

To access the environment-independent nucleus in the ELPA, specify USELPACOPY(YES) for this program definition and LPA=YES in the CICS startup parameters.

## Natural CICS Interface System Directory

- Add a program definition for the Natural CICS Interface system directory:

```
DEFINE PROGRAM(prefixCB) GROUP(natgroup) LANGUAGE(ASSEMBLER) *  
    DESCRIPTION(NATURAL CICS INTERFACE SYSTEM DIRECTORY)
```

You need not specify API, CONCURRENCY, DATALOCATION or EXECKEY for this module as it is not executable. The attribute EXECKEY defaults to EXECKEY(USER) and must not be changed.



## External CALLNAT Interface Module

This definition is optional.

- Add a program definition for the external CALLNAT interface module:

```
DEFINE PROGRAM(ncixcall) GROUP(natgroup) LANGUAGE(ASSEMBLER)      *
      DESCRIPTION(NATURAL CICS INTERFACE EXTERNAL CALLNAT MODULE)
```

where *ncixcall* is the name of the NCIXCALL module specified in [Step 8: Link the Natural CICS Interface External CALLNAT Interface Module](#).

The following attribute settings for the program definition are mandatory when using the CICS OTE and recommended otherwise:

```
DATALOCATION(ANY)
API(OPENAPI)
CONCURRENCY(REQUIRED)
```

The values of EXECKEY, CONCURRENCY and API for *ncixcall* must be the same as for the **environment-dependent nucleus** because Natural is called by *ncixcall* using standard linkage conventions (direct branch using a BASR instruction) instead of the EXEC CICS LINK command.

## Routing Module for Quasi-Reentrant Standard Linkage Calls (%P=SQ)

This definition is only required if you want to use the %P=SQ terminal command (see the *Terminal Commands* documentation) or the PGP profile parameter with the STDLO property set (see the *Parameter Reference* documentation).

- Add a program definition for the routing module for quasi-reentrant standard linkage calls (%P=SQ) in a threadsafe environment:

```
DEFINE PROGRAM(NCILINKQ) GROUP(natgroup) LANGUAGE(ASSEMBLER)      *
      CONCURRENCY(QUASIRENT) API(CICSAPI)                          *
      DESCRIPTION(ROUTING MODULE FOR QUASI-REENTRANT SL CALLS)
```

We recommend that you set the following parameter value in the CICS program definition:

```
DATALOCATION(ANY)
```

## Node Error Program

This definition is optional.

- Add a program definition for the node error program (NEP) of the Natural CICS Interface:

```
DEFINE PROGRAM(nciznep) GROUP(natgroup) LANGUAGE(ASSEMBLER)          *  
    EXECKEY(CICS)                                                    *  
    DESCRIPTION(NATURAL CICS INTERFACE NODE ERROR PROGRAM)
```

where *nciznep* is the NEP name specified in [Step 9: Link the Natural CICS Interface Node Error Program](#).

## Global User Exit

This definition is optional.

- Add a program definition for the XFAINTU global user exit:

```
DEFINE PROGRAM(prefixXFA) GROUP(natgroup) LANGUAGE(ASSEMBLER)      *  
    EXECKEY(CICS)                                                    *  
    DESCRIPTION(NATURAL CICS INTERFACE XFAINTU GLUE)
```

## Natural RPC Server Front-End

This definition is only required if you want to use the Natural RPC server front-end *ncirsfe*.

- Add a program definition for the Natural RPC server front-end:

```
DEFINE PROGRAM(ncirsfe) GROUP(natgroup) LANGUAGE(ASSEMBLER)      *  
    DESCRIPTION(NATURAL RPC SERVER FRONT-END)
```

where *ncirsfe* is the name of the NCIRSFE module specified for the Natural RPC server front-end in [Step 12: Link the Natural RPC Server Front-End](#).

The following attribute settings for the program definition are mandatory when using the CICS OTE and recommended otherwise:

```
DATALOCATION(ANY)
```

```
API(OPENAPI)
```

```
CONCURRENCY(REQUIRED)
```

The values of `API`, `CONCURRENCY` and `EXECKEY` for `ncirsfe` must be the same as for the **environment-dependent nucleus** because Natural is called by `ncirsfe` using standard linkage conventions (direct branch using a BASR instruction) instead of the `EXEC CICS LINK` command.

### Natural zIIP Shutdown Statistics

These definitions are only required if you want to print Natural zIIP statistics when the CICS environment is shut down (see also *zIIP Processing Reports Available* in the *Natural for zIIP* documentation). Using Natural for zIIP requires using the CICS OTE.

The Natural zIIP shutdown statistics are written to the CSSL queue (directed to DD name MSGUSR).

1. Add a program definition to load the `NCIZPST` module:

```
DEFINE PROGRAM(NCIZPST) GROUP(natgroup) LANGUAGE(ASSEMBLER)          *
      API(OPENAPI) CONCURRENCY(REQUIRED)                             *
      DESCRIPTION(NATURAL ZIIP SHUTDOWN STATISTICS)
```

Add a program definition to load the `NATZPST` module:

```
DEFINE PROGRAM(NATZPST) GROUP(natgroup) LANGUAGE(ASSEMBLER)          *
      DESCRIPTION(NATURAL ZIIP SHUTDOWN STATISTICS)
```

2. Add the `NCIZPST` module to the CICS PLTSD as a first phase PLT program.

### Transaction Definitions

We recommend that you define or choose a CICS profile for the Natural transactions similar to the following:

```
DEFINE PROFILE(natprof) GROUP(natgroup)                               *
      DESCRIPTION(CICS PROFILE FOR NATURAL TRANSACTIONS)              *
      SCRNSIZE(ALTERNATE) INBFMH(ALL)
```

where `natprof` is the name of the CICS profile assigned to the Natural transactions.

We also recommend that you define a CICS transaction class for the Natural transactions similar to the following:

```
DEFINE TRANCLASS(natclass) GROUP(natgroup) MAXACTIVE(999) *  
    DESCRIPTION(CLASS FOR NATURAL TRANSACTIONS)
```

where *natclass* is the name of the CICS transaction class assigned to the Natural transactions.

A CICS transaction class dedicated to Natural helps control storage usage by Natural (see also *Controlling Storage Usage* in the *TP Monitor Interfaces* documentation). Assign this transaction class to the definitions of all transactions that directly or indirectly call Natural.

You can define the following:

- [Natural Transaction](#)
- [Natural Message Switching Transaction](#)
- [Node Error Program](#)
- [Natural RPC Server Front-End](#)

### Natural Transaction

- Add a definition for the Natural transaction:

```
DEFINE TRANSACTION(ncitransact) GROUP(natgroup) *  
    PROGRAM(dep-nuc) TWASIZE(128) DUMP(NO) SPURGE (YES) *  
    PROFILE(natprof) TRANCLASS(natclass)
```

where:

*ncitransact* is the name of the Natural CICS Interface user transaction ID.

*dep-nuc* is the environment-dependent nucleus linked in [Step 6: Link the Environment-Dependent Nucleus](#).

We recommend that you set the following parameter values in the CICS transaction definitions:

```
TASKDATALOC(ANY)
```

```
ISOLATE(YES)
```

TASKDATALOC(ANY) can have an impact on non-Natural programs called by Natural; for details, see the relevant IBM literature on CICS.

For the impact of transaction isolation, see also *THRDSIZE - Thread Size* in the *TP Monitor Interfaces* documentation.

## Natural Message Switching Transaction

- Add a definition for the Natural internal message switching transaction:

```
DEFINE TRANSACTION(nmsg) GROUP(natgroup) *
      PROGRAM(dep-nuc) TWASIZE(128) DUMP(NO) SPURGE (YES) *
      PROFILE(natprof) TRANCLASS(natclass)
```

where:

*dep-nuc* is the environment-dependent nucleus linked in [Step 6: Link the Environment-Dependent Nucleus](#).

*nmsg* is the name of the Natural CICS Interface message switching transaction ID as defined with the MSGTRAN parameter in the NTCICSP macro described in the *Parameter Reference* documentation. The default name is NMSG.

We recommend that you set the following parameter values in the CICS transaction definitions:

```
TASKDATALOC(ANY)
```

```
ISOLATE(YES)
```

TASKDATALOC(ANY) can have an impact on non-Natural programs called by Natural; for details, see the relevant IBM literature on CICS.

For the impact of transaction isolation, see also *THRDSIZE - Thread Size* in the *TP Monitor Interfaces* documentation.

## Node Error Program

This definition is optional.

- Add a definition for the node error program (NEP) of the Natural CICS Interface:

```
DEFINE TRANSACTION(neptran) GROUP(natgroup) *
      PROGRAM(nciznep) DUMP(NO) PRIORITY(255) *
      TASKDATAKEY(CICS) TASKDATALOC(ANY) *
      PROFILE(natprof)
```

where:

*neptran* is the NEP transaction code defined with the NEPTRAN parameter of the NCIZNEP module linked in [Step 9: Link the Natural CICS Interface Node Error Program](#).

*nciznep* is the NEP name of the NCIZNEP module linked in [Step 9: Link the Natural CICS Interface Node Error Program](#).

## Natural RPC Server Front-End

- Add a definition for the Natural RPC server front-end transaction:

```
DEFINE TRANSACTION(ncisfetransact) GROUP(natgroup) *  
    PROGRAM(ncirsfe) TWASIZE(128) DUMP(NO) SPURGE (YES) *  
    PROFILE(natprof) TRANCLASS(natclass)
```

where:

*ncisfetransact* is the name of the Natural RPC server front-end transaction ID.

*ncirsfe* is the name of the NCIRSFE module specified for the Natural RPC server front-end in [Step 12: Link the Natural RPC Server Front-End](#).

## File Definitions

These definitions are only required if VSAM roll files are to be used.

- Add one entry in the FCT for each Natural CICS Interface VSAM roll file:

```
DEFINE FILE(prefixR1) GROUP(natgroup) *  
    BROWSE(YES) ADD(YES) DELETE(YES) UPDATE(YES) READ(YES) *  
    RECORDFORMAT(F) STRINGS(3) DATABUFFERS(5)
```

Local shared resources (LSR) should be used whenever possible. If multiple LSR pools are supported, one pool should be dedicated exclusively to Natural CICS Interface roll files.

## Transient Data Destinations

- [Error Messages](#)
- [Natural NATRJE Utility](#)
- [Natural CICS Interface Session Statistics](#)
- [Natural CICS Interface Profile Parameter File](#)

## Error Messages

This definition is optional but highly recommended to log Natural CICS Interface informational messages and Natural abend codes and corresponding error messages.

Add entries in the DCT for the Natural CICS Interface error message logging facility. For Natural error messages, you can use:

- A destination that is already defined in CICS (for example, CSSL); in this case, no extra DCT entry is required.
- An extra partition destination as a synonym for an existing CICS message destination:

```
DEFINE TDQUEUE(message-destination) GROUP(natgroup) TYPE(INDIRECT)      *
      INDIRECTNAME(name)
```

where:

*message-destination* is the name of the Natural CICS Interface error message destination as defined with the MSGDEST parameter in the NTCICSP macro described in the *Parameter Reference* documentation. The default name is NERR.

*name* is the name of the corresponding indirect destination.

- An extra file:

```
DEFINE TDQUEUE(message-destination) GROUP(natgroup) TYPE(EXTRA)      *
      DDNAME(NATMSG) OPEN(INITIAL) TYPEFILE(OUTPUT)                  *
      RECORDFORMAT(VARIABLE) BLOCKFORMAT(UNBLOCKED)                  *
      RECORDSIZE(nnn)
```

where *message-destination* is the name of the Natural CICS Interface error message destination as defined with the MSGDEST parameter in the NTCICSP macro described in the *Parameter Reference* documentation. The default name is NERR.

You can, for example, change the BLOCKFORMAT format from UNBLOCKED to BLOCKED. Natural and the Natural CICS Interface messages have a length of up to 120 bytes. Therefore, the record size (RECORDSIZE (*nnn*)) should be at least 124 bytes for variable record format or 120 bytes for fixed record format.

### When using a disk file:

Sufficient disk space must be reserved for this data set; a DD statement must be added to the CICS startup JCL.

### Natural NATRJE Utility

- Add one entry in the DCT for the Natural NATRJE utility (described in the *Utilities* documentation). When submitting a job to JES with the following entry, the internal reader is started on CLOSE of the destination:

```
DEFINE TDQUEUE(submit-destination) GROUP(natgroup) TYPE(EXTRA)      *
      DDNAME(NATRJE) OPEN(DEFERRED) TYPEFILE(OUTPUT)                  *
      RECORDFORMAT(FIXED) BLOCKFORMAT(UNBLOCKED) RECORDSIZE(80)
```

where:

*submit-destination* is the name of the Natural CICS Interface submit destination as defined with the RJEDEST parameter in the NTCICSP macro described in the *Parameter Reference* documentation. The default name is NRJE.

Additionally, add the following DD statement to the CICS startup JCL:

```
//NATRJE DD SYSOUT=(*,INTRDR)
```

When submitting a job to JES with the following *two* entries, the Natural CICS Interface deals with an indirect destination that will not be closed:

```
DEFINE TDQUEUE(submit-destination) GROUP(natgroup) TYPE(INDIRECT)      *  
    INDIRECTNAME(name)  
  
DEFINE TDQUEUE(name) GROUP(natgroup) TYPE(EXTRA)                      *  
    DDNAME(NATRJE) OPEN(DEFERRED) TYPEFILE(OUTPUT)                    *  
    RECORDFORMAT(FIXED) BLOCKFORMAT(UNBLOCKED) RECORDSIZE(80)
```

where:

*submit-destination* is the name of the Natural CICS Interface submit destination as defined with the RJEDEST parameter in the NTCICSP macro described in the *Parameter Reference* documentation. The default name is NRJE.

*name* is the name of the corresponding indirect destination.

You can use either a /\*EOF card as the very last card in the job stream or the corresponding NATRJE exit. When detecting the /\*EOF card, JES submits the previous job stream.

### Natural CICS Interface Session Statistics

This definition is optional.

- Add one entry in the DCT for the Natural CICS Interface session statistics:

```
DEFINE TDQUEUE(log-destination) GROUP(natgroup) TYPE(EXTRA)          *  
    DDNAME(NATLOG) OPEN(INITIAL) TYPEFILE(OUTPUT)                    *  
    RECORDFORMAT(VARIABLE) BLOCKFORMAT(BLOCKED)                      *  
    RECORDSIZE(4624) BLOCKSIZE(4628)
```

where *log-destination* is the name of the Natural CICS Interface logging destination as defined with the parameter LOGDEST described in the *Parameter Reference* documentation. The default name is NLOG.

Sufficient disk space must be reserved for this data set; a DD statement must be added to the CICS startup JCL.



## Natural CICS Interface Profile Parameter File

This definition is optional.

- Add one entry in the DCT for the Natural CICS Interface profile parameter file:

```
DEFINE TDQUEUE(parameter-destination) GROUP(natgroup) TYPE(EXTRA)      *
      DDNAME(CMPRMIN) OPEN(DEFERRED) TYPEFILE(INPUT)                  *
      RECORDFORMAT(FIXED) BLOCKFORMAT(BLOCKED)                        *
      RECORDSIZE(80) BLOCKSIZE(nnn)
```

where:

*parameter-destination* is the name of the Natural CICS Interface profile parameter input destination as defined with the `PRMDEST` parameter in the `NTCICSP` macro described in the *Parameter Reference* documentation. The default name is `NPRM`.

*nnn* is a multiple of 80.

A DD statement must be added to the CICS startup JCL.

## Temporary Storage Queues

Using the prefix determined by the value of the parameter `PREFIX` in the `NTCICSP` macro of the Natural parameter module, the Natural CICS Interface creates temporary storage queues to store control records.

To exempt these temporary storage control records from automatic deletion, do not specify an expiry interval in the respective `TSMODEL` resource definition.

## Other Definitions

- Add the following system abend codes to a CICS System Recovery Table (SRT):

0D6	Protects CICS against failing Natural Roll Server and Natural Authorized Services Manager requests (using PC instructions) by Natural.
01D	Protects CICS against failing data space cache requests by Natural.
DC2	Protects CICS against failing memory object cache requests by Natural.

## Installation Verification

---

You can verify the successful installation of the Natural CICS Interface by performing the following steps:

1. From a CICS session, type in the Natural transaction ID to start a Natural session.
2. Proceed with the steps described in the section [\*Test Online Natural\*](#).

# VIII

## Installing Natural Com-plete/SMARTS Interface on

z/OS

---



## 9 Installing Natural Com-plete/SMARTS Interface on z/OS

---

■ Prerequisites .....	110
■ Installation Medium .....	110
■ Installation Procedure .....	111
■ Installation Verification .....	115

This document describes the steps for installing Natural Com-plete/SMARTS Interface which corresponds to the Natural Com-plete Interface (product code NCF) on z/OS.

### Related Topics:

For information on how to operate Natural in a Com-plete/SMARTS environment, see the following topics:

- *Using Natural with TP Monitors* in the *TP Monitor Interfaces* documentation.
- *Natural under Com-plete/SMARTS* in the *TP Monitor Interfaces* documentation.
- *Natural under Com-plete/SMARTS User Abend Codes* in the *Messages and Codes* documentation.

For information on installing and using Com-plete, see the *Com-plete* documentation.

### Notation *vrs* or *vr*:

When used in this document, the notation *vrs* or *vr* represents the relevant product version (see also Version in the *Glossary*).

## Prerequisites

---

A supported version of the following product must be installed before you can install the Natural Com-plete/SMARTS Interface:

- Com-plete

See the Com-plete *Installation* documentation.

See also [General Prerequisites and System Support](#) in the section *Overview of the Installation Process*.

## Installation Medium

---

The **installation medium** contains the following data sets required for product installation:

Data Set Name	Contents
NCF <i>vrs</i> .LOAD	Load modules
NCF <i>vrs</i> .SRCE	Source modules and macros
NCF <i>vrs</i> .LICS	Product license file for Natural for Com-plete for zIIP
	For information on the license file and product licensing, see <i>Mainframe Product Licensing</i> .

Copy the data sets into your environment as described in [Copying Data Sets to a z/OS Disk](#) in the section *Installing Natural*.

### Sample Jobs

Sample installation jobs are contained in the NATVRS.JOBS data set and are prefixed with the product code. The data set is provided on the installation medium supplied for base Natural.

## Installation Procedure

---

Be sure to read [Installation Process and Major Natural Features](#) before you start the installation procedure.

- [Step 1: Prepare, Convert, Assemble and Link the License File for Natural for Com-plete for zIIP](#)
- [Step 2: Create the Startup Program](#)
- [Step 3: Build the Natural Parameter Module](#)
- [Step 4: Link the Nucleus](#)
- [Step 5: Link the Natural Com-plete/SMARTS Interface Server](#)
- [Step 6: Define the Natural Com-plete/SMARTS Interface Server](#)
- [Step 7: Catalog the Natural Com-plete/SMARTS Interface](#)
- [Step 8: Natural zIIP Shutdown Statistics](#)

### Step 1: Prepare, Convert, Assemble and Link the License File for Natural for Com-plete for zIIP

(Job I007, Steps 2301, 2302, 2304)

This step is optional and only required if you want to install Natural for Com-plete for zIIP.

You must install a valid Natural license file. An additional license file is required if you want to install Natural for Com-plete for zIIP to enable support of the IBM z/IIP (IBM System z Integrated Information Processor).

For detailed information on the license file and product licensing, see *Mainframe Product Licensing*.

1. Copy the license file from the supplied installation medium to disk or transfer it from the PC as described in *Transferring a License File from PC to a z/OS Host Using FTP* in *Mainframe Product Licensing*.
2. Check, convert, assemble and link the license file supplied for Natural for Com-plete for zIIP:

Step 2301	Check license file <code>NCFvrs.LICS</code> . This job runs the CHECK function of the LICUTIL license utility (see below).
Step 2302	Convert license file into an assembler source. This job runs the MAKE function of the LICUTIL license utility (see below).
Step 2304	Assemble and link the assembler source to generate load module <code>NCF LIC</code> . This module is then linked to the nucleus in <a href="#">Job I080</a> .

The functions and option settings provided by LICUTIL are described in *Using the License Utility: LICUTIL in Mainframe Product Licensing*.

## Step 2: Create the Startup Program

(Job I070, Steps 2320, 2321)

This step is optional.

You can use a Natural Com-plete/SMARTS Interface startup program to pass dynamic parameters to Natural.

1. Adapt the example program `NC0001` contained in the source library to your requirements.
2. Assemble and link the startup program into your Com-plete user program library.

## Step 3: Build the Natural Parameter Module

(Job I080, Steps 2300, 2310)

The Natural profile parameters and parameter macros mentioned in this section are described in the *Parameter Reference* documentation unless otherwise noted.

1. Modify the Natural parameter module for Com-plete/SMARTS:
  - Configure the Com-plete/SMARTS batch interface: Modify the settings of the parameters supplied with the macro `NTCOMP` to meet your requirements. For descriptions of these parameters, see the corresponding profile parameter `COMP`.
  - Modify the following parameters:

```
FNAT=(database-id,file-number)
FUSER=(database-id,file-number)
```

where *database-id* and *file-number* are the values you specified when loading the system files during the [Installation Procedure](#) for base Natural.

2. Define a Natural local buffer pool under Com-plete by modifying the values of the keyword parameters supplied with the parameter macro `NTBPI` (see the Natural profile parameter `BPI`) as required.



A local buffer pool is allocated during initialization of the first Natural session after Com-plete startup.

The status of the local buffer pools can be displayed on the operator console by issuing the following Com-plete operator command:

```
SERV,server-name,BPSTAT
```

where *server-name* is the name of the server as specified with the Com-plete SERVER startup option.

3. If you want to use a Natural global buffer pool under Com-plete, specify the same values as in the Natural installation procedure for the profile parameter `SUBSID` in the parameter macro `NTPRM` (see the *Operations* documentation) for the keyword subparameter `NAME` in the parameter macro `NTBPI` (see the *Parameter Reference* documentation).
4. Assemble and link the Natural parameter module.

#### Step 4: Link the Nucleus

(Job I080, Step 2320)

Link the **environment-dependent nucleus** for the Natural Com-plete/SMARTS Interface.

- Link the **environment-dependent nucleus** into your Com-plete user program library.

The list of the modules to be linked for the environment-dependent nucleus is supplied with Step 2320.

If you want Natural to run in the IBM Language Environment (LE), set the **System Maintenance Aid (SMA)** `NAT-LE` to Y (Yes). The default setting is N (No).

- Specify the **environment-dependent nucleus** as a Com-plete startup option by setting the following Com-plete keyword parameter:

```
RESIDENTPAGE=name
```

where *name* is the name of the environment-dependent nucleus for the Natural Com-plete/SMARTS Interface.

## Step 5: Link the Natural Com-plete/SMARTS Interface Server

(Job I080, Step 2350)

- Link the Natural Com-plete/SMARTS Interface server.

The Natural Com-plete/SMARTS Interface server is used to maintain common storage and tables across Natural sessions, for example, the local buffer pool.

## Step 6: Define the Natural Com-plete/SMARTS Interface Server

- Specify the Natural Com-plete/SMARTS Interface server as a Com-plete startup option by setting the following Com-plete keyword parameter:

```
SERVER=(server-name,module-name)
```

where:

*server-name* is the name of the server as specified with the keyword subparameter SERVER in the parameter macro NTCOMP (see the *Parameter Reference* documentation).

*module-name* is the name of the load module linked in [Step 4: Link the Natural Com-plete/SMARTS Interface Server](#).

The Natural Com-plete/SMARTS Interface server module is loaded during Com-plete initialization. The module must therefore be placed in a load library contained in the COMPINIT load library concatenation (see also the Com-plete *Installation* documentation).

## Step 7: Catalog the Natural Com-plete/SMARTS Interface

This step is required if either of the following is true:

You run Natural under Com-plete/SMARTS and use threads below the line (THABOVE=NO setting in the NTCOMP macro).

Or:

You want to use Natural work pools below the 16-MB line.

- Catalog the Natural Com-plete/SMARTS Interface by using the Com-plete ULIB utility.

- For threads below the line:

The region size to be specified with the ULIB utility parameter RG depends on the setting of the keyword subparameter NTHSIZE in the parameter macro NTCOMP described in the *Parameter Reference* documentation.

- For work pools below the 16-MB line:

The region size to be specified with the ULIB utility parameter `RG` depends on the setting of the Natural profile parameter `WPSIZE` (see the *Parameter Reference* documentation) for the parameter macro `NTPRM` (see the *Operations* documentation).

See also *Storage Usage* in the section *Natural under Com-plete/SMARTS* in the *TP Monitor Interfaces* documentation.

After installation, you can use the Natural SYSTP utility (see the *Utilities* documentation) to determine the region size actually used.

### Step 8: Natural zIIP Shutdown Statistics

This step is required if you want to print Natural zIIP statistics when the Com-plete environment is shut down. For more information, see *zIIP Processing Reports Available* in the *Natural for zIIP* documentation.

NCFTRMEX writes zIIP statistics to the `APSLLOG` which are being collected since the startup of Com-plete. The shutdown exit `NCFTRMEX` uses program `NATZPST` to access the zIIP statistics.

To activate zIIP Shutdown statistics, the modules `NCFTRMEX` and `NATZPST` must be placed in a load library contained in the Com-plete `COMPLIB` load library concatenation. For more information, see the *Com-plete Installation* documentation.

## Installation Verification

---

You can verify the successful installation of the Natural Com-plete/SMARTS Interface by performing the following steps:

1. Stop and restart Com-plete.
2. Enter the Com-plete user menu and type in the name of the environment-dependent nucleus for the Natural Com-plete/SMARTS Interface.

The Natural initial screen should appear.

3. Proceed with the steps described in the section [Test Online Natural](#).



# IX

## Installing Natural IMS TM Interface on z/OS

---



# 10

## Installing Natural IMS TM Interface on z/OS

---

■ Prerequisites .....	120
■ Installation Medium .....	120
■ Installation Procedure .....	121
■ Prepare, Convert, Assemble and Link the License File for Natural for IMS for zIIP .....	121
■ Common Installation Steps .....	122
■ Installing the Batch Message Processing BMP Environment .....	124
■ Installing the Message-Oriented NTRD Environment .....	126
■ Installing the Dialog-Oriented MPP Environment .....	128
■ Installing the Natural Development/Natural Web I/O Interface Server .....	132
■ Installing the Server Environment .....	133
■ Customizing the IMS TM Environment .....	135
■ Installation Verification .....	139

This document describes the steps for installing the Natural IMS TM Interface (product code NII) on z/OS.

### Related Topic:

For information on how to operate Natural in an IMS TM environment, see *Using Natural with TP Monitors* and *Natural under IMS TM* in the *TP Monitor Interfaces* documentation.

### Notation *vrs* or *vr*:

When used in this document, the notation *vrs* or *vr* represents the relevant product version (see also Version in the *Glossary*).

## Prerequisites

---

The following software must be installed before you can install the Natural IMS TM Interface:

- Natural global buffer pool if you are using the MPP environment (strongly recommended).
- Natural Roll Server if the `ROLLSRV` parameter of the Natural IMS TM Interface is set to YES.
- Natural Authorized Services Manager with the SIP server function if the Non-Conversational MPP Interface, the monitoring or the broadcasting function of the Natural IMS TM Interface is used.
- Natural Authorized Services Manager if the Accounting to SMF function of the Natural IMS TM Interface is used.
- Adabas IMS/TM Interface (product code AII), version as specified under *Product Versions Supported by Natural* in the current Natural for z/OS *Release Notes*.

For further information on the functions mentioned above, see the relevant sections in the *TP Monitor Interfaces* and *Operations* documentation.

See also [General Prerequisites and System Support](#) in the section *Overview of the Installation Process*.

## Installation Medium

---

The [installation medium](#) contains the following data sets required for product installation:



Data Set Name	Contents
NII <i>vrs</i> .LOAD	Load modules
NII <i>vrs</i> .SRCE	Source modules and macros

Copy the data sets into your environment as described in [Copying Data Sets to a z/OS Disk](#) in the section *Installing Natural*.

### Sample Jobs

Sample installation jobs are contained in the NAT *vrs*.JOBS data set and are prefixed with the product code. The data set is provided on the installation medium supplied for base Natural.

## Installation Procedure

Be sure to read [Installation Process and Major Natural Features](#) before you start the installation procedure.

The installation procedure comprises the following:

- [Prepare, Convert, Assemble and Link the License File for Natural for IMS for zIIP](#)
- [Common Installation Steps](#)
- [Installing the Batch Message Processing BMP Environment](#)
- [Installing the Message-Oriented NTRD Environment](#)
- [Installing the Dialog-Oriented MPP Environment](#)
- [Installing the Natural Development/Natural Web I/O Interface](#)
- [Installing the Server Environment](#)
- [Customizing the IMS TM Environment](#)

### Prepare, Convert, Assemble and Link the License File for Natural for IMS for zIIP

(Job I007, Steps 2501, 2502, 2504)



**Note:** This step is optional. It is only required if you want to install Natural for IMS for zIIP, and if Natural IMS TM Interface Version 8.3.4 is installed in your environment.

You must install a valid Natural license file. An additional license file is required if you want to install [Natural for IMS for zIIP](#) to enable support of the IBM z/IIP (IBM System z Integrated Information Processor).

For detailed information on the license file and product licensing, see *Mainframe Product Licensing*.

1. Copy the license file from the supplied installation medium to disk or transfer it from the PC as described in *Transferring a License File from PC to a z/OS Host Using FTP* in *Mainframe Product Licensing*.
2. Check, convert, assemble and link the license file supplied for Natural for IMS for zIIP:

Step 2501	Check license file <code>NIIvrs.LICS</code> . This job runs the CHECK function of the LICUTIL license utility (see below).
Step 2502	Convert license file into an assembler source. This job runs the MAKE function of the LICUTIL license utility (see below).
Step 2504	Assemble and link the assembler source to generate load module <code>NII LIC</code> .  This module is then linked to all relevant front-ends in the Jobs I070 and I080.

The functions and option settings provided by LICUTIL are described in *Using the License Utility: LICUTIL* in *Mainframe Product Licensing*.


## Common Installation Steps

---

### Note for LE Options:

If you want Natural to run in the IBM Language Environment (LE), set the **System Maintenance Aid (SMA)** parameter `NAT-LE` to Y (Yes). The default setting is N (No). Additionally, if you want to modify the LE options in the `NATLEOPT` source module or if you use non-Natural programs running in 24-bit mode, set the appropriate SMA parameter as described in *Build the Natural-Specific IBM Language Environment Options* in *Installing Natural*.

The following is an overview of the installation jobs/steps required to install the Natural IMS TM Interface in a BMP, an NTRD an MPP and/or a server environment:



## Step: Link the Natural IMS TM Interface Module

(Job I055, Step 2582)

- Link the Natural IMS TM Interface module.


The same interface module can be used in a BMP, an NTRD, an MPP and/or a server environment.

The name of the interface module must be specified with the `NI I NAME` keyword subparameter of the `NTIMSP` macro contained in the Natural parameter module. For details, see the *Parameter Reference* documentation.

## Installing the Batch Message Processing BMP Environment

---

The following is an overview of the installation jobs/steps required to install the Natural IMS TM Interface for the BMP environment:



### Step: Link the BMP Front-End

(Job I070, Step 2510)

The front-end consists of the load module `NIIBMP` contained in the `NIIvrs.LOAD` data set, the Natural parameter module created in *Build the Natural Parameter Module* (see *Installing Natural*) and additional optional modules (see the list of module names supplied with Step 2510).

- Link the front-end for the BMP environment.




**Important:** The name of the linked BMP front-end must also be specified in your BMP region job as the application program name (parameter `MBR` of the `IMSBATCH` procedure invocation).

You can specify the parameter settings for your BMP environment by using the parameter macros `NTIMSP` and `NTIMSPE` of the Natural parameter module (see the *Parameter Reference* documentation).

## Installing the Message-Oriented NTRD Environment

---

The following is an overview of the installation jobs/steps required to install the Natural IMS TM Interface for the NTRD environment:



- Step 1: Build the NIIBOOT Bootstrap Module

■ [Step 2: Link the NTRD Front-End](#)

### Step 1: Build the NIIBOOT Bootstrap Module

(Job I056, Steps 2520, 2521)

This step is only required if you want to invoke the NTRD front-end by a bootstrap module and not directly by a transaction code.

1. Create the NIIBOOT source module which contains a call to the NIMBOOT macro. For the DRIVERN parameter, specify the name of the front-end module to be linked in [Step 2](#).
2. Assemble and link the bootstrap module.

### Step 2: Link the NTRD Front-End

(Job I070, Step 2530)

The front-end consists of the NIINTRD load module contained in the NIIVrs.LOAD data set, the Natural parameter module created in [Build the Natural Parameter Module](#) (see *Installing Natural*) and additional optional modules (see the list of module names supplied with Step 2530).

- Link the front-end for the NTRD environment.

If you invoke the NTRD front-end by a bootstrap module, you must additionally specify the name of the linked NTRD front-end as the driver name (DRIVERN parameter) in the NIMBOOT macro. The NIMBOOT macro is described in the *TP Monitor Interfaces* documentation.

If you invoke the NTRD front-end directly by a transaction code, you must additionally specify the name of the linked NTRD front-end as the application program name (parameter PSB) in the APPLCNT macro.


You can specify the parameter settings for your NTRD environment by using the parameter macros NTIMSP and NTIMSPE of the Natural parameter module (see the *Parameter Reference* documentation).

## Installing the Dialog-Oriented MPP Environment

---

The following is an overview of the installation jobs/steps required to install the Natural IMS TM Interface for the MPP environment:





- [Step 1: Allocate and Format the Roll Files](#)
- [Step 2: Build the Natural Parameter Module](#)
- [Step 3: Link the Conversational MPP Front-End](#)
- [Step 4: Link the Non-Conversational MPP Front-End](#)

## Step 1: Allocate and Format the Roll Files

(Job I070, Step 2590)

This step is only required if you do not use the Natural Roll Server.

If you do not want to use the Natural Roll Server, you have to allocate and format the roll files to be used by the Natural IMS TM Interface.

You can allocate up to 5 sequential data sets with a fixed-record format for use as roll files.

1. Allocate the roll files.
2. Format the roll files by using the module NATRSRFI described in *Formatting the Roll File* in the *Operations* documentation.

The roll file initialization program produces a WTO message indicating the number of concurrent users which can be serviced by the roll file. For information on the roll file facility, see *Natural Roll Server Functionality* in the *Operations* documentation.

## Step 2: Build the Natural Parameter Module

(Job I080, Steps 2500, 2510)

1. Set the profile parameters FNAT and FUSER (see the *Parameter Reference* documentation) in the Natural parameter module:

```
FNAT=(database-id,file-number)
FUSER=(database-id,file-number)
```

where *database-id* and *file-number* are the values you specified when loading the system files during the [Installation Procedure](#) for base Natural.

2. If you want to use a Natural global buffer pool, specify the macro NTBPI in the Natural parameter module with the name of the global Natural buffer pool and set the profile parameter SUBSID in the parameter module.

If you want to use any other buffer pool, specify the macro NTBPI in the parameter module for each required buffer pool type.

We strongly recommend that you use a global buffer pool for each buffer pool type.

If an editor buffer pool is required, you must use a global editor buffer pool.

3. Modify any other parameters in the parameter module whose default values do not meet your requirements. For further information on the parameters contained in the parameter module, see *Building a Natural Parameter Module* in the *Operations* documentation.
4. Assemble and link the Natural parameter module for the dialog-oriented environments.

### Step 3: Link the Conversational MPP Front-End

(Job I080, Step 2570)

The front-end consists of the `NIICONV` load module contained in the `NIIVrs.LOAD` data set, the Natural parameter module created in [Step 2: Build the Natural Parameter Module](#) and additional optional modules (see the list of module names supplied with Step 2570).

- Link the front-end for the conversational MPP environment.



**Important:** The name of the linked MPP front-end must also be specified in the `APPLCNT` macro as the application program name (parameter `PSB`).

You can specify the parameter settings for your conversational MPP environment by using the parameter macros `NTIMSP` and `NTIMSPE` of the Natural parameter module (see the *Parameter Reference* documentation).

### Step 4: Link the Non-Conversational MPP Front-End

(Job I080, Step 2572)

The front-end consists of the `NIINONC` load module contained in the `NIIVrs.LOAD` data set, the Natural parameter module created in [Step 2: Build the Natural Parameter Module](#) and additional optional modules (see the list of module names supplied with Step 2572).

- Link the front-end for the non-conversational MPP environment.




**Important:** The name of the Non-Conversational MPP front-end must also be specified in the `APPLCNT` macro as the application program name (parameter `PSB`).

You can specify the parameter settings for your non-conversational MPP environment by using the parameter macros `NTIMSP` and `NTIMSPE` of the Natural parameter module (see the *Parameter Reference* documentation).

## Installing the Natural Development/Natural Web I/O Interface Server

The following steps are required to implement the Natural Development Server (NDV) and the Natural Web I/O Interface (NWO) server in your IMS TM environment.



**Note:** You are recommended to also read the information contained in the sections *Installing the Natural Development Server IMS Adapter* of the *Natural Development Server for z/OS (Batch)*

documentation and *Installing the Natural Web I/O Interface Server IMS Adapter under z/OS* in the *Natural Web I/O Interface* documentation.

### Step: Link the Natural Development/Natural Web I/O Interface Server Front-End

(Job I080, Step 2586)

The front-end consists of the `NIISFE` load module contained in the `NIIVRS.LOAD` data set, the Natural parameter module created in [Step 2: Build the Natural Parameter Module](#) and additional optional modules (see the list of module names supplied with Step 2586).

- Link the front-end for the Natural Development Server/Natural Web I/O Interface server.




**Important:** The name of the linked Natural Development Server/Natural Web I/O Interface server front-end must also be specified in the `APPLCNT` macro as the application program name (parameter `PSB`).

You can specify the parameter settings for your Natural Development Server/Natural Web I/O Interface server environment by using the parameter macros `NTIMSP` and `NTIMSPE` of the Natural parameter module (see the *Parameter Reference* documentation).

## Installing the Server Environment

---

The following is an overview of the installation jobs/steps required to install the Natural IMS TM Interface for the server environment:



- Step 1: Build the NIIBOOTS Bootstrap Module

- [Step 2: Link the Server Front-End](#)

### Step 1: Build the NIIBOOTS Bootstrap Module

(Job I056, Steps 2540, 2541)

1. Create the NIIBOOTS source module which contains a call to the NIMBOOT macro with the SERVER parameter set to YES. For the DRIVERN parameter, specify the name of the front-end module to be linked in [Step 2](#).
2. Assemble and link the bootstrap module.

### Step 2: Link the Server Front-End

(Job I070, Step 2550)

The front-end consists of the NIISRVD load module contained in the NIIVRS.LOAD data set, the Natural parameter module created in [Build the Natural Parameter Module](#) (see *Installing Natural*) and additional optional modules (see the list of module names supplied with Step 2550).

- Link the front-end for the server environment.



**Important:** The name of the server front-end must also be specified in the NIMBOOT macro as the driver name (parameter DRIVERN) described in the *TP Monitor Interfaces* documentation.

You can specify the parameter settings for your server environment by using the parameter macros NTIMSP and NTIMSPE of the Natural parameter module (see the *Parameter Reference* documentation).

## Customizing the IMS TM Environment

The following steps require system modifications to your IMS TM environment.

- [Step 1: Create the APPLCTN Table Definitions for MPP, BMP, NTRD and SFE](#)
- [Step 2: Create the PSB/ACB for both the MPP and BMP](#)
- [Step 3: Create the BMP and MPP Regions](#)

- [Step 4: Create the PRELOAD List](#)

**Step 1: Create the APPLCTN Table Definitions for MPP, BMP, NTRD and SFE**

Create the APPLCTN table definitions for MPP, BMP and NTRD according to the following examples:

- Example for MPP:

```
APPLCTN PSB=NIIvrsFR,PGMTYPE=TP
        TRANSACT CODE=NATvrs,MODE=SNGL,SPA=512,
        MSGTYPE=(SNLGSEG,RESPONSE,4) *
```



**Important:** The size of the SPA must be set to at least 157 bytes plus the NRAFT value specified in the NTIMSPT macro of the Natural parameter module.

- Example for BMP (message-driven or specific for Natural Advanced Facilities):

```
APPLCTN PSB=NIIvrsBM,PGMTYPE=BATCH
        TRANSACT CODE=NATvrsBM,MODE=SNGL,
        MSGTYPE=(SNLGSEG,RESPONSE,4) *
```

This APPLCTN definition is required if you use the CMGETMSG feature.

- Example for BMP (without message queue processing):

```
APPLCTN PSB=NIIvrsBM,PGMTYPE=BATCH
```

- Example for NTRD:

```
APPLCTN PSP=NIIvrsOB,PGMTYPE=TP
        TRANSACT CODE=NATvrsOB,MODE=SNGL,
        MSGTYPE=(MULTSEG,NONRESPONSE,4) *
```

- Example for SFE:

```
APPLCTN PSB=NIIvrsAD,PGMTYPE=TP,SCHDTYP=PARALLEL
        TRANSACT CODE=NATvrsAD,MODE=SNGL,
        MSGTYPE=(SNGLSEG,NONRESPONSE,4) *
```



**Step 2: Create the PSB/ACB for both the MPP and BMP**

1. Create the PSB for MPP according to the following example for conversational Natural:

```
PCB TYPE=TP,MODIFY=YES
PCB TYPE=TP,MODIFY=YES
PCB TYPE=TP,MODIFY=YES
SENSEG NAME=COURSE
SENSEG NAME=PREREQ,PARENT=COURSE
SENSEG NAME=OFFERING,PARENT=COURSE
SENSEG NAME=TEACHER,PARENT=OFFERING
SENSEG NAME=STUDENT,PARENT=OFFERING

PSBGEN PSBNAME=NII vrsFR,LANG=ASSEM,MAXQ=3,IOASIZE=132
```

At least one modifiable TP-PCB must be defined for default use of hardcopy, sending messages and transaction switching. The value of the WRKPCBS keyword subparameter (NTIMSPT macro in the Natural parameter module) in the current environment table must be less than or equal to the number of PCBs minus 1 to avoid a Natural initialization error.

2. Create the PSB for BMP according to the following example:

```
PCB TYPE=TP,MODIFY=YES
PCB TYPE=TP,MODIFY=YES

SENSEG NAME=COURSE
SENSEG NAME=PREREQ,PARENT=COURSE
SENSEG NAME=OFFERING,PARENT=COURSE
SENSEG NAME=TEACHER,PARENT=OFFERING
SENSEG NAME=STUDENT,PARENT=OFFERING

PSBGEN PSBNAME=NII vrsBM,LANG=ASSEM,MAXQ=3,IOASIZE=132
```

At least one modifiable TP-PCB must be defined for default use of hardcopy and sending messages. The value of the WRKPCBS keyword subparameter in the current environment table must be less than or equal to the number of PCBs minus 1 to avoid a Natural initialization error.

3. After creating the required APPLCTNs for the BMP and MPP environments, generate the PSB, DBD and ACB.
4. After generating the ACB, activate the new definitions by issuing the following commands :

```
/MODIFY PREP ACBLIB
/MODIFY COMMIT
```

### Step 3: Create the BMP and MPP Regions

(Job I200, Steps 2500, 2504)

- Create the BMP region (Step 2500) according to the `BMPJOB` sample member.
- Create the MPP region (Step 2504) according to the `MPPJOB` sample member.

### Step 4: Create the PRELOAD List

- Update the `PRELOAD` list by using a `PRELOAD` member `DFSMPLE xx` with the names of the following modules:

the nucleus,  
the interface module,  
the front-end, and  
the Adabas link module.

#### Example for MPP:

```
NATvrsSH,NIIvrsIF,NIIvrsFR,ADALNI
```

#### Example for BMP:

```
NATvrsSH,NIIvrsIF,NIIvrsBM,ADALNK
```

- If alias names are used for any members in the `PRELOAD` list, these names should be added to the `PRELOAD` list as well. Failure to do so leads to performance degradation.

### Special Considerations:

- The region size must be large enough to hold the nucleus, the interface module, the front-end, the Natural thread and about 20 KB of working storage below the line.
- Include the load libraries used by the Natural IMS TM Interface.
- Include the DD statement for the roll file created in [Step 1: Allocate and Format the Roll Files](#):

```
//ROLLFn DD DSN=...DISP=SHR
```

where *n* is a value from 1 - 5.

- Include the DD statement for `NATRJE`:

```
//NIIRJEDD DD SYSOUT=(X,INTRDR)
```

- In the JCL of the MPP region, add the SYSTPCD DD statement if the Natural Development Server or Natural Web I/O Interface server is used. See IBM's *z/OS V1Rx.0 Communications Server IP Configuration Guide, Chapter 1.5.2, Configuring TCPIP.DATA*.

## Installation Verification

You can verify the successful installation of the Natural IMS TM Interface by following the instructions in this section.

- [Start Batch Natural](#)
- [Start and Test Online Natural](#)

### Start Batch Natural

1. From an IMS TM session, start a BMP with the following IMS TM command:

```
/STA REG BMPJOB
```

2. Check the output. The output results from the Natural system command TECH described in the *System Commands* documentation. Verify the output in your environment.

### Start and Test Online Natural

1. From an IMS TM session, issue the following IMS TM commands:

```
/STA REG MPPJOB
/STA TRAN NATvrs
/STA PROG NIIvrsFR
```

The Natural IMS TM Interface is available.

2. From an IMS TM session, type in the following transaction name:

```
NATvrs
```

A Natural session is started.

3. Proceed with the steps described in the section [Test Online Natural](#).



# X

## Installing Natural TSO Interface on z/OS

---



# 11

## Installing Natural TSO Interface on z/OS

---

■ Prerequisites .....	144
■ Installation Medium .....	144
■ Installation Procedure .....	145
■ Installation Verification .....	147

This document describes the steps for installing the Natural TSO Interface (product code NTI) on z/OS.

### Related Topics:

For information on how to operate Natural in a TSO environment, see *Using Natural with TP Monitors* and *Natural under TSO* in the *TP Monitor Interfaces* documentation and the following topics:

- *General Information about the Natural TSO Interface*
- *Data Sets Used by Natural under TSO*

### Notation *vrs* or *vr*:

When used in this document, the notation *vrs* or *vr* represents the relevant product version (see also Version in the *Glossary*).

## Prerequisites

---

See [General Prerequisites and System Support](#) in the section *Overview of the Installation Process*.

## Installation Medium

---

The [installation medium](#) contains the following data set required for product installation:

Data Set Name	Contents
NTI $vrs$ .LOAD	Load modules

Copy the data set into your environment as described in [Copying Data Sets to a z/OS Disk](#) in the section *Installing Natural*.

### Sample Jobs

Sample installation jobs are contained in the NAT $vrs$ .JOBS data set and are prefixed with the product code. The data set is provided on the installation medium supplied for base Natural.



## Installation Procedure

---

Be sure to read *Installation Process and Major Natural Features* before you start the installation procedure.

### Note for LE Options:

If you want Natural to run in the IBM Language Environment (LE), set the **System Maintenance Aid (SMA)** parameter NAT-LE to Y (Yes). The default setting is N (No). Additionally, if you want to modify the LE options in the NATLEOPT source module or if you use non-Natural programs running in 24-bit mode, set the appropriate SMA parameter as described in *Build the Natural-Specific IBM Language Environment Options* in *Installing Natural*.

The installation procedure consists of the steps below.

- Step 1: Create the CLIST for the Natural TSO Interface
- Step 2: Create ADARUN Cards
- Step 3: Build the Natural Parameter Module
- Step 4: Link the Nucleus
- Step 5: Make the Adabas Interface Available

### Step 1: Create the CLIST for the Natural TSO Interface

(Job I070, Step 2400)

- Create a TSO CLIST for Natural.

This CLIST is used later to invoke Natural under TSO. Note that the CLIST supplied with this step is only a basic example which you can adapt to your requirements and to your TSO environment.

### Step 2: Create ADARUN Cards

(Job I070, Step 2410)

- Create ADARUN cards in a source library.

This is required by the CLIST created in *Step 1: Create the CLIST for the Natural TSO Interface*.

### Step 3: Build the Natural Parameter Module

(Job I080, Steps 0010, 0015)

#### 1. Modify the Natural parameter module for TSO.

- Configure the TSO batch interface:

Modify the settings of the parameters supplied with the `NTTSOP` macro in the Natural parameter module to meet your requirements. For descriptions of these parameters, see the corresponding dynamic profile parameter `TSOP` in the *Parameter Reference* documentation.

- Modify the following parameters:

```
FNAT=(database-id,file-number)
FUSER=(database-id,file-number)
```

where *database-id* and *file-number* are the values you specified when loading the system files during the [Installation Procedure](#) for base Natural.

- Global buffer pool:

If you want to use a global buffer pool, specify the `NTBPI` macro.

- For all other parameters:

You can generally use the default values. Modify only the values of those parameters whose default values do not suit your requirements. For descriptions of the individual parameters contained in the parameter module, refer to the *Parameter Reference* documentation.

For dynamic assignment of profile parameters, see also the `CMPRMIN` data set described in the section *Natural in Batch Mode* in the *Operations* documentation.

#### 2. Assemble and link the Natural parameter module.

### Step 4: Link the Nucleus

(Job I080, Step 0020)

- Link the [environment-dependent nucleus](#).

## Step 5: Make the Adabas Interface Available

Skip this step if the Adabas link module is available in your LPA.

- Perform either of the following steps:
  - Include the Adabas load library in the steplib of your TSO user procedures.
  - Copy the modules listed in the section referring to installation with TSO of the appropriate Adabas installation documentation to a library of your TSO user steplib.

## Installation Verification

---

You can verify the successful installation of the Natural TSO Interface by performing the following steps:

1. Start a TSO session in ISPF mode.
2. Invoke the CLIST you created in [Step 1: Create the CLIST for the Natural TSO Interface](#).

Example:

```
TSO EX 'SAGLIB.SMASRCE(NTICLIST)'
```

3. Proceed with the steps described in the section [Test Online Natural](#).



# XI

## Installing Natural for Db2 on z/OS

---



# 12

## Installing Natural for Db2 on z/OS

---

■ Prerequisites .....	152
■ Installation Medium .....	152
■ Installation Procedure .....	153
■ Common Installation Steps .....	153
■ Installation Steps Specific to CICS .....	160
■ Installation Steps Specific to Com-plete .....	164
■ Installation Steps Specific to IMS TM .....	164
■ Installation Steps Specific to TSO .....	166
■ Installation Verification .....	167
■ Natural Parameter Modifications for Natural for Db2 .....	170
■ Special Requirements for Natural Tools for Db2 .....	174
■ Natural for Db2 Server Stub .....	176

This document describes the steps for installing Natural for Db2 (product code NDB) on z/OS.

### Related Topics:

For information on how to operate Natural in a Db2 environment, see *Natural for Db2* in the *Database Management System Interfaces* documentation.

### Notation *vrs* or *vr*:

When used in this document, the notation *vrs* or *vr* represents the relevant product version (see also Version in the *Glossary*).

## Prerequisites

---

The following software must be installed before you can install Natural for Db2:

- **Natural** Version 9.2.3 (or higher); you cannot install Natural and Natural for Db2 at the same time.
- **Software AG Editor**

See also *General Prerequisites and System Support* in the section *Overview of the Installation Process*.

## Installation Medium

---

The **installation medium** contains the following data sets required for product installation:

Data Set Name	Contents
NDB <i>vrs</i> .LOAD	Load modules
NDB <i>vrs</i> .SRCE	Source modules and macros
NDB <i>vrs</i> .JOBS	Sample installation jobs
NDB <i>vrs</i> .INPL	Natural objects including error messages

Copy the data sets into your environment as described in *Copying Data Sets to a z/OS Disk* in the section *Installing Natural*.



## Installation Procedure

---

Be sure to read *Installation Process and Major Natural Features* before you start the installation procedure.

The installation procedure comprises the following:

- [Common Installation Steps](#)
- [Installation Steps Specific to CICS](#)
- [Installation Steps Specific to Com-plete](#)
- [Installation Steps Specific to IMS TM](#)
- [Installation Steps Specific to TSO](#)

## Common Installation Steps

---

This section described the installation steps that apply to all Natural environments where Natural for Db2 can be installed. The steps additionally required for a particular TP monitor are described in the following sections.

- [Db2 Upgrade Considerations](#)
- [Step 1: Install the Natural for Db2 License File](#)
- [Step 2: Allocate the DBRM Library for Use with Natural for Db2](#)
- [Step 3: Generate the Natural for Db2 I/O Module NDBIOMO](#)
- [Step 4: Build NDBIOMO](#)
- [Step 5: Bind the DBRM NDBIOMO into a Package](#)
- [Step 6: Create the Db2 Plan for Use with Natural for Db2](#)
- [Step 7: Link-Edit NATGWDB2](#)
- [Step 8: Build the Natural Parameter Module](#)
- [Step 9: Link the Nucleus](#)
- [Step 10: Load New Objects](#)
- [Step 11: Create the Natural for Db2 Server Stub](#)

- [Step 12: Bind the DBRM ROUTINEN into a Package](#)

## Db2 Upgrade Considerations

If you upgrade to a newer Db2 version, you need not upgrade your current Natural for Db2 installation.

If you upgrade to a newer Db2 version and also want to upgrade to a newer Natural for Db2 version, consider the following:

- Do not recreate the `NDBIOM0` module with the Db2 version parameter of the new Db2 version, unless the new-function mode is enabled in the new Db2 version. In this case, skip the Steps 2 to 5.
- If the new-function mode is enabled in the new Db2 version, you only need to create a new `NDBIOM0` module if you want to use the new Db2 statements added to the `NDBIOM0` module for the new Db2 version. Otherwise, you can also skip the Steps 2 to 5.

## Step 1: Install the Natural for Db2 License File

In addition to the Natural product license file, a license file is required and must be installed for each environment in which Natural for Db2 (NDB) runs. For license file `NDBvrs.LICS`, see [Step 2: Prepare, Convert, Assemble and Link the License File](#) in section *Installing Natural on z/OS*.

Natural for Db2 is not enabled unless you install a valid Natural for Db2 license file. Trying to activate the NDB without a valid license file results in warnings or errors at session start.

## Step 2: Allocate the DBRM Library for Use with Natural for Db2

- Allocate a PDS as DBRM (database request module) library. The size of this data set and the number of directory entries depend on the particular site (5 tracks and 20 directory blocks must be adequate for most environments). The PDS must have a fixed-block record format and a record length of 80.

Any standard data set name can be used for this DBRM library; however, this installation procedure assumes that the name `SAGLIB.DB2DBRM` is used.

### Step 3: Generate the Natural for Db2 I/O Module NDBIOMO

(Job I055, Step 1600)

1. Execute the standard Natural batch job provided with this step to generate the assembly source for the NDBIOMO module from the NDBIOTM member. This batch job invokes the Natural program NDBGENI, which is loaded with the Natural **INPL utility** during the installation of base Natural.

NDBIOMO provides dynamic access to Db2 and contains all necessary EXEC SQL statements. In addition, it contains some special SQL statements which cannot be executed in dynamic mode. See also *I/O Module NDBIOMO for Dynamic SQL Statement Execution* in the *Database Management System Interfaces* documentation.

2. Modify the following two positional parameters contained in NDBGENI to meet your requirements.
  - The first parameter restricts the use of SQL statements to those supported by a particular Db2 version. Set this parameter to one of the following values:
    - DB2V11 for Db2 Version 11 in new function mode, or any higher Db2 version.
    - DB2V13 for Db2 Version 13 in new function mode, or any higher Db2 version.
  - The second parameter specifies the maximum number of parallel dynamic prepared Db2 statements.
3. Check the output report created by this job for successful job completion. In addition, a condition code of 0 indicates normal completion.

### Step 4: Build NDBIOMO

(Job I055, Step 1610)

- Precompile, assemble and link the Natural for Db2 I/O module NDBIOMO.

The link-edit step receives a condition code of 4 because of unresolved references for DSNHLI. This is normal and can be ignored.

### Step 5: Bind the DBRM NDBIOMO into a Package

(Job I057, Step 1620)

- Bind the DBRM NDBIOMO into a package.

**Step 6: Create the Db2 Plan for Use with Natural for Db2**

(Job I057, Step 1631 - 1634)

- Create the DB2 plans to be used by Natural for DB2 in batch mode, TSO and under CICS.

**Step 7: Link-Edit NATGWDB2**

(Job I055, Step 1680)

- Link-edit the Natural for Db2 load module NATGWDB2.

**Step 8: Build the Natural Parameter Module**

(Job I060, Steps 0010, 0015)

Build the Natural parameter module for batch mode. The macros and parameters mentioned in this section are described in the *Parameter Reference* documentation.

1. Modify the settings of the parameters supplied with the Natural parameter module as required:
  - Set the parameters supplied with the NTOSP macro to configure the z/OS batch interface. For descriptions of these parameters, see the corresponding dynamic profile parameter OSP.
  - Set the parameters specific to Natural for Db2 supplied with the NTDB2 macro. For descriptions of these parameters, see the corresponding dynamic profile parameter DB2.

See also [Natural Parameter Modifications for Natural for Db2](#).

2. Assemble and link the Natural parameter module.

**Step 9: Link the Nucleus**

(Jobs I060, I080)

1. Link the [environment-dependent nucleus](#):

Add the following INCLUDE statements and corresponding DD statements to the link instructions for the linkage editor:

INCLUDE SMALIB( <i>nat-parm-module</i> )	Natural parameter module, where <i>nat-parm-module</i> is the module name used in <a href="#">Step 7: Build the Natural Parameter Module</a>

INCLUDE DSNLIB(DSNTIAR)	SQL error message module
INCLUDE SMALIB(NDBIOMO)	Natural for Db2 I/O module created in <a href="#">Step 3: Build NDBIOMO</a>
INCLUDE xxxxxxxx(yyyyyyyyyy)	Environment-dependent Db2 interface (see below)

Depending on your environment, specify the appropriate Db2 interface *yyyyyyyyyy* from library *xxxxxxx* in your INCLUDE statement as shown in the following table:

Interface	Library	Environment
DSNALI	DSNLIB	Under TSO and in batch mode without running under the control of the DSN command processor, that is, with CAF (Call Attachment Facility)
DSNRLI	DSNLIB	WLM (Workload Manager) stored procedure address space and Natural Development Server (recommended)  This can also be used in TSO and batch environments.
DSNELI	DSNLIB	Under TSO and in batch mode when running under the control of the DSN command processor
DSNCLI	DFHLIB	Under CICS
DSNULI	DSNLIB	Under all environments except Com-plete
DFSLI000	IMSLIB	Under IMS TM (MPP and BMP) and in batch mode using the Db2 batch support (DSNMTV01)
NDBCOM	NDBLIB	Under Com-plete

## 2. Link the [environment-independent nucleus](#):

Add the following INCLUDE statement and corresponding DD statement to the link instructions for the Natural for Db2 load module:

```
INCLUDE SMALIB(NATGWDB2)
```

## Alternatives

Instead of linking both the environment-dependent nucleus and environment-independent nucleus as described above, you can use one of the following methods:

### 1. Create a single environment-dependent nucleus:

Link all the environment-dependent modules together with all environment-independent modules, thus creating one single, environment-dependent nucleus.

### 2. Separate the NATGWDB2 module (not linked to the environment-independent nucleus):

Run the NATGWDB2 module as a separate module by using the Natural Resolve STATIC Addresses feature (RCA).

You can modify the name of the NATGWDB2 module linked in [Step 6](#). However, if you use a name different from NATGWDB2, this name must be specified as an alias name in the NTALIAS macro (see the *Parameter Reference* documentation) in the Natural parameter module.

3. Create an alternative Natural parameter module containing all the environment-dependent and environment-independent Natural for Db2 and Db2 for z/OS modules:

Link the alternative Natural parameter module together with all Natural for Db2 modules (NATGWDB2, NDBIOM0) and all Db2 for z/OS modules (DSNTIAR and a Db2 interface module) as Natural for Db2 nucleus NDBNUC<sub>xx</sub> with ENTRY NATPARM.

You can deploy the Natural for Db2 nucleus NDBNUC<sub>xx</sub> by specifying PARM=NDBNUC<sub>xx</sub> as a dynamic parameter.

This method provides the option to execute a new Natural for Db2 Version *xx* in an existing Natural environment with an older Natural for Db2 version.

A Natural for Db2 nucleus with a linked Db2 interface module DSNULI supported by Db2 for z/OS Version 12 can operate in all environments except Com-plete.

The following applies when linking a separate NATGWDB2 module (Alternative 2 above) or a separate Natural parameter module (Alternative 3 above):

TP Monitor	Requirement
CICS	<p>The resulting module must be defined as PPT entry or RDO.</p> <p>PPT entry:</p> <pre>DFHPPT TYPE=ENTRY, PROGRAM=module-name, PGMLANG=ASSEMBLER</pre>
Com-plete	The resulting module must be defined as RESIDENTPAGE or reside in the LPA/(E)LPA.

## Step 10: Load New Objects

(Job I061, Step 1610)

Before executing this step, change the CMWKF01 DD statement to point to the NDB<sub>vrs</sub>.INPL data set.

- Load the Natural objects specific to Natural for Db2 from the NDB<sub>vrs</sub>.INPL data set into the Natural system file by using the Natural **INPL utility**. The Natural objects are loaded into the Natural system libraries SYSDDM, SYSTEM and SYSDB2 in the FNAT system file.



**Important:** Ensure that your newly created SYSDB2 library contains all necessary Predict interface programs which are loaded into SYSDB2 when installing Predict (see the relevant *Predict* documentation).

## Step 11: Create the Natural for Db2 Server Stub

(Job I070, Steps 1604, 1606, 1608, 1610)

1. Create server stubs to execute Natural stored procedures and Natural user-defined functions. Natural for Db2 server stubs are interface modules between the Db2 database system and the Natural server. The server stub must be installed in order to execute Natural stored procedures and Natural user-defined functions.

There are two types of server stub:

### Natural for Db2 server stub (module NDB<sub>vr</sub>SRV, Steps 1604 and 1606)

The server stub is used to execute Natural stored procedures and Natural user-defined functions.

The IBM Language Environment (LE) runtime modules required must be linked to the Natural for Db2 server stub module. Use the CALL option of the linkage editor and assign the LE runtime library as SYSLIB.

### Natural for Db2 start server stub (module NDB<sub>vr</sub>STR, Steps 1608 and 1610)

The start server stub is used to start the Natural server environment(s) explicitly.

The IBM LE runtime modules required must be linked to the Natural for Db2 start server stub module. Use the CALL option of the linkage editor and assign the LE runtime library as SYSLIB. Additionally, include the modules NDBSTRP (delivered with Natural for Db2) and NATCONFIG (delivered with Natural) from NDB<sub>vr</sub>s.LOAD and NAT<sub>vr</sub>s.LOAD.

2. Natural for Db2 server stubs are generated from the NDBSTUB macro. You can generally use the default values for all parameters. Modify only the values of the parameters whose default values do not suit your requirements. The individual parameters are described in the section [Natural for Db2 Server Stub](#).
3. Place the resulting load modules into a steplib library of the JCL used to execute the Db2 stored procedure address space.
4. For Db2 UDB, each Natural stored procedure or Natural user-defined function must be defined by a Db2 CREATE PROCEDURE or Db2 CREATE FUNCTION statement, where the name of the generated Natural for Db2 server stub module NDB<sub>vr</sub>SRV is specified as EXTERNAL NAME.

## Step 12: Bind the DBRM ROUTINEN into a Package

(Job I057, Step 1640)

- Bind the DBRM `ROUTINEN` into a package.

The DBRM `ROUTINEN` is contained in the collection `SAGNDBROUTINENPACK` and delivered with Natural for DB2. Natural for DB2 needs this collection to access the DB2 catalog and retrieve the parameter descriptions of Natural stored procedures and Natural user-defined functions.

## Installation Steps Specific to CICS

---

This section describes the additional steps required to install Natural for Db2 in a CICS environment.

Ensure that your Natural/CICS thread size is large enough to contain the `DB2SIZE`; if you use the Natural Tools for Db2 (described in the *Database Management System Interfaces* documentation), additional storage of 8 KB is required.

This section covers the following topics:

- [Using Plan Selection by CICS RCT Entry Threads](#)
- [Using Plan Selection by Dynamic Plan Exit](#)
- [Installing the Natural File Server with VSAM on CICS](#)

### Using Plan Selection by CICS RCT Entry Threads

(Job I005)

If you want fixed assignment of your transaction code to the Db2 plan, add an additional entry to your CICS RCT, or define a `DB2Entry` with RDO by performing one of the following alternative steps:

- Modify your RCT:

```
DSNRCT TYPE=ENTRY,PLAN=plan-name,TXID=(transaction-id)
```

where *plan-name* must be the same as the name used to create the Db2 plan for Natural for Db2: see [Common Installation Steps](#).

Assemble and link the RCT.

- Define a `DB2Entry` with RDO:



```

DEFINE DB2ENTRY
  OVERTYPE TO MODIFY                                CICS RELEASE = nnnn
  CEDA  DEfine DB2Entry(                               )
    DB2Entry      : DB2ENTR
    Group         : NCI
    Description    :
  THREAD SELECTION ATTRIBUTES
    TRansid       : transaction-id
  THREAD OPERATION ATTRIBUTES
    ACcountrec    : None                          None ! TXid ! TAsk ! Uow
    AUTHId        :
    AUTHType      : Userid                        Userid ! Opid ! Group ! Sign ! TTerm
                                                ! TX
    DRollback     : Yes                          Yes ! No
    PLAN          : plan-name
    PLANExitname  :
    PRIority      : High                        High ! Equal ! Low
    PROtectnum    : 0005                        0-2000
    THREADLimit   : 0005                        0-2000
    THREADWait    : Pool                        Pool ! Yes ! No

```

*plan-name* must be the same as the name used to create the Db2 plan for Natural for Db2: see [Common Installation Steps](#).

For explanations of the parameters, refer to the relevant CICS literature from IBM.

### Using Plan Selection by Dynamic Plan Exit

If you want to perform plan selection by using the dynamic plan exit, perform the following steps:

- [Step 1: Build the CICS Dynamic Plan Selection Exit Module NDBUEXT](#)
- [Step 2: Link the CICS Dynamic Plan Selection Exit Module NDBUEXT](#)
- [Step 3: Define a DB2Entry](#)

#### Step 1: Build the CICS Dynamic Plan Selection Exit Module NDBUEXT

(Job I070, Step 1630)

1. If you want to specify a default plan name, modify the source module NDBUEXT.

The sample exit routine NDBUEXT can be modified to use a default plan name if none has been specified prior to the first SQL call. Review the source code in the NDBUEXT module for details about specifying a default plan name.

Ensure that all NDBUEXT modules used in Natural for Db2 versions prior to Version 8.3 are replaced by the new NDBUEXT module built in this step. The new NDBUEXT module still supports CICS TS queue names used in previous versions of Natural for Db2.

2. Precompile, assemble and link NDBUEXT for CICS.

This step receives a condition code of 4 because of an unresolved external reference for DFHEAIO and DFHEI1. This is normal and can be ignored.

## Step 2: Link the CICS Dynamic Plan Selection Exit Module NDBUEXT

(Job I075, Step 1640)

- Link the module NDBUEXT resulting from the previous step to the CICS load library and define it via a corresponding PPT entry or RDO.

PPT entry:

```
DFHPPT TYPE=ENTRY,PROGRAM=NDBUEXT,PGMLANG=ASSEMBLER
```

For explanations of the parameters, refer to the relevant CICS literature from IBM.

## Step 3: Define a DB2Entry

Perform the following step:

- Define a DB2Entry with RDO:

```
DEFINE DB2ENTRY
OVERTYPE TO MODIFY                                CICS RELEASE = nnnn
CEDA  DEfine DB2Entry(                             )
  DB2Entry      : DB2ENTR
  Group         : NCI
  Description    :
THREAD SELECTION ATTRIBUTES
  TRansid       : transaction-id
THREAD OPERATION ATTRIBUTES
  ACcountrec    : None                          None ! TXid ! TAsk ! Uow
  AUTHId        :
  AUTHType      : Userid                        Userid ! Opid ! Group ! Sign ! TTerm
                                                ! TX
  DRollback     : Yes                          Yes ! No
  PLAN          :
  PLANExitname  : NDBUEXT
  PRIority      : High                          High ! Equal ! Low
  PROtectnum    : 0005                          0-2000
  THREADLimit   : 0005                          0-2000
  THREADWait    : Pool                          Pool ! Yes ! No
```

The parameter PLANExitname must specify the same program as the NAME statement of [Step 2: Link the CICS Dynamic Plan Selection Exit Module NDBUEXT](#).

Alternatively or additionally, you can specify the plan exit program NDBUEXT with the PLANExitname parameter of POOL THREAD ATTRIBUTES of the DB2Conn resource definition of CICS TS.

## Installing the Natural File Server with VSAM on CICS

If you want to use the Natural file server with VSAM, perform the following additional installation steps:

- [Step 1: Define a VSAM Data Set for the Natural File Server](#)
- [Step 2: Format the Natural File Server Data Set](#)
- [Step 3: Build the CICS Table](#)
- [Step 4: Restart CICS](#)

### Step 1: Define a VSAM Data Set for the Natural File Server

(Job I008, Step 1610)

- Specify the size and the name of the VSAM RRDS that is to be used as the Natural file server (see also *Preparations for Using the File Server in the Database Management System Interfaces* documentation).

### Step 2: Format the Natural File Server Data Set

(Job I075, Step 1610)

- Specify the five input parameters required to format the Natural file server data set (see also *Preparations for Using the File Server in the Database Management System Interfaces* documentation).

### Step 3: Build the CICS Table

1. Add an additional FCT entry required for the Natural file server and the Db2 components of Natural according to the following example:

```
CMFSERV  DFHFCT  TYPE=DATASET,                                *
          ACCMETH=VSAM ,                                       *
          BUFND=5,                                             *
          BUFNI=4,                                             *
          DATASET=CMFSERV,                                     *
          DISP=SHR,                                           *
          DSN= SAGLIB.NCIDB2.SERVER,                          *
          FILSTAT=(ENABLED,CLOSED),                          *
          JID=NO,                                             *
          LOG=NO,                                             *
          LSRPOOL=NONE, 1-8 ONLY FOR XA; NONE                 *
          RECFORM=(FIXED,BLOCKED),                           *
          RSL=PUBLIC,                                         *
          SERVREQ=(ADD,UPDATE,DELETE,BROWSE),                 *
          STRNO=4
```

2. Assemble and link the CICS table.

#### Step 4: Restart CICS

- Restarting CICS is required, because of the additional FCT entry specified in the previous step.

## Installation Steps Specific to Com-plete

---

Under Com-plete, the installation procedure of Natural for Db2 continues with the adaptation of your Com-plete environment.

Ensure that the changes required for Db2 have been applied to your Com-plete environment (see the relevant section in the *Com-plete* documentation).

## Installation Steps Specific to IMS TM

---

This section describes the additional steps required to install Natural for Db2 in an IMS TM environment.

Ensure that the thread of your Natural IMS TM Interface is large enough to contain the DB2SIZE; if you use the Natural Tools for Db2 (described in the *Database Management System Interfaces* documentation), additional storage of 8 KB is required.

- [Binding Db2 Plans](#)
- [Using Plan Selection with IMS TM Resource Translation Table](#)
- [Installing the Natural File Server with VSAM in an IMS TM Environment](#)

### Binding Db2 Plans

(Job I055, Steps 1631, 1632, 1633, 1634 for IMS MPP conversational, IMS BMP, IMS MPP non-conversational, OBMP)

- Build the Db2 plan to be used by Natural for Db2 in all IMS TM environments supported by Natural.

## Using Plan Selection with IMS TM Resource Translation Table

If the name (or any ALIAS) of your **environment-dependent nucleus** does not match the name of your Db2 plan or if you want to use the same Db2 plan for all IMS TM environments, you must use a Resource Translation Table (RTT).

- Modify, assemble and link the IMS TM RTT:

Add an additional DSNMAPN macro to your RTT as follows (for any other parameters, refer to the relevant Db2 literature from IBM):

DSNMAPN macro:

```
DSNMAPN APN=load-module,PLAN=plan-name
```

where *load-module* is the environment-dependent nucleus (that is, the IMS TM application program) and *plan-name* is the same as the one used in [Binding Db2 Plans](#).

## Installing the Natural File Server with VSAM in an IMS TM Environment

Be aware that database loops cannot be continued across terminal I/Os without using the Natural file server.

If you want to use the Natural file server with VSAM, perform the following additional installation steps:

- [Step 1: Define the VSAM Data Set for the Natural File Server](#)
- [Step 2: Format the Natural File Server Data Set](#)
- [Step 3: Update the JCL for the MPP Region](#)
- [Step 4: Restart the MPP Region Used by Your Natural IMS TM Interface](#)

### Step 1: Define the VSAM Data Set for the Natural File Server

(Job I008, Step 1600)

- Specify the size and the name of the VSAM RRDS that is to be used as the Natural file server (see also *Preparations for Using the File Server* in the *Database Management System Interfaces* documentation).

## Step 2: Format the Natural File Server Data Set

(Job I075, Step 1600)

- Specify the five input parameters required to format the Natural file server data set (see also *Preparations for Using the File Server* in the *Database Management System Interfaces* documentation).

## Step 3: Update the JCL for the MPP Region

- Include the DD statement `CMFSERV` to define the Natural file server data set.
- Increase the `REGION` parameter if necessary.

## Step 4: Restart the MPP Region Used by Your Natural IMS TM Interface

- Restart your MPP region, because of the additional DD statement.

# Installation Steps Specific to TSO

---

This section describes the additional installation steps required in a TSO environment if you want to use the Natural file server with VSAM:

- [Step 1: Modify NDBFSRV in NTTSOP](#)
- [Step 2: Define the VSAM Data Set for the Natural File Server](#)
- [Step 3: Format the Natural File Server Data Set](#)

## Step 1: Modify NDBFSRV in NTTSOP

- Set the keyword subparameter `NDBFSRV` (see the *Parameter Reference* documentation) in the `NTTSOP` macro to `ON` and reassemble and relink your Natural TSO Interface.

## Step 2: Define the VSAM Data Set for the Natural File Server

(Job I008, Step 1620)

- Specify the size and the name of the VSAM RRDS that is to be used as the Natural file server (see also *Preparations for Using the File Server* in the *Database Management System Interfaces* documentation).

### Step 3: Format the Natural File Server Data Set

(Job I075, Step 1620)

- Specify the five input parameters required to format the Natural file server data set (see also *Preparations for Using the File Server in the Database Management System Interfaces* documentation).

## Installation Verification

This section provides example batch jobs and online methods for verifying the successful installation of Natural for Db2.

- [Test Batch Natural for Db2 under CAF - Job NDBBATCA](#)
- [Test Batch Natural for Db2 under DSN - Job NDBBATTB](#)
- [Test DSNMTV01 - Job NDBMTV01](#)
- [Test TSO Natural for Db2 under CAF - CLIST NDBCAF](#)
- [Test TSO Natural for Db2 under DSN - CLIST NDBTSO](#)
- [Online Verification Methods](#)

### Test Batch Natural for Db2 under CAF - Job NDBBATCA

NDBBATCA contains sample JCL to test Natural for Db2 in batch mode by using the CAF (Call Attachment Facility) interface.

Modify the sample JCL to meet your requirements.

Before the first SQL call, you must call NATPLAN to explicitly allocate the plan. The plan name must be the same as the name used in [Step 5: Create the Db2 Plan for Use with Natural for Db2](#). NATPLAN can be edited to specify the appropriate Db2 subsystem ID.

### Test Batch Natural for Db2 under DSN - Job NDBBATTB

NDBBATTB contains sample JCL to test Natural for Db2 in batch mode by using the DSN command processor. Modify the sample JCL to meet your requirements.

The plan name must be the same as the name used in [Step 5: Create the Db2 Plan for Use with Natural for Db2](#). For explanations of the DSN and RUN commands, refer to the relevant IBM literature for Db2/TSO and batch users.

## Test DSNMTV01 - Job NDBMTV01

NDBMTV01 contains a sample JCL to execute Natural by using the Db2 batch support.

Modify the sample JCL to meet your requirements.

The plan name must be the same as the name used in [Step 5: Create the Db2 Plan for Use with Natural for Db2](#).

## Test TSO Natural for Db2 under CAF - CLIST NDBCAF

You can perform the following steps to test the TSO installation of Natural for Db2 under CAF (Call Attachment Facility):

### 1. Adapt CLIST NDBCAF

(Job I070, Step 240C)

Change the library and program names in the CLIST NDBCAF to meet your requirements. If you do not use the Natural file server, remove the ALLOC and FREE statements for CMFSERV.

### 2. Invoke Natural

Invoke Natural by executing the CLIST adapted in the [previous step](#). Ensure that Db2 tables can be accessed and that plan switching can be performed.

Before the first SQL call, you must call NATPLAN to explicitly allocate the plan. The plan name must be the same as the name used in [Step 5: Create the Db2 Plan for Use with Natural for Db2](#). NATPLAN can be edited to specify the appropriate Db2 subsystem ID.

## Test TSO Natural for Db2 under DSN - CLIST NDBTSO

You can perform the following steps to test the TSO installation of Natural for Db2 under DSN:

### 1. Adapt CLIST NDBTSO

(Job I070, Step 240B)

Change the subsystem ID and the library, plan and program names in the CLIST NDBTSO to meet your requirements. If you do not use the Natural file server, remove the ALLOC and FREE statements for CMFSERV.

### 2. Invoke Natural

Invoke Natural by executing the CLIST created in the previous step. Ensure that Db2 tables can be accessed. The plan name must be the same as the name used in [Binding Db2 Plans](#). For explanations of the DSN and RUN commands, refer to the relevant IBM literature for Db2/TSO and batch users.



## Online Verification Methods

You can verify the successful installation of Natural for Db2 online by using either **SQL Services** or **DEM2** example programs:

- [Using SQL Services](#)
- [Using DEM2\\* Example Programs](#)

### Using SQL Services

You can verify the successful installation of Natural for Db2 by using the **SQL Services (NDB/NSQ)** function (described in the *Database Management System Interfaces* documentation) of the Natural SYSDDM utility:

1. Invoke Natural.
2. Invoke the SYSDDM utility.
3. In the SYSDDM main menu, enter function code **B** to invoke **SQL Services (NDB/NSQ)**.
4. Enter function code **S** to select all Db2 tables.

The communication between Natural and Db2 works if all existing Db2 tables are displayed.

For one of the tables, generate a Natural DDM as described in the section *Generate DDM from an SQL Table* in the *Database Management System Interfaces* documentation.

5. After you have generated a DDM, access the corresponding Db2 table with a simple Natural program as indicated in the following example:

```
DEFINE DATA
01 view-name OF ddm-name
02 field
...
END-DEFINE
FIND view-name WITH field = value
  DISPLAY field
END-FIND
END
```

where:

*view-name* is a view of the DDM *ddm-name*,  
*field* is a DDM field,  
*value* is the search value to be used for the field.

If you receive the message NAT3700, enter the Natural system command **SQLERR** to display the corresponding SQL return code. **SQLERR** is described in the *System Commands* documentation.

## Using DEM2\* Example Programs

You can also use the DEM2\* example programs in the Natural system library SYSDB2 provided on the installation medium to verify and test your installation.

You can create a Db2 table with DEM2CREA, and then create the corresponding DDM by using the Natural SYSDDM utility. You can store data in the created table with DEM2STOR, and retrieve data from the table with DEM2FIND or DEM2SEL. You can also drop the table with the DEM2DROP program.

## Natural Parameter Modifications for Natural for Db2

---

This section covers the following topics:

- [Natural Profile Parameter Settings](#)
- [Performance Considerations for the DB2SIZE Parameter](#)

### Natural Profile Parameter Settings

Adapt the Natural parameter module to meet your requirements. The Natural parameters mentioned in this section are described in the *Parameter Reference* documentation.

#### DB2SIZE Parameter

Specify the profile parameter DB2SIZE:

```
DB2SIZE=nn
```

DB2SIZE indicates the size of the work area used for processing SQL requests. It must be set to at least 6 KB.

The setting of DB2SIZE also depends on whether you use the Natural file server or not. If the Natural file server is not used, the setting can be calculated according to the following formula:

```
((1064 + n1 * 48 + n2 * 120) + 1023) / 1024 KB
```

If the Natural file server is used, the setting can be calculated according to the following formula:

```
((1160 + n1 * 48 + n2 * 160 + n3 * 8) + 1023) / 1024 KB
```

The variables *n1*, *n2* and *n3* correspond to the following:

<i>n1</i>	Number of statements for dynamic access as specified as the second parameter in <a href="#">Step 2: Generate the Natural for Db2 I/O Module NDBIOMO</a>
<i>n2</i>	Maximum number of nested database loops as specified with the MAXLOOP parameter in the NTDB2 macro
<i>n3</i>	Maximum number of Natural file server blocks to be allocated per user specified as the fifth parameter in <a href="#">Job I075, Step 1620</a> , or the EBPMAX parameter in the NTDB2 macro, if you decided to use the Software AG Editor buffer pool as the Natural file server

The DB2SIZE parameter can also be specified dynamically at the start of a Natural session.



**Important:** Ensure that you have also added the Natural parameters required for the Software AG Editor; see the relevant installation description in the section [Installing Software AG Editor](#).

### NTDB Macro

Specify database type Db2 and a list of DBIDs (database IDs) in the NTDB macro. All Natural DDMs that refer to a Db2 table must be cataloged with a DBID from this list. DBID can be any number from 1 to 65535. For most environments, one DBID (usually 250) is sufficient for database type Db2.

The Db2 DBIDs can also be specified dynamically at the start of a Natural session by using the DB profile parameter.



**Important:** Ensure that all Db2 DDMs used when cataloging a given program have a valid Db2 DBID. Also ensure that the DBIDs selected in the NTDB macro for Db2 do not conflict with DBIDs selected for other database systems.

The DBID for SQL/DS used when cataloging a Natural program does not have to be in the NTDB list of DBIDs used when executing this program. Therefore, when executing existing Natural programs, DBID 250 is not mandatory. Two sample NTDB macros follow:

```
NTDB DB2,250
```

```
NTDB DB2,(200,250,251)
```

### NTDB2 Macro

Set the keyword subparameters in the NTDB2 macro according to your requirements.

The NTDB2 keyword subparameters can also be specified dynamically at the start of a Natural session by using the profile parameter DB2.

### NTLFILE Macro

Set the profile parameter LFILE in the macro NTLFILE to specify a logical DBID (database ID) that relates to database type Db2:

```
NTLFILE 100,250,1
```

This is necessary for using ISQL or calling `NDBISQL` with Natural for Db2.

The `LFILE` parameter can also be specified dynamically at the start of a Natural session.

## Performance Considerations for the DB2SIZE Parameter

During execution of an SQL statement, storage is allocated dynamically to build the SQLDA for passing the host variables to Db2.

In previous Natural for Db2 versions, this storage was always obtained from the TP monitor or operating system. For performance reasons, it is now first attempted to meet the storage requirements by free space in the Natural for Db2 buffer (`DB2SIZE`). If there is not enough space available in this buffer, the TP monitor or operating system is invoked to provide additional storage.

You can avoid `GETMAIN` requests by setting `DB2SIZE` to a size larger than calculated with the [formulas](#) in the section [DB2SIZE Parameter](#).

Depending on the SQL execution mode and on the usage of the Natural file server, the additional storage requirements (in bytes) can be calculated as follows:

- [Dynamic Mode](#)
- [Static Mode](#)
- [Storage Requirements for the Natural File Server](#)
- [Example Calculation for Dynamic Mode without Using the Natural File Server](#)
- [Considerations for VARCHAR Fields](#)

### Dynamic Mode

- With sending fields:

```
80 + n * 56
```

With sending fields including LOB columns:

```
80 + 2 * n * 56
```

where  $n$  is the number of sending fields in an SQL statement.

The storage is freed immediately after the execution of the SQL statement.

- With receiving fields (that is, with variables of the `INTO` clause (see *into-clause*) of a `SELECT` statement):

$$80 + n * 56 + 24 + n * 2$$

With receiving fields including LOB columns:

$$80 + 2 * n * 56 + 24 + n * 2$$

where  $n$  is the number of receiving fields in an SQL statement.

The storage remains allocated until the loop is terminated.

### Static Mode

- With sending fields:

$$80 + n * 24$$

With sending fields including LOB columns:

$$80 + 2 * n * 56$$

where  $n$  is the number of sending fields in an SQL statement.

The storage is freed immediately after the execution of the SQL statement.

- With receiving fields (that is, with variables of the INTO clause (see *into-clause*) of a SELECT statement):

$$80 + n * 24 + 24 + n * 2$$

With receiving fields including LOB columns:

$$80 + 2 * n * 56 + 24 + n * 2$$

where  $n$  is the number of receiving fields in an SQL statement.

The storage remains allocated until the loop is terminated.

### Storage Requirements for the Natural File Server

When using the Natural file server, additional storage is required for each database loop that contains positioned UPDATE and/or DELETE statements.

For each of such loops, a buffer is allocated to save the contents of all receiving fields contained in the INTO clause (see *into-clause*). Therefore, the size of this buffer corresponds to the total length of all receiving fields:

```
20 + 4 + sum (length (v1), ..., length (vn))
```

where  $v1 \dots vn$  refers to the variables contained in the INTO clause.

The buffer remains allocated until the loop is terminated.

### Example Calculation for Dynamic Mode without Using the Natural File Server

If you use the default value 10 for both variables ( $n1$  and  $n2$ ), the calculated DB2SIZE will be 2208 bytes. However, if you specify a DB2SIZE of 20 KB instead, the available space for dynamically allocated storage will be 18272 bytes, which means enough space for up to either 325 sending fields or 313 receiving fields.

Since space for receiving fields remains allocated until a database loop is terminated, the number of fields that can be used inside such a loop is reduced accordingly. For example, if you retrieve 200 fields, you can update about 110 fields inside the loop.

### Considerations for VARCHAR Fields

When using VARCHAR fields (that is, fields with either an accompanying L@ field in the Natural view or an explicit LINDICATOR clause), additional storage is allocated dynamically if the L@ or LINDICATOR field is not specified directly in front of the corresponding base field. Therefore, always specify these fields in front of their base fields.

## Special Requirements for Natural Tools for Db2

---

Consider the following requirements and recommendations for using the Natural Tools for Db2 (described in the *Database Management System Interfaces* documentation).

- [Retrieval and Explain Functions](#)
- [LISTSQL and Explain Functions](#)

### Retrieval and Explain Functions

In order to be independent of Db2 versions, the **Retrieval** and **Explain** functions of the Natural Tools for Db2 have been designed not to access the Db2 catalog tables directly, but to access identical tables qualified by the creator name SYSSAG.

Thus, before you can use the **Retrieval** or **Explain** function, you must create these tables. The SYSSAG tables must have the same columns as the Db2 catalog tables and they must be created as ALIAS, VIEW or TABLE.

You can use the sample SQLCODE provided in the member DEMSQL4 in the Natural system library SYSDB2 to create these tables. By default, it creates an ALIAS SYSSAG.xxx for the corresponding SYSIBM table.

For some catalog tables, no indexes are defined. For performance reasons, consider creating copies of these tables with appropriate indexes.

We recommend that you work with copies of the catalog tables for the following tables:

SYSCOLAUTH  
 SYSDBRM  
 SYSFOREIGNKEYS  
 SYSINDEXPART  
 SYSKEYS  
 SYSSTMT  
 SYSSYNONYMS  
 SYSTABLEPART  
 SYSVIEWS

The required `CREATE TABLE` and `CREATE INDEX` statements are contained as comments in the sample SQL member `DEMSQL4`. In addition, `DEMSQLUP` contains sample `SQLCODE` to update the data in the copies of the catalog tables.

For any other table, we recommend that you create an `ALIAS` or a `VIEW` that points to the corresponding `SYSIBM` table.



**Note:** The sample SQL members can be executed with the `ISQL` part of `SYSDB2`. `ISQL` enables you to read SQL members from the Natural system library `SYSDB2`. You can save an SQL member in any other library by issuing the command `LIBRARY MYLIB` from the `ISQL` input screen to switch to another library and then save the SQL member there. You cannot save SQL members in the library `SYSDB2`.

## LISTSQL and Explain Functions

These functions access Db2 `PLAN_TABLES`. You can only use these functions if a `PLAN_TABLE` exists for your `SQLID`. For the layout of the `PLAN_TABLE`, refer to IBM's Db2 literature on the `EXPLAIN` command.

We recommend that you create an index on the following columns of the `PLAN_TABLE`:

APPLNAME  
 PROGNAME  
 COLLID  
 QUERYNO  
 TIMESTAMP  
 DESC  
 QBLOCKNO  
 PLANNO  
 MIXOPSEQ

## Natural for Db2 Server Stub

---

A Natural for Db2 server stub is an interface module needed to communicate between the Db2 database system and the Natural server. The server stub module determines, sets up and invokes a Natural server environment for executing Natural stored procedures and Natural user-defined functions.

As mentioned in the [Installation Procedure](#), there are two types of server stub: the Natural for Db2 start server stub (STR) and the Natural for Db2 server stub (SRV). Both stubs are generated from the NDBSTUB macro.

- [Natural for Db2 Start Server Stub](#)
- [Specify Natural for Db2 Server Stub](#)
- [JCL Procedure](#)
- [NDBSTUB Macro](#)

### Natural for Db2 Start Server Stub

The Natural for Db2 start server stub is used for setting up the Natural server environments desired. The start server stub must be the main execution program in the Stored Procedure Address Space (SPAS). After the start server stub has established the Natural server environments, it passes control to the appropriate Db2 program (DSNX9WLM for WLM SPAS and DSNX9STP for Db2 SPAS). When SPAS terminates, the Db2 program returns control to the start server stub. The start server stub stops the Natural server environments and returns control to the operating system.

The Natural for Db2 start server stub reads the names and parameters of the Natural server to be started from the CMSRVIN data set. CMSRVIN must be specified with the DD name CMSRVIN.

The CMSRVIN data set is a sequential file that contains all information required to start the desired Natural servers. For each server to be started, one START entry must be provided. The parameters used for the START entries are identical to the parameters that apply to the NDBSTUB macro. Enclose the contents of each START entry in brackets and delimit comments by the following signs: /\* and \*/.

#### Example of START Entries:

```
START=(SERVER=NDBvrSRV,NATURAL=NATBATvr,CMPRMIN=CMPRMIN,
        CMPRINT=CMPRINT,CMTRACE=CMTRACE,THREADSIZE=768,
        THREADNUMBER=2,TRACE=ON)
START=(SERVER=WDBvrSRV,NATURAL=NATBATvr,CMPRMIN=CMPRMIN,
        CMPRINT=CMPRINT,CMTRACE=CMTRACE,THREADSIZE=768,
        THREADNUMBER=2,TRACE=ON)
/* START=(SERVER=QEvrSRV,NATURAL=NATBATvr,CMPRMIN=QAPARM, */
/*      CMPRINT=CMPRINT,CMTRACE=CMTRACE,THREADSIZE=700, */
/*      THREADNUMBER=2,TRACE=OFF) */
```



If the start server data set is missing or has not been assigned, the start server stub will start a Natural server environment with the parameters that derive from the parameters defined for the start server stub itself.

## Specify Natural for Db2 Server Stub

The Natural for Db2 server stub is the link between Db2 and Natural stored procedures or Natural user-defined functions (Natural UDFs). Specify the Natural for Db2 server stub as `EXTERNAL NAME` in the `SYSIBM.SYSROUTINES` table row that refers to the Natural stored procedure or Natural UDF. The server stub is started by Db2/WLM when the Natural stored procedures or Natural UDFs are invoked. The Natural for Db2 server stub creates a Natural session in the Natural server environment and invokes the Natural subprogram comprising the Natural stored procedure or the Natural UDF.

A Natural session created for executing a Natural stored procedure terminates when the corresponding Natural subprogram ends and control returns to Db2 and to the calling client.

A Natural session created for executing a Natural UDF stays active for multiple function invocations if the `PARALLEL` attribute is set to `D` and the `FINAL CALL` attribute is set to `Y`. The session invoked for a Natural UDF function is terminated by the server stub if it detects a termination call.

## JCL Procedure

The JCL procedure of the Stored Procedure Address Space (SPAS) must specify the Natural for Db2 start server stub as program in the `EXEC` statement.

The Natural for Db2 start server stub and the Natural for Db2 server stub must reside in a library contained in the `steplib` concatenation of the JCL procedure of the SPAS.

### Example of JCL:

```

/******
/**      JCL FOR RUNNING THE WLM-ESTABLISHED STORED PROCEDURES
/**      ADDRESS SPACE
/**      RGN      -- MVS REGION SIZE FOR THE ADDRESS SPACE.
/**      DB2SSN   -- DB2 SUBSYSTEM NAME.
/**      NUMTCB   -- NUMBER OF TCBS USED TO
/**                  PROCESS END USER REQUESTS.
/**      APPLENV  -- MVS WLM APPLICATION ENVIRONMENT
/**                  SUPPORTED BY THIS JCL PROCEDURE.
/**
/******
//DBvrsENV PROC RGN=OK,APPLENV=DBvrsENV,DB2SSN=DBvrs,NUMTCB=8
//IEFPROC EXEC PGM=NDBvrSTR,REGION=&RGN,TIME=NOLIMIT, /* Start server stub
/*IEFPROC EXEC PGM=DSNX9WLM,REGION=&RGN,TIME=NOLIMIT,
//          PARM='&DB2SSN,&NUMTCB,&APPLENV'
//STEPLIB DD DISP=SHR,DSN=DSNvrs.RUNLIB.LOAD
//          DD DISP=SHR,DSN=CEE.SCEERUN

```

```
//      DD  DISP=SHR,DSN=DSNvrs.SDSNLOAD
//      DD  DISP=SHR,DSN=NATURAL.LOAD /* Library containing stubs and nucleus
//CMPRMIN DD  DISP=SHR,DSN=hilev.SOURCE(DYNPARM) /* Dynamic Natural parameters
//CMSRVIN DD  DISP=SHR,DSN=hilev.SOURCE(CMSRVIN) /* Servers to be started
//CEEDUMP DD  SYSOUT=X
//SYSOUT  DD  SYSOUT=X /* Traces records of server stub
//RMTRACE DD  SYSOUT=X
//CMPRINT DD  SYSOUT=X
//SYSPRINT DD  SYSOUT=X
//SYSERROR DD  SYSOUT=X
//SYSUDUMP DD  SYSOUT=X
```

where *hilev* represents a high-level qualifier.

## NDBSTUB Macro

The NDBSTUB macro is used to generate the Natural for Db2 server stub and Natural for Db2 start server stub. You can parameterize NDBSTUB to create different stubs.

Below are the parameters available with NDBSTUB:

CMPRINT | CMPRMIN | CMTRACE | GTRACE | GTRCID | MODE | NATURAL | SERVER | THREADSIZE | TRACE  
| WLM

### CMPRINT - DD Name of CMPRINT Data Set

CMPRINT specifies the DD name of the CMPRINT data set to which the primary report output is written. If an asterisk (\*) is specified, a unique *ddname Pnnnnnnnn* is built whenever a Natural stored procedure is invoked.

Possible Values:

Value	Explanation
<i>ddname</i>	Any valid 8-character DD name
CMPRINT	This is the default name.

### CMPRMIN - DD Name of CMPRMIN Data Set

CMPRMIN specifies the DD name of the CMPRMIN data set during startup to read the input PROFILE parameter for this server.

Possible Values:

Value	Explanation
<i>ddname</i>	Any valid 8-character DD name
CMPRMIN	This is the default name.

### CMTRACE - DD Name of CMTRACE Data Set

CMTRACE specifies the DD name of the CMTRACE data set to which the primary report output is written. If an asterisk (\*) is specified, a unique *ddname Pnnnnnnnn* is built whenever a Natural stored procedure is invoked, which makes it possible to store each output separately.

Possible Values:

Value	Explanation
<i>ddname</i>	Any valid 8-character DD name
CMTRACE	This is the default name.

### GTRACE - Natural for Db2 Server Stub to Execute GTRACE Calls

GTRACE specifies whether or not the server stub executes GTRACE macro calls for tracing purposes.

Possible Values:

Value	Explanation
ON	The generated server stub executes GTRACE macros in order to document its processing.
OFF	The generated server stub does not execute GTRACE macros during its processing cycle.  This is the default value.

### GTRCID - GTRACE ID to be Used

GTRCID specifies the event ID recorded with the trace data created by the Natural for Db2 server stub.

Possible Values:

Value	Explanation
<i>event-id</i>	Decimal number from 0 to 1023
203	This is the default value.

**MODE - Operating Mode of Natural for Db2 Server Stub**

MODE determines the operating mode of the Natural for Db2 server stub generated.

Value	Explanation
STR	The generated Natural for Db2 server stub operates as Natural for Db2 start server stub that sets up the Natural server environment.
SRV	The generated Natural for Db2 server stub operates as Natural for Db2 server stub that invokes the associated Natural stored procedure or Natural UDF.  This is the default value.

**NATURAL - Name of Server Front-End or Natural Server**

NATURAL denotes the name of the server front-end or Natural server load module loaded by the Natural for Db2 server stub if the external CMSTART has not yet been resolved by the linkage editor during the creation of the server stub. The named load module has to be present in any steplib of the stored procedure address space.

Value	Explanation
<i>name</i>	Any valid load module name
NATBAT <i>vr</i>	This is the default value.

**SERVER - Server Name for Natural Server Environment**

Server names suffixed with the three characters SRV denote the names of the servers used by the server front-end in order to identify the Natural server. These names must be unique within one address space.

Value	Explanation
<i>server-name</i>	Server name of up to 5 characters
NDB <i>vr</i>	This is the default value.

**THREADSIZE - Size of Natural Threads for Natural Server**

THREADSIZE determines the size of the Natural threads to be used by the Natural server. The size is specified in units of kilobytes.

Value	Explanation
<i>threadsiz</i>	Decimal number
768	This is the default value.

### TRACE - Natural for Db2 Server Stub to Write Trace Records

Determines whether the generated Natural for Db2 server stub writes trace records. The trace records are written to the data set specified with *ddname* SYSOUT.

Value	Explanation
YES	Trace records are written.
NO	No trace records are written. This is the default value.

### WLM - Natural for Db2 Start Server Stub Mode WLM/DB2 SPAS

WLM (Workload Manager) specifies where control is passed to after the Natural for Db2 start server stub has established the Natural server environments requested.

This parameter is only evaluated if the [MODE=STR](#) parameter is set. Specify WLM=YES if the Natural for Db2 start server stub runs in an address space that has been established by WLM.

Value	Explanation
YES	The start server stub generates links to DSNX9WLM, after setting up the Natural server environments.
NO	The start server stub generates links to DSNX9STP, after setting up the Natural server environments. This is default value.



# XII

## Installing Natural for Db2 for z/OS

---





# 13

## Installing Natural for Db2 for z/OS

---

■ Installation Medium .....	186
■ Prerequisites .....	186
■ Installation Procedure .....	188
■ NDZ Server Installation Steps .....	188
■ Add NDZ Support to Natural Batch Nucleus .....	191

This document describes the additional steps for installing Natural for Db2 for zIIP (product code NDZ) on z/OS.

### Related Topics:

For information on how to use Natural for Db2 for zIIP, see *Natural for Db2 for zIIP* in the *Database Management System Interfaces* documentation.

### Notation *vrs* or *vr*:

When used in this document, the notation *vrs* or *vr* represents the relevant product version (see also Version in the *Glossary*).

## Installation Medium

---

The **installation medium** contains the following datasets required for product installation:

Data Set Name	Contents
NDZ <i>vrs</i> .LOAD	Load modules
NDZ <i>vrs</i> .JOBS	Sample jobs for static preparation, creating trusted context, etc.
NDZ <i>vrs</i> .TAR	USS files (tar format for extraction to unix system services)

Copy the datasets into your environment as described in [Copying Data Sets to a z/OS Disk](#) in the section *Installing Natural*.

## Prerequisites

---

Before you can install Natural for Db2 for zIIP, you must have a complete and functioning installation of the standard Natural for Db2 (product code 'NDB') in the z/OS environment, see *Natural for z/OS > Installation for z/OS > Installing Natural for Db2 on z/OS*.

Parts of Natural for Db2 for zIIP will be installed in the Unix Systems Services environment (USS), and USS must have the following configuration and software already installed:

<p>IBM Java 64-bit</p> <p>This is an example of how to verify the java installation and version (your Java version may be different).</p>	<pre>\$ &lt;JAVA_PATH&gt;/bin/java -version java 17.0.7 2023-04-18 IBM Semeru Runtime Certified Edition for z/OS ↵ 17.0.7.0 (build 17.0.7+7) IBM J9 VM 17.0.7.0 (build ↵ z/OS-Release-17.0.7.0-b01, JRE 17 z/OS s390x-64-Bit Compressed References 20230809_41 (JIT ↵ enabled, AOT enabled) OpenJ9      - bc2691d03c1 OMR         - 49ecb822254 IBM         - fae32e3 JCL         - 8e3170b6410 based on jdk-17.0.7+7) ↵</pre>
<p>Db2 JDBC Driver</p> <p>This is an example of how to verify the JDBC driver installation and version (your driver version may be different).</p>	<pre>\$ &lt;JAVA_PATH&gt;/bin/java -cp ↵ &lt;DB2_PATH&gt;/jdbc/classes/db2jcc.jar com.ibm.db2.jcc.DB2Jcc -version IBM DB2 JDBC Universal Driver Architecture 3.72.54 ↵</pre>
<p>NDZ Installation Directory</p> <p>An installation directory for NDZ must already have been created.</p>	<pre>\$ pwd /DAXY/u/nat/ndzuser \$ mkdir ndz923 ↵</pre>

In addition, the following must be configured on z/OS:

- The NDZ load library must be included in the APF authorized list.
- RACF user (called *ndzuser* in the following examples) with:
  - A started RACF profile defined for NDZ started task(s).
  - A permit to ERBSDS.MON3DATA RACF facility profile.
  - A permit to BPX.WLMSEVER RACF facility profile.
  - Write permissions to the NDZ installation directory.
- A Db2 user (called *db2user* in the following examples) must be created to access Db2 via TCP/IP. *ndzuser* can also be used in place of *db2user*.

## Installation Procedure

---

Be sure to read *Installation Process and Major Natural Features on z/OS* before you start the installation procedure.

The installation procedure comprises the following:

- **NDZ Server Installation Steps**
- **Installation Steps Specific to Batch**

## NDZ Server Installation Steps

---

This section describes the installation steps that apply to all Natural environments where Natural for Db2 for zIIP can be installed.

- Step 1: Prepare the License Key
- Step 2: Create Trusted Context
- Step 3: Copy and Extract the NDZ Installation TAR file
- Step 4: Generate the db2.properties File
- Step 5: Generate the ndz.properties File
- Step 6: Update Static Preparation Shell Script setenv.sh
- Step 7: Encrypt the Db2 Password (optional step)
- Step 8: Link the NDZ Nucleus
- Step 9: Create NDZ started task procedure(s)

### Step 1: Prepare the License Key

Copy the license file from the supplied installation medium to disk. If the license file is supplied on PC as an .xml file, then allocate a dataset called NDZvrs.LICS with the attributes below:

```
ORGANIZATION   :  PS
RECORD FORMAT  :  FB
RECORD LENGTH  :  80
BLOCK SIZE     :  27920
ALLOCATION TYPE :  TRK
1ST EXTENT     :  0          CYL 1    TRK
```

Then use FTP in binary transfer mode to transfer the .xml file from the PC to the dataset.

**Step 2: Create Trusted Context**

(Job I010 Step 9610)

Create the Trusted context object in a Db2 server using the Db2 user to establish a trusted connection.

- Replace the variable 'UID' with db2user. For example:

```
BASED UPON CONNECTION USING SYSTEM AUTHID db2user
```

- Submit the job.

**Step 3: Copy and Extract the NDZ Installation TAR file**

(Job I020 Step 9610 + 9615 + 9620)

- Step 9610 (delete old .tar and Java jar files in USS, if present)
- Step 9615 (copy .tar file to USS)
- Step 9620 (unpack .tar file in USS)
- Edit NDZvrs.MVSJOBS(NDZI020) and replace all occurrences of /U/SAG/NAT/NDZ with your actual installation directory.
- Submit the job.

**Step 4: Generate the db2.properties File**

(Job I022 Step 9615)

Create the Db2 properties file in the NDZ configuration directory (*<NDZ installation directory>/etc/db2.properties*) with the specific Db2 connection and configuration properties.

**OR:**

1. Create the *<NDZ installation directory>/etc/db2.properties* file from the sample file *<NDZ installation directory>/etc/db2.properties.sample*.
2. Set the variables according to the instructions located in the sample file.

For more information, refer to *Natural for z/OS > Database Management System Interfaces > Configuration and Parameters > Parameters*.

## Step 5: Generate the ndz.properties File

(Job I022 Step 9620)

Create the NDZ properties file in the NDZ configuration directory (*<NDZ installation directory>/etc/ndz.properties*) with the parameters for the NDZ Server.

**OR:**

1. Create the *<NDZ installation directory>/etc/ndz.properties* file from the sample file *<NDZ installation directory>/etc/ndz.properties.sample*.
2. Set the variables according to the instructions located in the sample file.

For more information, refer to *Natural for z/OS > Database Management System Interfaces > Configuration and Parameters > Parameters*.

## Step 6: Update Static Preparation Shell Script setenv.sh

(Job I022 Step 9625)

Update the shell script responsible for setting the Db2, Java, and NDZ home path variables (*<NDZ installation directory>/bin/setenv.sh*) for the NDZ Server.

**OR:**

Create the *<NDZ installation directory>/bin/setenv.sh* file from the sample *<NDZ installation directory>/bin/setenv.sh.sample* file. Update the Db2, Java, and NDZ home path variables in the *setenv.sh* file.

For more information, refer to *Natural for z/OS > Database Management System Interfaces > Configuration and Parameters > Parameters*.

## Step 7: Encrypt the Db2 Password (optional step)

You may secure your Db2 connection password using Db2 password encryption. Doing so is optional but strongly recommended. The instructions are described in *Database Management System Interfaces > Configuration and Parameters > Db2 Password Encryption*.

If you use the Db2 encrypted password utility, you may delete the password parameter from the *db2.properties* file, as this parameter will be ignored.

## Step 8: Link the NDZ Nucleus

(Job I058 Step 9610)

Link the NDZ nucleus with `NDZvrs.LOAD(NDZNUC)`, `MLCvrs.LOAD(LICMAIN)` and `MLCvrs.LOAD(LICCHECK)`.

## Step 9: Create NDZ started task procedure(s)

(Job I200 Step 9610)

Create procedure(s) for NDZ started task(s) (or daemons) using the following template:

```
//NAME      PROC
//*
//NDZ11      EXEC  PGM=NDZNUC11,REGION=0M,TIME=NOLIMIT,
//  PARM=('PATH=<NDZ INSTALLATION DIRECTORY>')
//*-----*
//LICNDZBT   DD  DISP=SHR,DSN=<LICENSE DATASET>
//STEPLIB    DD  DISP=SHR,DSN=<LOAD DATASET>
//SYSPRINT   DD  SYSOUT=X
//SYSOUT      DD  SYSOUT=X
//SYSUDUMP    DD  SYSOUT=X
//STDOUT      DD  SYSOUT=X
//STDERR      DD  SYSOUT=X ↵
```

- Substitute the highlighted parts using the following instructions:
  - NAME – The name of the started task.
  - NDZ INSTALLATION PATH – The path to the NDZ home directory.
  - LICENSE DATASET – The dataset which contains the license file.
  - LOAD DATASET – The APF authorized dataset in which the NDZ nucleus is located.
- Submit the job.

## Add NDZ Support to Natural Batch Nucleus

(Job I060 Step 9625)

1. Link the Batch Nucleus with NDZ Support.
2. Add the following `INCLUDE` statements and corresponding `DD` statements to the link instructions for the linkage editor. Specify the same Db2 interface module used during NDB installation, see *Natural for z/OS > Installation for z/OS > Installing Natural for Db2 on z/OS*.

INCLUDE NDBLIB(NDBNDZ)	NDB support for NDZ
CHANGE DSNHLI(DB2HLI)	Db2 Interface module
INCLUDE DB2LIB(DSNALI) OR	Db2 Interface module (CAF)
INCLUDE DB2LIB(DSNELI)	Db2 Interface module (TSO)



# XIII

## Installing Natural for VSAM on z/OS

---

This document describes the installation of Natural for VSAM (product code NVS) on an Adabas database or in a VSAM (Virtual Storage Access Method) file system on z/OS.

### Prerequisites

[Installing Natural for VSAM on Adabas System Files](#)

[Installing Natural for VSAM on VSAM System Files](#)

### Related Topic:

For information on how to operate Natural in a VSAM environment, see *Natural for VSAM* in the *Database Management System Interfaces* documentation.

### Notation *vrs* or *vr*:

When used in this document, the notation *vrs* or *vr* represents the relevant product version (see also Version in the *Glossary*).



# 14

## Prerequisites

---

See *General Prerequisites and System Support* in the section *Overview of the Installation Process*.

For the installation of Natural ISPF in a VSAM file system, see the Natural ISPF *Installation* documentation. Be sure that you use the relevant module (NVSISPV) provided on the Natural for VSAM installation medium.



# 15

## Installing Natural for VSAM on Adabas System Files on z/OS

---

■ Installation Medium .....	198
■ Installation Procedure .....	198
■ Installation Verification .....	202

This document describes the steps for installing Natural for VSAM on an Adabas database on z/OS.

## Installation Medium

---

The **installation medium** contains the following data sets required for product installation:

Data Set Name	Contents
NVSvrs.LOAD	Load modules
NVSvrs.SRCE	Source modules and macros
NVSvrs.JOBS	Sample installation jobs
NVSvrs.EMPL	EMPLOYEES example data
NVSvrs.EXPL	Natural example objects

Copy the data sets into your environment as described in [Copying Data Sets to a z/OS Disk](#) in the section *Installing Natural*.

## Installation Procedure

---

Be sure to read [Installation Process and Major Natural Features](#) before you start the installation procedure.

- [Step 1: Define the CICS RDO Definitions](#)
- [Step 2: Load the Employees Example Data](#)
- [Step 3: Build the Natural for VSAM I/O Module](#)
- [Step 4: Build the Natural Parameter Module for VSAM](#)
- [Step 5: Link the Nucleus](#)
- [Step 6: Load the Natural Example Objects](#)
- [Step 7: Customize your TP Monitor](#)

### Step 1: Define the CICS RDO Definitions

(Job I005)

- Define the CICS RDO definitions for the sample VSAM files.

## Step 2: Load the Employees Example Data

(Job I008, Steps 1403 - 1407)

1. Define the VSAM cluster and files to contain the Employees example file.
2. Load the `NVSvrs.EMPL` data set into the first of these files (suffix `.EMPL`).
3. Build a secondary index of this into the second file (suffix `.EMPLX`) and define the path for this.

## Step 3: Build the Natural for VSAM I/O Module

- Assemble and link the Natural for VSAM I/O module:

- Under Com-plete:

(Job I055, Steps 1410, 1411, 1415, 1416)

Assemble the I/O module `NVSMISC` by using the parameter `SMARTS=YES` (Steps 1415 and 1416). For detailed information, see *NVSMISC Module* and `SMARTS` described in the *Database Management System Interfaces* documentation.

- Under CICS:

(Job I070, Step 1400)

Use the I/O module `NVSCICS`. See *NVSCICS Module* described in the *Database Management System Interfaces* documentation.



**Note:** If you are not using the most recent CICS version, the precompile step may result in a non-zero return code (4 - 16, depending on your CICS version) because of CICS commands being used that are unknown to your CICS translator. This return code can be ignored as long as the subsequent assembly step ends with a return code of 0.

- In any other environment:

Use the I/O module `NVSMISC`. See *NVSMISC Module* described in the *Database Management System Interfaces* documentation.

## Step 4: Build the Natural Parameter Module for VSAM

(Jobs I060, I080)

Build the Natural parameter module:

1. Modify the appropriate jobs according to the batch modules or TP monitor you are relinking: Job I060 for batch, Job I080 for Com-plete and Job I080 for CICS. This applies also to [Step 5: Link the Nucleus](#).

Add the following parameter and macro calls to your Natural parameter module:

```
VSIZ=72 NTDB VSAM, vsam-dbid NTVSAM
```

The values for `VSIZ` depend on the values specified in `NTVSAM` (see also the *VSIZ Parameter* in the *Database Management System Interfaces* documentation).

2. Assemble and link the Natural parameter module.

## Step 5: Link the Nucleus

(Jobs I060, I080)

- Modify the JCL used to link your [environment-independent nucleus](#) by adding the following `INCLUDE` statement:

```
INCLUDE NVSLIB(NVSNUC)
```

- Modify the JCL used to link your [environment-dependent nucleus](#) for the Natural CICS Interface by adding the following `INCLUDE` statement:

```
INCLUDE SMALIB(NVSCICS)
```

- Modify the JCL used to link your [environment-dependent nucleus](#) for Natural TP monitor interfaces other than the Natural CICS Interface by adding the following `INCLUDE` statement:

```
INCLUDE SMALIB(NVSMISC)
```

- Modify the JCL used to link your [environment-dependent nucleus](#) for Natural TP monitor interfaces other than the Natural CICS Interface if `RLS=CHECK` is specified in the `NTVSAM` macro of the VSAM-specific Natural parameter module by adding the following `INCLUDE` statement:



```
INCLUDE CSSLIB(IGWARLS)
```

The routine `IGWARLS` is a callable service to support RLS processing. It resides in the system library `SYS1.CSSLIB`. Add the corresponding DD statements to the link step for Natural.

For information on the components and structure of Natural for VSAM, see also *Components of Natural for VSAM* and *Structure of the Natural Interface to VSAM* in the *Database Management System Interfaces* documentation.

## Step 6: Load the Natural Example Objects

(Job I061, Step 1400)

- Load the Natural example objects specific to Natural for VSAM from the `NVSvrs.EXPL` data set into the Natural system file by using the Natural [INPL utility](#).

## Step 7: Customize your TP Monitor

- Customize your TP monitor environment:

TP Monitor	Instruction
Com-plete	<p>Catalog all VSAM files to Com-plete using the CA function of the Com-plete UFILE utility (described in the <i>Com-plete</i> documentation).</p> <p>If you have specified <code>PATH=CHECK</code> in <code>NTVSAM</code>:</p> <ol style="list-style-type: none"> <li>1. Catalog your front program to Com-plete using the CA function of the Com-plete ULIB utility with a region size of 40 KB if you have not changed the first default value of the <code>WPSIZE</code> parameter in the Natural parameter module.</li> <li>2. Load the IBM routine <code>IGGOCLA0</code> either in the LPA or as a resident program using the Com-plete UCTRL utility.</li> </ol>
CICS	<p>Add the entries for the VSAM-specific example files <code>EMPLVS</code> and <code>EMPLVX</code> to your RDO definition as described in <a href="#">Step 1: Define the CICS RDO Definitions</a>; you can find the CICS tables on the <code>NVSvrs.JOBS</code> data set as <code>NVSI005</code>.</p>
TSO	<p>Add the following statements to the CLIST used to start Natural:</p> <pre>ALLOCATE F(EMPLVS) DATASET('SAGLIB.VSAM.EMPL')      SHR ALLOCATE F(EMPLVX) DATASET('SAGLIB.VSAM.EMPLX.PATH') SHR</pre>

## Installation Verification

---

You can verify the successful installation of Natural for VSAM by performing the following:

■ Log on to the Natural system library SYSEXNVS and run the following programs:

- NVSINST1
- NVSINST2
- NVSINST3
- NVSINST4
- NVSINST5
- NVSINST6

If all these programs can be executed successfully, the installation of Natural for VSAM is completed and verified.

### **Note for Batch Mode:**

For verification in batch mode, you can run Job I200 which executes the above programs.

# 16

## Installing Natural for VSAM on VSAM System Files on z/OS

---

■ Installation Medium for VSAM .....	204
■ Installation Procedure for VSAM .....	205
■ Installation Verification on VSAM System Files .....	213
■ Restrictions .....	213

This document describes the steps for installing Natural for VSAM in a VSAM file system on z/OS.

The Natural system files `FNAT`, `FUSER`, `FDIC`, `FSEC` and `FSP00L` can also be located on VSAM files.

The installation of Natural for VSAM in a VSAM file system is basically a combination of the installation descriptions for both base Natural and Natural for VSAM, plus some points specific to VSAM.

For support of source object locking, a separate `FLOCK` file and related paths are required.

## Installation Medium for VSAM

---

The **installation medium** contains the following data sets required for product installation:

If you want to install Natural in a VSAM file system, you need the data sets for both base Natural and Natural for VSAM. The required data sets are listed in the table below:

Data Set Name	Contents
<code>NATvrs.LOAD</code>	Load modules
<code>NATvrs.SRCE</code>	Source modules and macros
<code>NATvrs.JOBS</code>	Sample installation jobs
<code>NATvrs.INPL</code>	Natural objects
<code>NATvrs.EXPL</code>	Natural example objects
<code>NVSvrs.LOAD</code>	Load modules
<code>NVSvrs.SRCE</code>	Source modules and macros
<code>NVSvrs.JOBS</code>	Sample installation jobs
<code>NVSvrs.VINI</code>	<code>FDIC</code> initialization file for Natural for VSAM
<code>NVSvrs.LINI</code>	<code>FLOCK</code> initialization file for Natural for VSAM
<code>NVSvrs.EMPL</code>	<code>EMPLOYEES</code> example data
<code>NVSvrs.EXPL</code>	Natural example objects

Copy the data sets into your environment as described in [Copying Data Sets to a z/OS Disk](#).

## Installation Procedure for VSAM

Be sure to read *Installation Process and Major Natural Features* before you start the installation procedure.

The VSAM jobs (for example, VSAMI008) indicated in this section are identical to the jobs generated by *System Maintenance Aid* (for example, I008).

- Step 1: Define the CICS RDO Definitions on VSAM System Files
- Step 2: Load the Employees Example Data on VSAM System Files
- Step 3: Prepare the VSAM Clusters for the Natural System Files
- Step 4: Prepare a VSAM Cluster for the Spool File
- Step 5: Prepare a VSAM Cluster for the Security File
- Step 6: Prepare a VSAM Cluster for the Scratch-Pad File
- Step 7: Prepare a VSAM Cluster for the Source Locking File FLOCK
- Step 8: Build the Natural for VSAM I/O Module
- Step 9: Build the Natural Parameter Module for Batch Mode for VSAM
- Step 10: Link the Nucleus for Batch Natural
- Step 11: Load the Natural Objects
- Step 12: Load the Natural Example Objects
- Step 13: Reorganize the FNAT System File
- Step 14: Build the Natural for VSAM I/O Module for CICS
- Step 15: Link the Nucleus for Natural Under a TP Monitor
- Step 16: Customize your TP Monitor

### Step 1: Define the CICS RDO Definitions on VSAM System Files

(Job VSAMI005)

- Define the CICS RDO definitions for the sample VSAM files.

### Step 2: Load the Employees Example Data on VSAM System Files

(Job VSAMI008, Steps 1403 - 1407)

1. Define the VSAM cluster and files to contain the Employees example file.
2. Load the NVSvrs.EMPL data set into the first of these files (suffix .EMPL).
3. Build a secondary index of this into the second file (suffix .EMPLX) and define the path for this.

### Step 3: Prepare the VSAM Clusters for the Natural System Files

(Job VSAMI008, Steps 1420 - 1446)

- Define three VSAM clusters to be used as system files for Natural (FNAT, FUSER and FDIC), an alternate index and a path for the alternate index for FDIC.

We strongly recommend that you keep these three system files on separate VSAM clusters.

### Step 4: Prepare a VSAM Cluster for the Spool File

(Job VSAMI008, Steps 0300 - 0309)

This step must be performed only if you have Natural Advanced Facilities installed and want your spool file to be a VSAM file, too.

- Define an additional VSAM cluster to be used as the spool file (FSP00L) and five alternate indices.



**Note:** Path processing is *not* supported for FSP00L.

### Step 5: Prepare a VSAM Cluster for the Security File

(Job VSAMI008, Steps 9900 - 9907)

This step must be performed only if you have Natural Security installed and want your security file to be a VSAM file, too.

- Define an additional VSAM cluster to be used as the security file (FSEC) and three alternate indices.



**Note:** Path processing is *not* supported for FSEC.

### Step 6: Prepare a VSAM Cluster for the Scratch-Pad File

(Job VSAMI008, Steps 1450, 1451)

This step must be performed only if you want to use a scratch-pad file; that is, if you want to use read-only Natural system files (ROSY=ON); see also the Natural profile parameter ROSY and the macro NTLFILE described in the *Parameter Reference* documentation.

- Define an additional VSAM cluster to be used as the scratch-pad file (Step 1450).
- Initialize the VSAM scratch-pad file (Step 1451).
- Set the following parameters in the Natural parameter module according to your requirements:

```
NTLFILE 212,dbid,nt-file-number,dd-name-scratch-pad-file
ROSY=ON
```

- If you want your Natural system file(s) to be opened for input, adapt your Natural parameter module as follows:

```
FNAT=(dbid,fnr,filename,,RO),
FUSER=(dbid,fnr,filename,,RO),
FSEC=(dbid,fnr,filename,,RO),
```

## Step 7: Prepare a VSAM Cluster for the Source Locking File FLOCK

(Job VSAMI008, Steps 1460, 1461)

This step must be performed only if you want to lock source objects in a VSAM file system (SLOCK=PRE); see also the parameter SLOCK and the macro NTLFILE (described in the *Parameter Reference* documentation).

- Define an additional VSAM cluster to be used as the source locking file (Step 1460).
- Load and print the example data record contained in the VSAM source locking file (Step 1461).
- Set the following parameters in the Natural parameter module according to your requirements:

```
NTLFILE 002,dbid,nt-file-number,dd-name-source-locking-file,,PATH
SLOCK=PRE
```

The default DD name (*dd-name*) is FLOCK, the related default paths are FLOCKA, FLOCKB and FLOCKC.

## Step 8: Build the Natural for VSAM I/O Module

(Job VSAMI055, Steps 1410, 1411, 1415, 1416)

- Edit, assemble and link the Natural for VSAM I/O module NVSMISC with the LSR options:

```
DEFER=YES
COMMIT=NO
READINT=NO
```

For the parameters that can be specified in the NVSMISC module, see the relevant section in the *Database Management System Interfaces* documentation.

## Step 9: Build the Natural Parameter Module for Batch Mode for VSAM

(Job I060, Step 0010)

1. Modify the settings of the supplied Natural profile parameters as required for batch mode. The parameters and corresponding macros (if applicable) are described in the *Parameter Reference* documentation. The most important parameter/macro settings are described below.

- Configure the z/OS batch interface:

Modify the settings of the parameters supplied with the `NTOSP` macro to meet your requirements. For descriptions of these parameters, see the corresponding profile parameter `OSP`.

- In addition to the `VSIZ` and `NTDB` specifications, modify the parameters `FNAT`, `FUSER` and `FDIC` as follows:

```
VSIZ=126,  
FNAT=(vsam-dbid,fnr-fnat,dd-name-fnat),  
FUSER=(vsam-dbid,fnr-fuser,dd-name-fuser),  
FDIC=(vsam-dbid,fnr-fdic,dd-name-fdic),  
NTDB VSAM,vsam-dbid  
NTVSAM
```

The `vsam-dbid` must have the same value in all four entries.

We recommend that you use different files and different file numbers for `FNAT` and `FUSER`. The `FDIC` file must be a file different from `FNAT` and `FUSER`. Therefore, you may *not* omit the `FDIC` parameter.

The DD names (`dd-name`) are the logical names of the Natural system files; each DD name can be up to seven characters long. The DD name for the `FDIC` path is created by appending an `X` to the DD name of the `FDIC` file.

- If you have Natural Advanced Facilities installed and want your spool file to be a VSAM file, modify the `FSP00L` parameter accordingly:

```
FSP00L=(vsam-dbid,fnr-fspool,dd-name-fspool)
```

- If you have Natural Security installed and want your security file to be a VSAM file, modify the `FSEC` parameter accordingly:

```
FSEC=(vsam-dbid,fnr-fsec,dd-name-fsec)
```

The `FSEC` file must be a file different from `FNAT`.

- For a quick installation, use the Natural for VSAM LSR feature and specify the following `NTVLSR` definitions in the Natural parameter module (see also *NTVLSR Macro* in the *Parameter Reference* documentation):



```
NTVLSR fnat-dd-name,1
NTVLSR fuser-dd-name,2
NTVLSR fdic-dd-name,3
NTVLSR fdicx-dd-name,3
```

If you want to use FSEC system files:

```
NTVLSR fsec-dd-name,4
NTVLSR fseca-dd-name,4
NTVLSR fsecb-dd-name,4
NTVLSR fsecc-dd-name,4
```

2. Assemble and link the batch parameter module.

### Step 10: Link the Nucleus for Batch Natural

(Job I060, Step 0020)

1. Modify the JCL used to link your **environment-dependent nucleus** for batch Natural by adding the following INCLUDE statements:

```
INCLUDE NVSLIB(NVSNUC)
INCLUDE NVSLIB(NVSFNAT)
INCLUDE NVSLIB(NVSFSP0)
INCLUDE NVSLIB(NVSFSEC)
INCLUDE SMALIB(NVSFLOCK)
INCLUDE SMALIB(NVSMISC)
```

The module NVSFSP0 is only required if you have Natural Advanced Facilities installed and want your spool file to be installed in a VSAM file system.

The module NVSFSEC is only required if you have Natural Security installed and want your security file to be installed in a VSAM file system.

The module NVSFLOCK is only required if you want to lock source objects contained in an FUSER or FNAT system file in a VSAM file system.

If your **environment-dependent nucleus** is not linked to your **environment-independent nucleus**, NVSMISC must be linked to the Natural parameter module instead.

2. Add the corresponding DD statements to the link step for Natural.

For information on the components and structure of the Natural interface to VSAM, see also *Components of Natural for VSAM* and *Structure of the Natural Interface to VSAM* in the *Database Management System Interfaces* documentation.

## Step 11: Load the Natural Objects

(Job I061, Step 0100)

- Load the Natural objects from the `NATvrs.INPL` data set into the Natural system file by using the Natural **INPL utility**.

Ensure that the DD names specified in the Natural parameter module (see [Step 9: Build the Natural Parameter Module for Batch Mode for VSAM](#)) are also specified for the load function performed with the Natural INPL utility. In addition, an alternate index DD name (`dd-name-fdicX`) must be specified for FDIC.



**Note:** If you want to install any other products that require Natural objects to be loaded with the Natural **INPL utility**, ensure that the corresponding installation steps are adapted according to [Job VSAMI061](#).

## Step 12: Load the Natural Example Objects

(Job I061, Step 0103, and Job VSAMI061, Step 1400)

- Load the Natural example objects from the `NATvrs.EXPL` data set into the Natural system file by using the Natural INPL utility (Job I061, Step 0103).
- Load the Natural example objects specific to Natural for VSAM from the `NVSvrs.EXPL` data set into the Natural system file by using the Natural INPL utility (Job VSAMI061, Step 1400).

Ensure that the DD names specified in the Natural parameter module (see [Step 9: Build the Natural Parameter Module for Batch Mode for VSAM](#)) are also specified for the load function performed with the Natural INPL utility. In addition, a path DD name (`dd-name-fdicX`) must be specified for FDIC.

## Step 13: Reorganize the FNAT System File

- Reorganize the FNAT system file by using the VSAM facility AMS REPRO to unload and reload the file.

## Step 14: Build the Natural for VSAM I/O Module for CICS

(Job VSAMI070, Step 1400)

This step must be performed only if you want to install Natural for VSAM under CICS.

- Assemble and link the module NVSCICS.

**Step 15: Link the Nucleus for Natural Under a TP Monitor**

(Job VSAMI080)

Proceed with the TP monitor-specific installation steps for base Natural described in the relevant sections in *Installation for z/OS*, taking into account the following additions:

- Modify your VSAM-specific Natural parameter module according to [Step 9: Build the Natural Parameter Module for Batch Mode for VSAM](#).
- Add the following `INCLUDE` statements to all links of the online nucleus:

```
INCLUDE NVSLIB(NVSNUC)
INCLUDE NVSLIB(NVSFNAT)
INCLUDE NVSLIB(NVSFSP0)
INCLUDE NVSLIB(NVSFSEC)
INCLUDE NVSLIB(NVSFLOCK)
```

The module `NVSFSP0` is only required if you have Natural Advanced Facilities installed and want your spool file to be installed in a VSAM file system. The online environment for Natural Advanced Facilities must be a CICS environment, and the spool files installed in a VSAM file system must be defined in the CICS FCT.

The module `NVSFSEC` is only required if you have Natural Security installed and want your Natural security system file to be installed in a VSAM file system. The VSAM Natural security system files installed in a VSAM file system must be defined in the CICS FCT.

The module `NVSFLOCK` is only required if you want to lock source objects contained in an FUSER or FNAT system file in a VSAM file system. The locking files installed in a VSAM file system must be defined in the CICS FCT.

- Modify the JCL used to link your [environment-dependent nucleus](#) for the Natural CICS Interface by adding the following `INCLUDE` statement:

```
INCLUDE SMALIB(NVSCICS)
```

- Modify the JCL used to link your [environment-dependent nucleus](#) for Natural TP monitor interfaces other than the Natural CICS Interface by adding the following `INCLUDE` statement:

```
INCLUDE SMALIB(NVSMISC)
```

- Before starting Natural, ensure that the DD and DSN names of the Natural system files in the VSAM file system are known in your batch and online environments.

**Step 16: Customize your TP Monitor**

Customize your TP monitor environment:

TP Monitor	Instruction
Com-plete	<p>Catalog the FNAT, FUSER and FDIC system files in the VSAM file system under Com-plete using the CA function of the Com-plete UFILE utility (described in the <i>Com-plete</i> documentation).</p> <p>If Natural Security is installed, catalog the FSEC, FSECA, FSECB and FSECC system files in the VSAM file system under Com-plete using the CA function of the Com-plete UFILE utility.</p> <p>If you want to lock source objects contained in the FUSER or FNAT system file, catalog the VSAM files FLOCK, FLOCKA, FLOCKB and FLOCKC under Com-plete using the CA function of the Com-plete UFILE utility.</p> <p>If you have specified PATH=CHECK in NTVSAM, catalog your front program to <b>Com-plete</b> using the CA function of the Com-plete ULIB utility (described in the <i>Com-plete</i> documentation) with a region size of 36 KB if you have not changed the first default value for the WPSIZE (described in the <i>Parameter Reference</i> documentation) in the Natural parameter module.</p>
CICS	<p>Add the following entries to your FCT:</p> <ul style="list-style-type: none"> <li>■ the Natural system files FNAT, FUSER, FDIC and FDICX required for VSAM;</li> <li>■ the Natural example files EMPLVS and EMPLVX provided for VSAM;</li> <li>■ the Natural Security files FSEC, FSECA, FSECB and FSECC if you have Natural Security installed;</li> <li>■ the VSAM files FLOCK, FLOCKA, FLOCKB and FLOCKC if you want to lock source objects contained in the FUSER or FNAT system file in the VSAM file system.</li> </ul> <p>Refer to Job VSAMI005 for examples. You can add DD statements for these data sets to your CICS startup job, too.</p>
TSO	<p>Add the following statements to the CLIST used to start Natural:</p> <pre> ALLOCATE F(FNAT)      DATASET('SAGLIB.VSAM.FNAT')      SHR ALLOCATE F(FUSER)     DATASET('SAGLIB.VSAM.FUSER')     SHR ALLOCATE F(FDIC)      DATASET('SAGLIB.VSAM.FDIC')      SHR ALLOCATE F(FDICX)     DATASET('SAGLIB.VSAM.FDIC.PATH')  SHR ALLOCATE F(FSEC)      DATASET('SAGLIB.VSAM.FSEC')      SHR ALLOCATE F(FSECA)     DATASET('SAGLIB.VSAM.FSEC.AIXA')  SHR ALLOCATE F(FSECB)     DATASET('SAGLIB.VSAM.FSEC.AIXB')  SHR ALLOCATE F(FSECC)     DATASET('SAGLIB.VSAM.FSEC.AIXC')  SHR ALLOCATE F(FLOCK)     DATASET('SAGLIB.VSAM.FLOCK')     SHR ALLOCATE F(FLOCKA)    DATASET('SAGLIB.VSAM.FLOCK.PATHA') SHR ALLOCATE F(FLOCKB)    DATASET('SAGLIB.VSAM.FLOCK.PATHB') SHR ALLOCATE F(FLOCKC)    DATASET('SAGLIB.VSAM.FLOCK.PATHC') SHR ALLOCATE F(EMPLVS)    DATASET('SAGLIB.VSAM.EMPLVS')    SHR ALLOCATE F(EMPLVX)    DATASET('SAGLIB.VSAM.EMPLVX.PATH') SHR </pre>

## Installation Verification on VSAM System Files

---

You can verify the successful installation of Natural for VSAM by performing the following:

■ Log on to the Natural system library SYSEXNVS and run the following programs:

- NVSINST1
- NVSINST2
- NVSINST3
- NVSINST4
- NVSINST5
- NVSINST6

If all these programs can be executed successfully, the installation of Natural in a VSAM file system is completed and verified.

### Note for Batch Mode:

For verification in batch mode, you can run Job VSAMI200 which executes the above programs.

## Restrictions

---

The Natural FSEC and FSP00L system files provided for VSAM file systems cannot be used for record-level sharing (RLS), as the related AIX files cannot be accessed using a path definition. The reason is that null values are not suppressed during VSAM upgrade handling for AIX keys. The record length of AIX files related to FSEC and FSP00L would be exceeded for AIX keys filled with blanks or binary zeros. This would cause problems under CICS, as the record length supported is limited to 32 K only. Natural for VSAM supports null-value suppression for AIX keys and the upgrade handling for AIX files.



# XIV

## Installing Natural Messaging on z/OS

---





# 17

## Installing Natural Messaging on z/OS

---

■ Installation Medium .....	218
■ Installation Procedure .....	218

This document describes the steps for installing Natural Messaging (product code NMQ) on z/OS.

**Related Topic:**

For information on the features and functions provided by Natural Messaging, see *Natural Messaging* in the *Database Management System Interfaces* documentation.

**Notation *vrs* or *vr*:**

When used in this document, the notation *vrs* or *vr* represents the relevant product version (see also Version in the *Glossary*).

## Installation Medium

---

The **installation medium** contains the following data sets required for product installation:

Data Set Name	Contents
NMQ <i>vrs</i> .LICS	Load modules for the z/OS license check software containing the LICUTIL license utility  The placeholder <i>vrs</i> in the library name represents the version of the license check software, which is not necessarily the same as the version of Natural.  For detailed information on the license check software and the LICUTIL utility, see <i>Mainframe Product Licensing</i> .
NMQ <i>vrs</i> .LOAD	Load modules
NMQ <i>vrs</i> .INPL	DDMs for Natural Messaging and examples

Copy the data sets into your environment as described in *Copying Data Sets to a z/OS Disk* in the section *Installing Natural*.

## Installation Procedure

---

Be sure to read *Installation Process and Major Natural Features* before you start the installation procedure.

- Step 1: Prepare, Convert, Assemble and Link the License File
- Step 2: Build the Natural Parameter Module with a Database Assignment for Natural Messaging
- Step 3: Link the Nucleus

■ [Step 4: Load the DDMs and the Natural Example Objects](#)

## Step 1: Prepare, Convert, Assemble and Link the License File

(Job I007, Steps 3401, 3402, 3404)

In addition to the Natural product license file, a valid Natural Messaging license file is required and must be installed for each environment in which Natural Messaging (NMQ) runs. For license file `NMQvrs.LICS`, see *Mainframe Product Licensing*.

1. Copy the license file from the installation medium to disk or transfer it from the PC as described in *Transferring a License File from PC to a z/OS Host Using FTP* in *Mainframe Product Licensing*.
2. Check, convert, assemble, and link the license file:

Step 3401	Check the license file <code>NMQvrs.LICS</code> . This job executes the CHECK function of the LICUTIL license utility.
Step 3402	Convert the license file into an assembler source. This job executes the MAKE function of the LICUTIL license utility.
Step 3404	Assemble and link the assembler source to generate load module <code>NMQLIC</code> . This module is then linked to the nucleus (see below).

The functions and option settings provided by LICUTIL are described in *Using the License Utility: LICUTIL* in *Mainframe Product Licensing*.



**Caution:** Natural Messaging is not enabled unless you install a valid Natural Messaging license file. Trying to activate Natural Messaging without a valid license file results in warnings or errors at session start.

## Step 2: Build the Natural Parameter Module with a Database Assignment for Natural Messaging

(Job I060, Steps 0010, 0015 for batch)

(Job I080, Steps 2210, 2220 for CICS)

(Job I080, Steps 2300, 2310 for Com-plete)

(Job I080, Steps 0010, 0015 for TSO)

Build the Natural parameter module:

1. Modify the appropriate jobs according to the batch modules or TP monitor you are relinking: Job I060 for batch, Job I080 for CICS and Com-plete.

Add the following macro call to your Natural parameter module:

```
NTDB MQ, my-dbid
```

2. Assemble and link the Natural parameter module.

### Step 3: Link the Nucleus

(Job I060, Step 0105)

(Job I060, Step 0020 for batch)

(Job I080, Steps 2230 for CICS)

(Job I080, Steps 2320 for Com-plete)

(Job I080, Steps 0020 for TSO)

- Modify the JCL used to link your **environment-independent nucleus** by adding the following `INCLUDE` statement:

```
INCLUDE NMQLIB(NQMNUC)
```

- Modify the JCL used to link your **environment-dependent nucleus** for the Natural CICS Interface by adding the following `INCLUDE` statements:

```
INCLUDE NMQLIB(NMQTAB)  
INCLUDE MQLIB(CSQCSTUB)
```

CSQCSTUB is the IBM MQ stub for CICS provided in the IBM MQ library.

- Modify the JCL used to link your **environment-dependent nucleus** for all other environments besides CICS by adding the following `INCLUDE` statements:

```
INCLUDE NMQLIB(NMQTAB)  
INCLUDE MQLIB(CSQBSTUB)
```

CSQBSTUB is the IBM MQ stub for batch and TSO provided in the IBM MQ library. This is also applicable for Natural under Com-plete.

**Step 4: Load the DDMs and the Natural Example Objects**

(Job I061, Step 3410)

Load the DDMs and Natural example objects specific to Natural Messaging from the `NMQvrs.INPL` data set into the Natural system file by using the Natural INPL utility.



# XV

## Installing Natural Security on z/OS

---





# 18

## Installing Natural Security on z/OS

---

■ Prerequisites .....	226
■ Installation Medium .....	226
■ Installation Procedure .....	227
■ Installation Verification .....	230

This document describes the steps for installing Natural Security (product code NSC) on z/OS.

### **Related Topic:**

For information on the features and functions provided by Natural Security, see the *Natural Security* documentation.

### **Notation *vrs* or *vr*:**

When used in this document, the notation *vrs* or *vr* represents the relevant product version (see also Version in the *Glossary*).

## **Prerequisites**

---

See [General Prerequisites and System Support](#) in the section *Overview of the Installation Process*.

### **Additional Prerequisites for Natural Security in a Heterogeneous Environment**

In addition to the prerequisites referred to above, the following software must be installed to use Natural Security in a heterogeneous environment:

- Entire Net-Work
- Natural Security for z/OS

The following software must be installed as required:

- Natural Security for Linux
- Natural Security for Windows

For further information, see *Using Natural Security on Multiple Platforms* in the *Natural Security* documentation.

## **Installation Medium**

---

The [installation medium](#) contains the following data sets required for product installation:

Data Set Name	Contents
NSCvrs.LICS	Load modules for the z/OS license check software containing the LICUTIL license utility  The placeholder <i>vrs</i> in the library name represents the version of the license check software, which is not necessarily the same as the version of Natural.  For detailed information on the license check software and the LICUTIL utility, see <i>Mainframe Product Licensing</i> .
NSCvrs.SYSL	Natural Security log file
NSCvrs.INPL	Natural objects
NSCvrs.VINI	Natural Security FDIC initialization file for VSAM system files

Copy the data sets into your environment as described in [Copying Data Sets to a z/OS Disk](#) in the section *Installing Natural*.

### Sample Jobs

Sample installation jobs are contained in the NATvrs.JOBS data set and are prefixed with the product code. The data set is provided on the installation medium supplied for base Natural.

## Installation Procedure

Be sure to read [Installation Process and Major Natural Features](#) before you start the installation procedure.

### Note for the Reinstallation:

- When you repeat a Natural Security installation, only the Natural objects are replaced; the Natural Security data defined for SYSSEC and DBA is *not* reset to the values defined after the initial installation. You can use the **Natural Security Recover** function of the Natural **INPL utility** to reset the data.

This section describes the actual installation steps.

- [Step 1: Prepare, Convert, Assemble and Link the License File](#)
- [Step 2: Load the FSEC System File Definition](#)
- [Step 3: Load the Log File](#)
- [Step 4: Load the Logon and Error Log File](#)
- [Step 5: Build the Natural Parameter Module](#)

- [Step 6: Load New Natural Objects](#)

## Step 1: Prepare, Convert, Assemble and Link the License File

(Job I007, Steps 9901, 9902, 9904)

You must install a valid Natural Security license file. For detailed information on the license file and product licensing, see *Mainframe Product Licensing*.

1. Copy the license file from the installation medium to disk or transfer it from the PC as described in *Transferring a License File from PC to a z/OS Host Using FTP* in *Mainframe Product Licensing*.
2. Check, convert, assemble, and link the license file:

Step 9901	Check the license file <code>NSCvrs.LICS</code> . This job executes the CHECK function of the LICUTIL license utility.
Step 9902	Convert the license file into an assembler source. This job executes the MAKE function of the LICUTIL license utility.
Step 9904	Assemble and link the assembler source to generate load module NSCLIC. This module is then linked to the nucleus in <a href="#">Job I060</a> (see below).

The functions and option settings provided by LICUTIL are described in *Using the License Utility: LICUTIL* in *Mainframe Product Licensing*.



**Caution:** Natural Security is not enabled unless you install a valid Natural Security license file. Trying to activate Natural Security without a valid license file results in warnings or errors at session start.

## Step 2: Load the FSEC System File Definition

(Job I050, Step 9900)

Skip this step if you want to use an existing Natural FSEC system file.

Skip this step if you want to load the FSEC system file into a VSAM file system. In this case, refer to [Installing Natural for VSAM](#). See also *Natural for VSAM with Natural Security in the Database Management System Interfaces* documentation for restrictions on the use of the FSEC system file in a VSAM environment.

- Load the new Natural FSEC system file definition:

1. Set the System Maintenance Aid (SMA) parameter NSC-FIRST-INSTALL to Y (Yes). This is the default setting.
2. Specify the database ID and file number of the Adabas file where to load the FSEC system file by using the Adabas ADALOD utility.

In addition, you must specify this database ID and file number in the Natural parameter module as described in [Step 5: Build the Natural Parameter Module](#).

3. Load the FSEC system file definition contained in the NATvrs.SYSF data set by using the Adabas ADALOD utility.

The following ADALOD utility parameter must *not* be changed:

```
ISNREUSE=YES
```

### Step 3: Load the Log File

(Job I050, Step 9901)

This step only applies if Adabas is installed and if the Natural Security function **Logging of maintenance functions** (see the *Natural Security* documentation) is to be used. It creates the log file to be used by the function.

- Load the log file by using the Adabas ADALOD utility. Input for ADALOD is the NSCvrs.SYSL data set.

### Step 4: Load the Logon and Error Log File

(Job I050, Step 9902)

This step only applies if Adabas is installed and if the Natural Security function **Store Logon and Error Data on Separate System Files** (see the *Natural Security* documentation) is to be used. It creates the logon and error log file to be used by the function.

- Load the logon and error log file by using the Adabas ADALOD utility. Input for ADALOD is the NATvrs.SYSF data set.

### Step 5: Build the Natural Parameter Module

(Jobs I060, I080)

1. Specify the following profile parameter in your Natural parameter module:

```
FSEC=(database-id,file-number)
```

where *database-id* and *file-number* are the database ID and file number of either the new FSEC system file loaded in [Step 2](#) or your existing FSEC system file.

The FSEC profile parameter is described in the *Parameter Reference* documentation.

Repeat Job I080 for all your TP monitors.

2. Assemble and link your Natural parameter module.

### Step 6: Load New Natural Objects

(Job I061, Step 0102 or Step 9905)

#### For the migration installation (Step 0102):

1. Set the System Maintenance Aid (SMA) parameter `NSC-FIRST-INSTALL` to N (No). The default setting is Y (Yes).
2. Load the Natural objects specific to Natural Security from the `NSCvrs.INPL` data set into the appropriate Natural libraries in your `FNAT` system file by using the Natural [INPL utility](#).

Once this step has been performed, it is not possible to remove Natural Security from the Natural system file; to remove Natural Security from the system file, you would have to delete the entire contents of the system file and reinstall all Natural components again.

#### For the initial installation (Step 9905):

1. Set the System Maintenance Aid (SMA) parameter `NSC-FIRST-INSTALL` to Y (Yes).
2. Load the Natural objects specific to Natural Security from the `NSCvrs.INPL` data set into the appropriate Natural libraries in your `FNAT` system file by using the Natural [INPL utility](#).

When you load the contents of the `NSCvrs.INPL` data set for the first time, this step creates the following security profiles and relationships:

- A library security profile with the library ID `SYSSEC`. The library is people-protected (**People-protected** set to Y and **Terminal-protected** set to N).
- A user security profile with the user ID `DBA`, the user type Administrator, and the password set to `DBA`.

The user `DBA` is linked to the library `SYSSEC` (ordinary link, no special link).

## Installation Verification

---

Natural Security is operational after [Step 6: Load New Natural Objects](#) of the *Installation Procedure* has been completed successfully.

For the initial installation, proceed as described in the section *First Steps After the Installation* in the *Natural Security* documentation. If you upgrade from a previous Natural Security version, you can skip the steps described in this section.

# XVI

## Installing Natural SAF Security on z/OS

---





# 19

## Installing Natural SAF Security on z/OS

---

■ Prerequisites .....	234
■ Installation Medium .....	234
■ Installation Procedure .....	235
■ Installation Verification .....	241

This document describes the steps for installing Natural SAF Security (product code NSF) on z/OS.

### Related Topic:

For information on the features and functions provided by Natural SAF Security, see the *Natural SAF Security* documentation.

### Notation *vrs* or *vr*:

When used in this document, the notation *vrs* or *vr* represents the relevant product version (see also Version in the *Glossary*).

## Prerequisites

---

Supported versions of the following products must be installed before you can install Natural SAF Security:

- [Natural Security](#)
- Adabas
- Adabas Limited Libraries
- SAF-compliant security system

See also [General Prerequisites and System Support](#) in the section *Overview of the Installation Process*.

## Installation Medium

---

The [installation medium](#) contains the following data sets required for product installation:

Data Set	Contents
NSF <i>vrs</i> .LOAD	Load modules
NSF <i>vrs</i> .INPL	Natural objects

Copy the data sets into your environment as described in [Copying Data Sets to a z/OS Disk](#) in the section *Installing Natural*.

### Sample Jobs

Sample installation jobs are contained in the NAT*vrs*.JOBS data set and are prefixed with the product code. The data set is provided on the installation medium supplied for base Natural.

## Installation Procedure

Be sure to read *Installation Process and Major Natural Features* before you start the installation procedure.

- [Step 1: Load the Natural Objects](#)
- [Step 2: Build the Natural Parameter Module](#)
- [Step 3: Relink the Nucleus](#)
- [Step 4: Install the SAF Server](#)

### Step 1: Load the Natural Objects

(Job I005)

- Load the Natural objects specific to Natural SAF Security from the `NSFvrs.INPL` data set into the appropriate Natural libraries in your `FNAT` system file by using the Natural INPL utility.

### Step 2: Build the Natural Parameter Module

(Job I060, Step 0010)

Build the Natural parameter module. The parameters and macros mentioned in this section are described in the *Parameter Reference* documentation.

1. Specify the following with the `NTDS` macro:

```
NTDS NSFSIZE,8
```

8 KB is the minimum `NSFSIZE` value. Depending on your usage of Natural SAF Security, a higher value may be required, which can be calculated as follows:

$4 \text{ KB} + (e * 17 \text{ bytes}) + ((p + r) * 8 \text{ bytes})$ , rounded up to the next KB

where:

$e$  is the number of protected environments,  
 $p$  is the number of protected Natural objects,  
 $r$  is the number of protected RPC services.

You can also use the dynamic profile parameter `DS` to specify `NSFSIZE` at the start of a Natural session:

```
DS=(NSFSIZE,8)
```

2. If you want to use Natural SAF Security to control the execution of Natural objects, specify the following in the `NTRDC` macro of the Natural parameter module:

```
NTRDC SIZE=2,EXIT=(RDCEX3,2000)
```

You can also use the corresponding dynamic profile parameter `RDC` to specify the parameter at the start of a Natural session:

```
RDC=(SIZE=2,EXIT=(RDCEX3,2000))
```



**Note:** If this feature is used, you have to either link the Natural SAF Security module `NSFNUC` to the Natural parameter module or to the nucleus (in the case of an environment-independent nucleus, to the environment-independent part).

3. Assemble and link the Natural parameter module.

### Step 3: Relink the Nucleus

(Job I060, I080)

Adapt the link steps for Natural:

1. Add the following `INCLUDE` statement to the link of the nucleus to include Natural SAF Security modules:

```
INCLUDE NSFLIB(NSFNUC)
```

If you are using a shared nucleus, include this statement in the link of the shared part.

2. Add the corresponding `DD` statement:

```
//NSFLIB DD DSN=NSFvrs.LOAD,DISP=SHR
```

3. Relink your nucleus as described in [Link the Nucleus](#) in *Installing Natural*.

## Step 4: Install the SAF Server

The SAF Server also known as the SAF Security Daemon executes in its own address space as a target in the network. Operating within the daemon is the SAF Security Kernel. The SAF Security Daemon and the SAF Security Kernel are delivered with the Adabas Limited Libraries (product code WAL).

Refer to the *SAF Security Kernel* documentation for information on how to install the SAF Security Kernel in daemon installation mode and how to configure it using the SAFCFG configuration module.

For the correct operation of Natural SAF Security you must consider the following SAFCFG parameters.

### GWDBID: Node ID of the SAF Security Daemon

Parameter	Description	Syntax
GWDBID	<p>Node ID of the SAF Security Daemon.</p> <p>The node ID defined for GWDBID must be the same as the node ID defined to the SAF Security Daemon runtime parameter NODE= (assigned during the installation of the SAF Security Kernel in daemon mode) and the Server ID defined in the General NSF Options 1 screen of the <i>Administrator Services</i>.</p>	GWDBID={ <u>1234</u>   nnnnn }

### GWSIZE: Storage Size for Caching User Information

Parameter	Description	Syntax
GWSIZE	<p>The amount of storage in kilobytes used for caching user information.</p> <p>Generally, size this parameter based on approximately 512 bytes per user.</p> <p>The number of cached checks set by SAFCFG parameters NANUPG, NANURP, NANUSF, and NANUTC affects the usage of this storage. Refer to the corresponding explanation below for more information on each of these parameters.</p> <p>Use <i>SAF Online Services</i> to determine the efficiency of the current size by monitoring the number of times a user area is overwritten in the <i>System Statistics</i> menu option.</p>	GWSIZE={ <u>256</u>   nnnn }

**NACKPG: Programming Object Protection****NACKRP: RPC Services Protection****NACKSF: Environment Protection****NACKTC: Library Protection**

Parameter	Description	Syntax
NACKPG NACKRP NACKSF NACKTC	<p>These parameters are redundant.</p> <p>The protection options originally offered by these parameters can only be set online using the General NSF Options 2 screen of the <i>Administrator Services</i>.</p> <p>Any value (Y or N) defined to these parameters is ignored.</p> <p>When Natural SAF Security first connects to the SAF Security Daemon, the administrator defined protection options are dynamically passed to the SAF Security Daemon.</p>	NACKxx={ <u>N</u>   Y }

**NACLAP: Resource Class Name for User-Defined Resources**

Parameter	Description	Syntax
NACLAP	<p>The name of the resource class used in authorization checks against User-Defined Resources.</p> <p>The name can be up to eight alphanumeric characters.</p> <p>Refer to <i>User-Defined Resources</i> for more information.</p>	NACLAP={ <u>NPGSAG</u>   aa . . }

**NACLPG: Resource Class Name for Programming Objects**

Parameter	Description	Syntax
NACLPG	<p>The name of the resource class used in authorization checks against Programming Objects.</p> <p>The name can be up to eight alphanumeric characters.</p> <p>Refer to <i>Programming Objects</i> for more information.</p>	NACLPG={ <u>NPGSAG</u>   aa . . }

**NACLRP: Resource Class Name for RPC Services**

Parameter	Description	Syntax
NACLRP	<p>The name of the resource class used in authorization checks against RPC Services.</p> <p>The name can be up to eight alphanumeric characters.</p> <p>Refer to <i>RPC Services</i> for more information.</p>	NACLRP={ <u>NRPSAG</u>   aa.. }

**NACLSF: Resource Class Name for Environments**

Parameter	Description	Syntax
NACLSF	<p>The name of the resource class used in authorization checks against Environments.</p> <p>The name can be up to eight alphanumeric characters.</p> <p>Refer to <i>Environments</i> for more information.</p>	NACLSF={ <u>NSFSAG</u>   aa.. }

**NACLTC: Resource Class Name for Libraries**

Parameter	Description	Syntax
NACLTC	<p>The name of the resource class used in authorization checks against Libraries.</p> <p>The name can be up to eight alphanumeric characters.</p> <p>Refer to <i>Libraries</i> for more information.</p>	NACLTC={ <u>NTCSAG</u>   aa.. }

**NAFLEN: Format of Database ID and File Number in Environment Profiles**

Parameter	Description	Syntax
NAFLEN	<p>The format of the Database ID and File number in Environment resource profiles.</p> <p>Valid values are:</p> <ul style="list-style-type: none"> <li>■ 0 – 3 digits with leading zeros</li> <li>■ 1 – 5 digits with leading zeros</li> </ul> <p><b>Note:</b> Set this parameter to 1 to support 5-digit large databases and file numbers.</p> <p>Refer to <i>Environments</i> for more information.</p>	NAFLEN={ <u>0</u>   1 }

**NANUPG: Number of cached Programming Object Checks**

Parameter	Description	Minimum	Maximum	Syntax
NANUPG	<p>This is the number of successful Programming object checks to be cached.</p> <p>Each cached check takes approximately 23 bytes from the storage size specified by the SAFCFG parameter GWSIZE.</p> <p>Use <i>SAF Online Services</i> to determine the efficiency of the current value by monitoring the number of checks overwritten in the <i>System Statistics</i> menu option.</p> <p>For more information on programming objects, refer to the <i>Protect Natural Modules</i> option in <i>Library Options</i>.</p>	0	32767	NANUPG={Q nnnnn}

**NANURP: Number of cached RPC Service Checks**

Parameter	Description	Minimum	Maximum	Syntax
NANURP	<p>This is the number of successful RPC service checks to be cached.</p> <p>Each cached check takes approximately 26 bytes from the storage size specified by the SAFCFG parameter GWSIZE.</p> <p>Use <i>SAF Online Services</i> to determine the efficiency of the current value by monitoring the number of checks overwritten in the <i>System Statistics</i> menu option.</p> <p>For more information on RPC service checks, refer to <i>RPC Options</i>.</p>	0	32767	NANURP={Q nnnnn}

**NANUSF: Number of cached Environment Checks**

Parameter	Description	Minimum	Maximum	Syntax
NANUSF	<p>This is the number of successful Environment checks to be cached.</p> <p>Each cached check takes approximately 40 bytes from the storage size specified by the SAFCFG parameter GWSIZE.</p> <p>Use <i>SAF Online Services</i> to determine the efficiency of the current value by monitoring the number of checks overwritten in the <i>System Statistics</i> menu option.</p>	0	32767	NANUSF={Q nnnnn}



Parameter	Description	Minimum	Maximum	Syntax
	For more information on Environment checks, refer to <i>Environment Options</i> .			

### NANUTC: Number of cached Library Checks

Parameter	Description	Minimum	Maximum	Syntax
NANUTC	<p>This is the number of successful Library checks to be cached.</p> <p>Each cached check takes approximately 10 bytes from the storage size specified by the SAFCFG parameter GWSIZE.</p> <p>Use <i>SAF Online Services</i> to determine the efficiency of the current value by monitoring the number of checks overwritten in the <i>System Statistics</i> menu option.</p> <p>For more information on Library checks, refer to <i>Library Options</i>.</p>	0	32767	NANUTC={ <u>Q</u>   nnnnn}

## Installation Verification

Natural SAF Security is operational after [Step 4: Install the SAF Server](#) of the *Installation Procedure* has been completed successfully.

After the installation, proceed as described in *Activating Natural SAF Security* in the *Natural SAF Security* documentation.



# XVII

## Installing Natural Advanced Facilities on z/OS

---

This document describes the installation of Natural Advanced Facilities (product code NAF) on z/OS.

[Installing Natural Advanced Facilities under CICS on z/OS](#)

[Installation Verification for Natural Advanced Facilities under CICS on z/OS](#)

[Installing Natural Advanced Facilities under IMS TM on z/OS](#)

### **Related Topic:**

For information on the features and functions provided by Natural Advanced Facilities, see the *Natural Advanced Facilities* documentation.

### **Notation** *vrs* or *vr*:

When used in this document, the notation *vrs* or *vr* represents the relevant product version (see also Version in the *Glossary*).



# 20

## Installing Natural Advanced Facilities under CICS on z/OS

---

■ Prerequisites for CICS .....	246
■ Installation Medium for CICS .....	246
■ Installation Procedure for CICS .....	247

This document describes the steps for installing Natural Advanced Facilities under CICS on z/OS.

## Prerequisites for CICS

---

Supported versions of the following products must be installed before you can install Natural Advanced Facilities:

- **Natural CICS Interface**
- **Natural for VSAM** if a VSAM file is to be used as a spool file

See also [General Prerequisites and System Support](#) in the section *Overview of the Installation Process*.

## Installation Medium for CICS

---

The **installation medium** contains the following data sets required for product installation:

Data Set Name	Contents
NAFvrs.LOAD	Load modules
NAFvrs.SRCE	Source modules and macros
NAFvrs.SYSF	Natural FSP00L system file definition
NAFvrs.INPL	Natural objects
NAFvrs.ERRN	Natural error messages

Copy the data sets into your environment as described in [Copying Data Sets to a z/OS Disk](#) in the section *Installing Natural*.

### Sample Jobs

Sample installation jobs are contained in the NATvrs.JOBS data set and are prefixed with the product code. The data set is provided on the installation medium supplied for base Natural.

## Installation Procedure for CICS

---

Be sure to read *Installation Process and Major Natural Features* before you start the installation procedure.

- Step 1: Define the CICS RDO Definitions
- Step 2: Prepare a VSAM Cluster for the Spool File
- Step 3: Load the FSPPOOL System File Definition for Adabas
- Step 4: Build the NAFPARMC Parameter Module
- Step 5: Build the Natural Parameter Module
- Step 6: Link the Nucleus
- Step 7: Load the Natural Objects
- Step 8: Load the Natural Error Messages
- Step 9: Create a Separate Thread Group for Printer Transaction
- Step 10: Define Natural Advanced Facilities for Natural Security
- Step 11: Start Natural
- Step 12: Create the NATSPOOL Environment
- Step 13: Define Natural Advanced Facilities for VTAM/SNA
- Step 14: Define Natural Advanced Facilities for VTAM/non-SNA

### Step 1: Define the CICS RDO Definitions

(Job I005)

This step only applies when using VSAM system files.

- Define the CICS RDO definitions for the sample VSAM files:

Add the Natural Advanced Facilities spool files (SP00L, SP00LA, SP00LB, SP00LC, SP00LD and SP00LE) to your FCT.

For performance reasons, we strongly recommend you to specify a transaction ID for the spool server, which is different from that of the terminal task. It is then possible to dedicate special threads to the spool server.

If you want to convert an existing VSAM spool file, the FCT must contain the entries for this spool file. The cluster names of the new and the old versions must be different. The VSAM database ID and file number as well as the VSAM DD names must be unique.

## Step 2: Prepare a VSAM Cluster for the Spool File

(Job I008, Steps 0300 - 0311)

This step only applies when using VSAM system files.

- Define and initialize a VSAM cluster to be used as the spool file (FSP00L) and five alternate indices.

## Step 3: Load the FSP00L System File Definition for Adabas

(Job I050, Step 0300)

This step only applies when using Adabas system files.

Skip this step if you want to use an existing spool file of Natural Advanced Facilities.

Load the new Natural FSP00L system file definition contained in the `NAFvrs.SYSF` data set by using the Adabas ADALOD utility.

## Step 4: Build the NAFPARMC Parameter Module

(Job I055, Step 0305)

The use of the NAFPARMC parameter module is optional. Alternatively, you can set the server options with Function 30 (see the *Natural Advanced Facilities* documentation) of the SYSP00L application.

- Modify, assemble and link the NAFPARMC module.

## Step 5: Build the Natural Parameter Module

(Jobs I060, I080)

1. Modify the parameters FSP00L, NTPRINT, NAFUPF and NAFSIZE in the Natural parameter module according to your site requirements. For more information on these parameters, see *NATSP00L Initialization* in the *Natural Advanced Facilities* documentation.
2. Assemble and link the Natural parameter module.

## VSAM System Files

The following additional step applies when using VSAM system files:

- Set the FSP00L parameter as follows:



```
FSP00L=(vsam-dbid,fnr-fspool,dd-name-fspool)
```

where:

*vsam-dbid* is the database ID of the VSAM file to be used as the spool file,

*fnr-fspool* is the file number of the VSAM file to be used as the spool file,

*dd-name-fspool* is limited to seven characters.

## Step 6: Link the Nucleus

(Jobs I060, I080)

- Add the following `INCLUDE` statements to the link steps for Natural and link-edit the executable module:

INCLUDE NAFLIB(NAFAF)
INCLUDE NAFLIB(NAFNUC)
INCLUDE SMALIB(NAFPARMC)
(optional)

The link-edit of the load module containing Natural Advanced Facilities can be done in any of the following ways:

- Include all modules of Natural Advanced Facilities, that is, `NAFNUC`, `NAFAF` and, optionally, `NAFPARMC` in the link-edit of Natural.



**Note:** If a shared nucleus is created, the modules can be included in the shared nucleus.

- Link-edit `NAFNUC`, `NAFAF` and, optionally, `NAFPARMC` and an alternative Natural parameter module as a separate module with the mandatory name `CMPRMTB` specified in the `ENTRY` statement. The name of the resulting module is optional.



**Note:** This way of link-editing only applies if an alternate parameter module (`PARM=parameter`) is used. If so, an additional CICS PPT entry with `PROGRAM=name` is required.

- Link-edit `NAFNUC`, `NAFAF` and, optionally, `NAFPARMC` as a separate module with the mandatory name `NATAM08` specified in the `ENTRY` statement. The name of the resulting module is optional. If it is different from `NATAM08`, however, it must be specified as an alias name in the `NTALIAS` macro of the Natural parameter module.



**Note:** This way of link-editing only applies if the `CSTATIC` and `RCA` profile parameters (see the *Parameter Reference* documentation) are used. If so, an additional CICS PPT entry with `PROGRAM=name` is required.

The following additional step applies when using VSAM system files.

- Add the following `INCLUDE` statement to all links of the nucleus:

```
INCLUDE NVSLIB(NVSFSP0)
```

## Step 7: Load the Natural Objects

(Job I061, Step 0300)

- Load the Natural objects specific to Natural Advanced Facilities from the `NAFvrs.INPL` data set into the Natural system files `SYSPOOL` and `SYSPRINT` by using the Natural **INPL utility**.

Ensure that the INPL load function finishes with the message:

```
Natural Advanced Facilities initialized by INPL
```

If this initialization fails, various problems will be encountered at execution time.

The maps contained on the data set are provided in source form so that you can modify them according to your requirements (for example, translate the maps from English into another language). If you modify these maps, ensure that all fields have the same format/length/relative position in the map. Failure to abide by this restriction will result in an invalid system.

## Step 8: Load the Natural Error Messages

(Job I061, Step 0304)

- Load the Natural error messages specific to Natural Advanced Facilities from the `NAFvrs.ERRN` data set into the Natural `FDIC` system file by using the `ERRLODUS` program of the Natural `SYSERR` utility (described in the *Utilities* documentation).

## Step 9: Create a Separate Thread Group for Printer Transaction

(Job I070, Steps 2245, 2250, and Job I080)

We recommend that you establish a separate thread group for the Natural Advanced Facilities printer transaction. To do so, perform these steps:

1. Modify the Natural CICS Interface system directory (Step 2245):

Include a definition of the Natural Advanced Facilities printer thread group into the Natural CICS Interface system directory.

2. Relink the modified Natural CICS Interface system directory (Step 2250).

Repeat linking of the Natural CICS Interface system directory.

See also *Build the Natural CICS Interface System Directory Module* in *Installing Natural CICS Interface on z/OS* in the *Natural Installation* documentation.

## Step 10: Define Natural Advanced Facilities for Natural Security

This step must be performed only if Natural Advanced Facilities is being installed in a Natural Security environment.

- Define SYSP00L to Natural Security with the startup program MENU.



**Note:** The physical CICS printers and the application SYSPRINT need not be defined to Natural Security. The Natural Security logon processing will identify the NATSP00L spool server and perform a simplified logon to SYSPRINT, that is, without any further security checks. In this way, maintenance efforts and the number of Adabas calls at the start of the spool server are considerably reduced. Any logon to SYSPRINT attempted by users other than the NATSP00L spool server will be rejected by Natural Security, regardless of whether SYSPRINT is defined to it or not.

## Step 11: Start Natural

- Start Natural and add the user profile, as defined in the NAFUPF parameter of the Natural parameter module, to the SYSP00L file by using Function 31.1 (described in the *Natural Advanced Facilities* documentation).



**Note:** A NAT7201 message is issued at the start of the session indicating that the profile has not yet been added to the SYSP00L file.

## Step 12: Create the NATSPPOOL Environment

- Initialize a new NATSPPOOL environment as described in *NATSPPOOL Initialization* in the *Natural Advanced Facilities* documentation.

## Step 13: Define Natural Advanced Facilities for VTAM/SNA

This step must be performed only if Natural Advanced Facilities is to be used in conjunction with VTAM/SNA printers.

- Define devices in the TCT with a RELREQ=YES. This will ensure that VTAM printers are released at the end of printout time when devices are shared with other CICS, TSO or BATCH regions, or with JES.
- Define TRMSTAT=INTLOG or CREATESESS=YES for the printer to allow EXEC CICS START requests to create a session.
- Ensure that the devices have the SHARE option generated into the controller VTAM specifications.

## Step 14: Define Natural Advanced Facilities for VTAM/non-SNA

This step must be performed only if Natural Advanced Facilities is to be used in conjunction with VTAM/non-SNA printers.

1. Include TRMSTAT=TRANSCIVE in the TCT definition for the device.
2. Set the VTAM definition for the device parameter ISTATUS to ACTIVE.

# 21

## Installation Verification for Natural Advanced Facilities

### under CICS on z/OS

---

■ System Testing .....	254
■ NATSPOOL Reason Codes .....	256
■ NATSPOOL Initialization Console Messages .....	257
■ NATSPOOL Print Server Messages .....	258
■ NATSPOOL Abend Codes .....	258

You can verify the successful installation of Natural Advanced Facilities by following the instructions provided in this section.

## System Testing

---

You can perform the following steps to determine whether Natural Advanced Facilities functions correctly.

### ➤ To print a test report

- In the appropriate logical printer, set the `Disposition` to `K` for testing.

Log on to the Natural system library `SYSP00L` and execute the programs `NTEST` and `SPPTTEST`. These programs contain `WRITE (1)` statements.

Or:

Create test reports with Function 42 described in the *Natural Advanced Facilities* documentation.

### ➤ To proceed if a test report cannot be printed

- 1 Check that the CICS printer status is `IN SERVICE`.
- 2 Use the CICS message switching transaction `CMSG` to route a message to the specified printer:

```
CMSG 'message',ROUTE=term-id,SEND
```

where `term-id` is the terminal identification of the CICS printer as specified in the TCT.

- 3 If Natural Security is installed, check whether logon error records (of the `NATSP00L` spool server `NATP`) have been written to the Natural Security system file. The maintenance system for these error records can be invoked by entering `ERROR` in the command line of Natural Security.
- 4 Check that the standard Natural `LOGON` object has *not* been replaced. The `NATSP00L` spool server `NATP` must be able to execute the `SVPCIC01` module in the `SYSPRINT` library.

Also check whether the `LOGON` user exit causes the `LOGON` of the spool server to `SYSPRINT` to terminate.

- 5 Check that the catalog dates of the objects in `SYSPRINT` and `SYSP00L` are identical to one another.
- 6 Check that the parameters for the spool server match the Natural Advanced Facilities environment. To do so, invoke `MENU` in the `SYSP00L` library and check the **CICS Options** defined with Function 30.5 (see the *Natural Advanced Facilities* documentation).

- 7 Check that neither the external security (EXTSEC operand of CICS PCT) nor the security levels (TRANSEC operand of CICS PCT) are defined for the spool server NATP. This ensures that NATP can be initiated without security violations.
- 8 Check the TCT and VTAM definitions (see [Step 10: Define Natural Advanced Facilities for Natural Security](#), [Step 13: Define Natural Advanced Facilities for VTAM/SNA](#) and [Step 14: Define Natural Advanced Facilities for VTAM/non-SNA](#) in the section *Installing Natural Advanced Facilities under CICS*).
- 9 Allocate a screen device instead of a printer device to the Destination/Form pairing of the first logical printer, execute NTEST in the SYSPPOOL library, and check for error messages on the screen.

On certain devices, the CICS abend ATNI may occur.

Since the Natural Security logon processing checks whether the device is a printer, this test is only possible if Natural Security is *not* installed.

- 10 Start the transaction CEDF for your terminal device and check whether the command EXEC CICS START (to start the spool server) is executed.
- 11 Start the transaction CEDF for your printer device (CEDF terminal ID of printer) and check which commands are executed.
- 12 Check the Natural Advanced Facilities messages on the system operator console and/or in the log file (the destination of messages is defined with Function 30.5 (see the *Natural Advanced Facilities* documentation)).

Console messages sent by the spool server start with:

```
NAF SP-SERV:
```

Console messages sent by the terminal task start with:

```
NAF -
```

- 13 Obtain a NATSPPOOL trace and check which Natural Advanced Facilities modules are called, which Adabas commands are executed, and which return codes are encountered.

## NATSPPOOL Trace using SYSRDC

➤ To obtain an online NATSPPOOL trace by using the Natural SYSRDC utility

- 1 Start a Natural session with the following dynamic parameters:

```
RDCSIZE=100, TRACE=(NATAM08), ITRACE=ON
```

- 2 Log on to the SYSRDC library.
- 3 Execute the following command to select the internal trace type:

```
RDCSET N
```

- 4 Execute the following command to start the trace:

```
RDCSTART
```

- 5 Execute a program which creates a report, for example, NTEST in the SYSPPOOL library.
- 6 Log on to the SYSRDC library.
- 7 Execute the following command to display the trace entries:

```
RDCDISP
```

You will now see when a NATSPPOOL module begins (marked as `BEG`) and ends (marked as `END`) as well as its return code in decimal representation.

After the execution of an Adabas call (marked as `ADA`), you will see the command code, the first byte of the command ID and the return code in decimal representation.

For detailed information on the SYSRDC utility, see the *Utilities* documentation.

---

## NATSPPOOL Reason Codes

---

Errors that may occur during the check for printer availability:

Error	Description
INV REQU	Invalid request
INV ID	Invalid ID
INV ADDR	Invalid address
INV DEVC	Invalid logical device code for page status
ATI REQU	ATI required on NON-ATI terminal
RESO PRO	Resource problem for inter-partition session
INV PROG	Invalid program name
UNAB PER	Unable to perform request
INV TYPE	Type is not LUC
RESO QUI	Resource quiesced by TMP
LOCATERR	Any error different from those listed above



Errors that may occur during the start of the spool server:

Error	Description
TERMIDER	Terminal ID error
TRANIDER	Transaction ID error
SYSIDERR	SYSID error
INVREQ	Invalid request
IOERR	I/O error
LENGERR	Length error
ISCINVRE	ISC invalid request
NOTAUTH	Not authorized
STARTERR	Any error different from those listed above

## NATSPool Initialization Console Messages

Messages that may occur during the initialization of NATSPool:

Message	Text
NAF-01C	ADABAS RCxxx, DBIDxxx, FNRxxx, AT OPEN
NAF-02C	Not used
NAF-03C	ADABAS RCxxx, DBIDxxx, FNRxxx, AT READ REPORT
NAF-04C	ADABAS RCxxx, DBIDxxx, FNRxxx, AT READ PRINTER
NAF-05C	ADABAS RCxxx, DBIDxxx, FNRxxx, AT CLOSE
NAF-06C	ADABAS RCxxx, DBIDxxx, FNRxxx, AT UPDATE REPORT
NAF-07C	ADABAS RCxxx, DBIDxxx, FNRxxx, AT UPDATE PRINTER
NAF-08I	REPORT xxxxxxxxx, JOBxx.xxx, SET -TO BE PRINTED-
NAF-09I	PRINTER xxxx SET -FREE-
NAF-10I	PRINTER xxxx RESTARTS IN 20 SECONDS, DEST=xxxxxxx, FORM=x
NAF-11C	RESTART ERROR NAT xxxx ON PRINTER xxxx

## NATSPPOOL Print Server Messages

---

See the online help for descriptions of the NATSPPOOL print server messages.

➤ **To invoke online help for print server messages**

- 1 In the **Natural Spool Administration Menu**, press PF1.
- 2 Enter function code 99 (miscellaneous information).
- 3 Enter function code 4 (Natural Advanced Facilities SP-SERV messages from spool server).

## NATSPPOOL Abend Codes

---

Abend Code	Reason	Action
NAF1 - INVALID LENGTH	The length of the data to be printed is not positive.	Obtain the dump and contact support.
NAF2 - INVALID LENGTH	The length of the data to be printed is greater than the maximum length of the terminal I/O buffer (TIOBM).	Obtain the dump and contact support.
NAF3 - INVALID RETURN CODE	The return code of the task-end routine CMTSKND is not zero.	Obtain the dump and contact support.
NAF4 - INVALID RETURN CODE	The return code of the print routine CMWTERM is not zero.	Obtain the dump and contact support.

# 22

## Installing Natural Advanced Facilities under IMS TM on z/OS

---

■ Prerequisites for IMS TM .....	260
■ Installation Medium for IMS TM .....	260
■ Installation Procedure for IMS TM .....	260

This document describes the steps for installing Natural Advanced Facilities under IMS TM on z/OS.

## Prerequisites for IMS TM

---

A supported version of the following product must be installed before you can install Natural Advanced Facilities:

- **Natural IMS TM Interface**

See also [General Prerequisites and System Support](#) in the section *Overview of the Installation Process*.

## Installation Medium for IMS TM

---

The **installation medium** contains the following data sets required for product installation:

Data Set Name	Contents
NAFvrs.LOAD	Load modules
NAFvrs.SRCE	Source modules and macros
NAFvrs.SYSF	Natural FSP00L system file definition
NAFvrs.INPL	Natural objects
NAFvrs.ERRN	Natural error messages

Copy the data sets into your environment as described in [Copying Files to a z/OS Disk](#) in the section *Installing Natural*.

### Sample Jobs

Sample installation jobs are contained in the NATvrs.JOBS data set and are prefixed with the product code. The data set is provided on the installation medium supplied for base Natural.

## Installation Procedure for IMS TM

---

Be sure to read [Installation Process and Major Natural Features](#) before you start the installation procedure.

- [Step 1: Load the FSP00L System File Definition](#)
- [Step 2: Build the NAFPARMI Parameter Module](#)
- [Step 3: Build the Natural Parameter Module for the BMP Environment](#)

- [Step 4: Link the Environment-Dependent Nucleus for the BMP Environment](#)
- [Step 5: Build the Natural Parameter Module for the MPP Environment](#)
- [Step 6: Load the Natural Objects](#)
- [Step 7: Load the Natural Error Messages](#)
- [Step 8: Link the Environment-Dependent Nucleus for the MPP Environment](#)
- [Step 9: Define Natural Advanced Facilities for Natural Security](#)
- [Step 10: Start Natural](#)
- [Step 11: Create the MPP Region](#)
- [Step 12: Adapt the IMS TM Environment](#)

### Step 1: Load the FSPPOOL System File Definition

(Job I050, Step 0300)

Skip this step if you want to use an existing spool file of Natural Advanced Facilities.

Load the new Natural FSPPOOL system file definition contained in the `NAFvrs.SYSF` data set by using the Adabas ADALOD utility.

### Step 2: Build the NAFPARMI Parameter Module

(Job I055, Step 0305)

The use of the NAFPARMI parameter module is optional. Alternatively, to set the server options, you can use Function 30 (see the *Natural Advanced Facilities* documentation) of the SYSPPOOL application:

- Modify, assemble and link the NAFPARMI module.

### Step 3: Build the Natural Parameter Module for the BMP Environment

(Job I060)

1. Modify the parameters FSPPOOL, NTPRINT, NAFUPF and NAFSIZE in the Natural parameter module according to your site requirements. For more information on these parameters, see *Natural Profile Parameters for NATSPOOL* in the *Natural Advanced Facilities* documentation.

The Natural parameter module for Natural in a BMP environment must contain a valid `FSPPOOL=(dbid,fnr)` entry where *dbid* is a valid database ID and *fnr* a valid file number. The specified values must be identical to those of Natural in an MPP environment (see [Step 5: Build the Natural Parameter Module for the MPP Environment](#)).

2. Assemble and link the Natural parameter module.

#### Step 4: Link the Environment-Dependent Nucleus for the BMP Environment

(Job I060)

- Link your BMP front-end with the Natural parameter module created in the previous step.

#### Step 5: Build the Natural Parameter Module for the MPP Environment

(Job I060)

1. Modify the parameters `FSP00L`, `NTPRINT`, `NAFUPF` and `NAFSIZE` in the Natural parameter module according to your site requirements. For more information on these parameters, see *Natural Profile Parameters for NATSPOOL* in the *Natural Advanced Facilities* documentation.

The Natural parameter module for Natural in an MPP environment must contain a valid `FSP00L=(dbid,fnr)` entry and the values specified must be identical to those of Natural in a BMP environment (see also [Step 3: Build the Natural Parameter Module for the BMP Environment](#)).

2. Assemble and link the Natural parameter module.

#### Step 6: Load the Natural Objects

(Job I061, Step 0300)

- Load the Natural objects specific to Natural Advanced Facilities from the `NAFvrs.INPL` data set into the Natural system files `SYSPOOL` and `SYSPRINT` by using the Natural [INPL utility](#).

Ensure that the INPL load function finishes with the message:

```
Natural Advanced Facilities initialized by INPL
```

If this initialization fails, various problems will be encountered at execution time.

The maps contained on the data set are provided in source form so that you can modify them according to your requirements (for example, translate the maps from English into another language). If you modify these maps, ensure that all fields have the same format/length/relative position in the map. Failure to abide by this restriction will result in an invalid system.

**Step 7: Load the Natural Error Messages**

(Job I061, Step 0304)

- Load the Natural error messages specific to Natural Advanced Facilities from the `NAFvrs.ERRN` data set into the Natural `FDIC` system file by using the `ERRLODUS` program of the Natural `SYSERR` utility (described in the *Utilities* documentation).

**Step 8: Link the Environment-Dependent Nucleus for the MPP Environment**

(Job I080)

- Include all modules of Natural Advanced Facilities by adding the following `INCLUDE` statements to the link steps for Natural and link-edit the executable module:

```
INCLUDE NAFLIB(NAFAF)
INCLUDE NAFLIB(NAFNUC)
INCLUDE SMALIB(NAFPARMI) (optional)
```



**Note:** If an environment-independent nucleus is created, the modules can be included in the environment-independent nucleus.

**Step 9: Define Natural Advanced Facilities for Natural Security**

This step must be performed only if Natural Advanced Facilities is being installed in a Natural Security environment.

- Define `SYSP00L` to Natural Security with the startup program `MENU`.

**Step 10: Start Natural**

- Start Natural and add the user profile, as defined in the `NAFUPE` parameter of the Natural parameter module, to the `SYSP00L` file by using Function 31.1 (see the *Natural Advanced Facilities* documentation).



**Note:** A `NAT7201` message is issued at the start of the session indicating that the profile has not yet been added to the `SYSP00L` file.

## Step 11: Create the MPP Region

(Job I200, Steps 2502)

- Create the MPP region according to the `NAFJOB` sample member contained on the `NATvrs.JOBS` data set.

## Step 12: Adapt the IMS TM Environment

Adapt the IMS TM environment considering the following requirements:

- The JCL for the BMP printer job must be stored in the appropriate IMS library with the member name specified in the **BMP JCL Member** field of the **IMS TM Options** of Function 30.5 (see the *Natural Advanced Facilities* documentation).
- The BMP must use the input transaction code specified in the **BMP Transaction ID** field of the **IMS TM Options**.
- The BMP must use a PSB with at least two modifiable TP PCBs.
- The input transaction code for the BMP must be defined in the `NTIMSPT` macro of the Natural parameter module with at least one additional TP PCB specified with the `WRKPCBS` keyword subparameter. The keyword subparameters contained in `NTIMSPT` are described in the *Parameter Reference* documentation.
- If the input transaction code for the BMP is generated as WFI, the **Wait for input** field of the **IMS TM Options** must be set to Y (Yes). If the input transaction code for the BMP is *not* generated as WFI, the **Wait for input** field must be set to N (No). For further information, see also *Wait for Input WFI* in the *Natural Advanced Facilities* documentation.

If the input transaction code for the BMP is *not* generated as WFI, the MPP transaction code must be authorized to issue the `/STA REG` command. Otherwise, IMS TM will issue the status code CD when trying to start the BMP.



# XVIII

## Installing Natural Optimizer Compiler on z/OS

---



# 23

## Installing Natural Optimizer Compiler on z/OS

---

■ Prerequisites .....	268
■ Installation Medium .....	268
■ Installation Procedure .....	268
■ Installation Verification .....	270

This document describes the steps for installing the Natural Optimizer Compiler (product code NOC) on z/OS.

### Related Topic:

For information on the features and functions provided by the Natural Optimizer Compiler, see the *Natural Optimizer Compiler* documentation.

### Notation *vrs* or *vr*:

When used in this document, the notation *vrs* or *vr* represents the relevant product version (see also Version in the *Glossary*).

## Prerequisites

---

See [General Prerequisites and System Support](#) in the section *Overview of the Installation Process*.

## Installation Medium

---

The **installation medium** contains the following data set required for product installation:

Data Set Name	Contents
NOC <i>vrs</i> .LOAD	Load modules

Copy the data set into your environment as described in [Copying Data Sets to a z/OS Disk](#) in the section *Installing Natural*.

### Sample Jobs

Sample installation jobs are contained in the NAT*vrs*.JOBS data set and are prefixed with the product code. The data set is provided on the installation medium supplied for base Natural.

## Installation Procedure

---

Be sure to read [Installation Process and Major Natural Features](#) before you start the installation procedure.

- [Step 1: Install the Natural Optimizer Compiler License File](#)
- [Step 2: Build the Natural Parameter Module](#)

■ [Step 3: Relink the Nucleus](#)

### Step 1: Install the Natural Optimizer Compiler License File

In addition to the Natural product license file, a license file is required and must be installed for each environment in which Natural Optimizer Compiler (NOC) runs. For license file NOCvrs.LICS, see [Step 2: Prepare, Convert, Assemble and Link the License File](#).

Natural Optimizer Compiler will not be enabled unless a valid Natural Optimizer license file is installed. Trying to activate the NOC without a valid license file results in warnings or errors at session start.

### Step 2: Build the Natural Parameter Module

(Jobs I060 and I080)

1. Activate the Natural Optimizer Compiler by adding the following macro to your Natural parameter module:

```
NTOPT 'INDX,OVFLW,ZD=OFF'
```

See also *Macro NTOPT* in the *Natural Optimizer Compiler* documentation.

2. Assemble and link the Natural parameter module.

### Step 3: Relink the Nucleus

(Jobs I060, I080)

Adapt the link steps for Natural:

1. Add the following `INCLUDE` statement to the link of the nucleus to include the Natural Optimizer Compiler modules:

```
INCLUDE NOCLIB(NOCNUC)
```

Add the corresponding `DD` statement:

```
//NOCLIB DD DSN=NOCvrs.LOAD,DISP=SHR
```

2. Relink your nucleus as described in [Link the Nucleus](#) in *Installing Natural*.

## Installation Verification

---

You can verify the successful installation of the Natural Optimizer Compiler by performing the following steps:

1. Recatalog an existing program or write a new program and then catalog it.
2. Check the directory information for the program you have just cataloged, by using the following `LIST` system command:

```
LIST DIR object-name
```

The directory information for the specified object will be displayed, showing the size of the machine code at the bottom of the screen.

# XIX

## Installing Natural Connection on z/OS

---





# 24

## Installing Natural Connection on z/OS

---

■ Prerequisites .....	274
■ Installation Medium .....	274
■ Installation Procedure .....	275
■ Installation Verification .....	276

This document describes the steps for installing Natural Connection (product code NTC) on z/OS.

### Related Topic:

For information on the features and functions provided by Natural Connection, see the *Natural Connection* documentation.

### Notation *vrs* or *vr*:

When used in this document, the notation *vrs* or *vr* represents the relevant product version (see also Version in the *Glossary*).

## Prerequisites

---

A supported version of the following product must be installed before you can install Natural Connection:

#### ■ Entire Connection

See the *Installation* section in the *Entire Connection* documentation.

See also [General Prerequisites and System Support](#) in the section *Overview of the Installation Process*.

## Installation Medium

---

The [installation medium](#) contains the following data set required for product installation:

Data Set Name	Contents
NTC <i>vrs</i> .LOAD	Load modules

Copy the data set into your environment as described in [Copying Data Sets to a z/OS Disk](#) in the section *Installing Natural*.

### Sample Jobs

Sample installation jobs are contained in the NAT*vrs*.JOBS data set and are prefixed with the product code. The data set is provided on the installation medium supplied for base Natural.

## Installation Procedure

Be sure to read [Installation Process and Major Natural Features](#) before you start the installation procedure.

- [Step 1: Build the Natural Parameter Module](#)
- [Step 2: Adapt the Link Steps](#)

### Step 1: Build the Natural Parameter Module

(Jobs I060, I080)

1. Adapt the Natural parameter module:

- Specify the keyword subparameter `AM=PC` in the `NTPRINT` macro for all printer files and work files to be used for data transfer between the host and the PC. For example:

```
NTPRINT (7),AM=PC
NETWORK (7),AM=PC
```

- Specify the profile parameter `PC=ON`.

The parameters and the macro are described in the *Parameter Reference* documentation.

2. Assemble and link the Natural parameter module.

### Step 2: Adapt the Link Steps

(Job I080)

Adapt the link steps for online Natural:

1. Add the following `INCLUDE` statement and the corresponding `DD` statement to the link instructions for the linkage editor:

```
INCLUDE NTCLIB(NTCPCAM3)
```

2. Relink your nucleus as described in [Link the Nucleus](#) in *Installing Natural*.

## Installation Verification

---

You can verify the successful installation of Natural Connection by following the instructions below:

1. Invoke Entire Connection on the PC and start the terminal emulation.
2. Use the terminal emulation to invoke Natural on the z/OS machine.
3. Enter the terminal command %+ to activate the PC connection.
4. Use the Natural Object Handler (described in the *Utilities* documentation) to download Natural objects to the PC. For information on transferring Natural objects, see also *Data Transfer* in the section *Terminal Emulation* in the *Entire Connection* documentation.
5. Verify that the downloaded objects are now on your PC.

# XX

## Installing Natural Review

---



# 25

## Installing Natural Review

---

■ Prerequisites .....	280
■ Storage Requirements .....	280
■ Installation Medium .....	281
■ Installation Procedure .....	281
■ Installation Verification .....	289

This document describes the steps for installing Natural Review (product code RNM) on z/OS.

### Related Topic:

For information on the features and functions provided by Natural Review, see the *Natural Review* documentation.

### Notation *vrs* or *vr*:

When used in this document, the notation *vrs* or *vr* represents the relevant product version (see also Version in the *Glossary*).

## Prerequisites

---

See [General Prerequisites and System Support](#) in the section *Overview of the Installation Process*.

## Storage Requirements

---

The Natural Review monitoring system requires CICS shared storage for collecting its monitoring data. For each Natural session, a user account area of 656 bytes is allocated plus space for a Natural call table (NCT). This table is used to track the Natural programs and database calls issued within a transaction. The number of NCT entries is determined by the `NCTSIZE` parameter in the source member `RNMSCB3.A` (see [Step 7: Build the Natural Review System Control Block](#)). Each table entry is 48 bytes long and the table contains 32 entries (default). This yields a total amount of  $656 + 32 * 48 = 2192$  bytes per running session. The storage is reused when the session terminates.

Each active response time report requires a basic control block that is 400 bytes long. Each detail record is 128 bytes long. The maximum number of detail records per report is controlled by the `Number of Records` in the report definition. If the `Transaction Summary` option is set in the report definition, a 64 bytes transaction summary area is allocated for each transaction ID.

After a report has been written to the Natural Review repository file by the history session, all report-dependent storage is released.



## Installation Medium

The **installation medium** contains the following data sets required for product installation:

Data Set Name	Contents
RNMvrs.LOAD	Load modules
RNMvrs.SRCE	Source modules and macros
RNMvrs.SYSF	Natural system file definition
RNMvrs.JOBS	Sample installation jobs
RNMvrs.INPL	Natural objects

Copy the data sets into your environment as described in *Copying Data Sets to a z/OS Disk* in the section *Installing Natural*.

## Installation Procedure

Be sure to read *Installation Process and Major Natural Features* before you start the installation procedure.

- Step 1: Add CICS Control Table Entries for Natural Review
- Step 2: Load the Natural Review Repository File
- Step 3: Migrate an existing Natural Review Repository File
- Step 4: Build the Natural Parameter Module
- Step 5: Link the Nucleus
- Step 6: Load New Natural Objects
- Step 7: Define the SYSRNM Library in Natural Security
- Step 8: Build the Natural Review System Control Block
- Step 9: Link the Natural Review History Session Startup Module
- Step 10: Activate the Natural Review Modules

- [Step 11: Initialize the Natural Review Repository File](#)

## Step 1: Add CICS Control Table Entries for Natural Review

(Job I005, Step 2211)

Define the following CICS table entries with RDO. You may have to include additional parameters according to your requirements. Natural Review supports transaction isolation (that is, it can run in user key).

- [Program Control Table \(PCT\)](#)
- [Processing Program Table \(PPT\)](#)
- [Program List Tables CICS Startup and Shutdown \(PLTPI and PLTSD\)](#)

### Program Control Table (PCT)

1. Define the Natural Review history session start/stop transaction:

```
CEDA DEFINE TRANSACTION(RVH1) PROGRAM(RNMHIST3)
      GROUP(RNMvr)
```

2. Define the Natural Review asynchronous Natural history session transaction:

```
CEDA COPY TRANSACTION(XXXX) GROUP(yyyy) AS(RVH2)
      TO(RNMvr)
```

This copies your existing Natural transaction ID `XXXX` from your Natural definition group `yyyy` as an alias transaction for Natural Review. This definition is optional and you may use the online Natural transaction code `XXXX` as well, but it helps the administrator identify the Natural Review asynchronous history session.

The transaction codes `RVH1` and `RVH2` can be chosen freely (that is, you may change them if required). The Natural session transaction code must be the same as defined with the parameter `NATTRAN` (in this example, `NATTRAN=RVH2`). See [Step 7: Build the Natural Review System Control Block](#) and *Installation Verification* ([Step 3](#)).

### Processing Program Table (PPT)

1. Define the Natural Review history session start/stop program:

```
CEDA DEFINE PROGRAM(RNMHIST3) LANGUAGE(ASSEMBLER)
      GROUP(RNMvr)
```

2. Define the Natural Review system control block:

```
CEDA DEFINE PROGRAM(RNMSCB3) LANGUAGE(ASSEMBLER)
      RESIDENT(YES) GROUP(RNMvr)
```

3. After entering the online definitions, activate them by using `CEDA INSTALL GROUP(RNMvr)`. The new GROUP should be added to the GRPLIST defined for CICS cold start.

### Program List Tables CICS Startup and Shutdown (PLTPI and PLTSD)

This table entry is optional. You can use it for automatic start and termination of the Natural Review history session during CICS startup and shutdown.

1. Define the Natural Review history session start/stop program:

```
DFHPLT TYPE=ENTRY, PROGRAM=RNMHIST3
```

2. Insert the table entry in your assembled PLTPI and/or PLTSD CICS table. This avoids manual starting and stopping of the Natural Review history session (see [Step 7: Build the Natural Review System Control Block](#)).

### Step 2: Load the Natural Review Repository File

(Job I050, Step 2620)

You can skip this step if you have already installed a Natural Review repository file.

The repository file is an Adabas file used for storing response time reports and history data. It is possible to share the repository file across several CICS regions. Any Adabas file can be used to contain the Natural Review repository file. The corresponding file number must be defined to Natural as a logical system file (see [Step 4: Build the Natural Parameter Module](#)). The repository file has to be initialized via Natural (see [Step 11: Initialize the Natural Review Repository File](#)).

- Modify the job as follows before submitting it:
  - Change the data set definitions according to your requirements.
  - Change `DB=dbid` in the Adabas ADARUN statements to the correct database ID.
  - Change `SVC=nnn` to the correct Adabas SVC number.
  - Change the Adabas ADALOD statement to the file number *fnr* of the Adabas file that will contain the Natural Review repository file, and the Natural Review version *vrs* you are running:

```
ADALOD LOAD FILE=fnr,NAME='REPOS-RNMvrs'
```

### Step 3: Migrate an existing Natural Review Repository File

(Job I050, Step 2620)

You can skip this step if you have installed a Natural Review repository file with Step 2 above.

If you migrate from an older Natural Review repository file lower than Natural Version 9.2, then a migration step needs to be performed.

Alternatively, execute an ADADBS Job containing the following cards:

```
//DDKARTE DD *  
ADADBS OPERCOM STOPF=fnr,PURGE  
ADADBS NEWFIELD FILE=fnr  
ADADBS NEWFIELD FNDEF='01,DY,8,A,NU'
```

where you replace *fnr* with the file number of your Natural Review repository file.

### Step 4: Build the Natural Parameter Module

(Job I060, Steps 0010, 0015)

1. Modify the settings of the parameters supplied with the Natural parameter module as follows:

```
RDCSIZE=2  
MADIO=5000  
MAXCL=0  
RCA=NATGWREV  
NTLFILE 180,dbid,fnr
```

where:

RDCSIZE is the Natural profile parameter that determines whether a session is monitored by Natural Review. If you set RDCSIZE=0 (this is the default) for a session, it is *not* monitored by Natural Review.

RCA is the Natural profile parameter required if you want to link the Natural Review monitor interface module separate from the nucleus (see [Step 7: Build the Natural Review System Control Block](#)) by means of the RCA technique.

NTLFILE (or dynamic LFILE parameter) is the macro that determines the Natural Review repository file used by the SYSRNM application for retrieving and maintaining report definitions and storing history report data for the history session. The currently accessed repository file can be changed using the LFILE command within Natural Review (see the *Natural Review* documentation).

*dbid* is the database ID and *fnr* the file number specified in [Step 2: Load the Natural Review Repository File](#).

For details about the parameters mentioned above, see the *Parameter Reference* documentation.

2. Assemble and link the Natural parameter module.

## Step 5: Link the Nucleus

(Job I060, Step 0020)

- Link the nucleus for Natural Review by including the following module from the Natural Review load library `RNMLIB`:

```
INCLUDE RNMLIB(RNMNUC3)
```

Natural Review uses the Natural Data Collector exit interface to get data from Natural. For more information on the `SYSRDC` Data Collector, see the Natural `SYSRDC` utility described in the *Utilities* documentation.

The Natural Review module `RNMNUC3` supports all different ways of statically linked Natural subprograms. For more information about linking the nucleus, see *Linking Natural Objects to the Natural Nucleus* in the *Natural Operations* documentation.

If you run an **environment-independent nucleus** for multiple environments (for example, CICS and batch), link `RNMNUC3` to the environment-dependent nucleus, because Natural Review monitoring runs under CICS only. This prevents unnecessary overload in your non-CICS systems.

- If `RNMNUC3` is not linked to the **environment-dependent nucleus**, the following CICS assembler command level stub from the CICS load library must be linked to `RNMNUC3`:

```
INCLUDE CICSlib(DFHEAI)
```

- Instead of linking `RNMNUC3` to the nucleus, you can link it as a separate module defined with the Natural profile parameter `RCA` (described in the *Parameter Reference* documentation). The following linkage editor statements are then required:

```
MODE RMODE(ANY)
INCLUDE CICSlib(DFHEAI)
INCLUDE RNMLIB(RNMNUC3)
ENTRY NATGWREV
NAME NATGWREV
```

The `MODE` statement is optional. A CICS PPT entry is required for the module `NATGWREV`. It must be specified with the profile parameter `RCA` (see [Step 3: Build the Natural Parameter Module](#)). The module can be shared between multiple Natural nuclei.

## Step 6: Load New Natural Objects

(Job I061, Step 2661)

1. If you want to continue using a profile text object `DEFAULT` you modified according to your requirements, rename your `DEFAULT` object in the `SYSRNM` library before you start loading the new Natural objects.
2. Load the Natural objects specific to Natural Review from the `RNMvrs.INPL` data set into your `FNAT` system file by using the Natural `INPL` utility.

It is sufficient to load the Natural objects only into one `FNAT` system file even if you want to monitor other `FNAT` system files as well.

The Natural Review User Profile Subsystem is initialized when the profile text object `DEFAULT` is copied to the `SYSRNM` library.

3. If you renamed the profile text object `DEFAULT` in the first step, replace the newly loaded `DEFAULT` by this object.

## Step 7: Define the `SYSRNM` Library in Natural Security

This step only applies if Natural Security is installed.

- Define the Natural Review library `SYSRNM` in Natural Security.

You can define a startup menu for the `SYSRNM` library. If the library is `People`-protected, each user of this library must be linked to it.

- Define `REVHIST` as a user of type `PERSON` with a default application of `SYSRNM`. `REVHIST` is used as the user ID by the Natural Review history session.

## Step 8: Build the Natural Review System Control Block

(Job I070, Steps 2622, 2623)

The Natural Review System Control Block `RNMSCB3` is defined as a program in `CICS`. `RNMSCB3` is not an executable program. Its storage is used by Natural Review as the common anchor and control point for all monitored Natural sessions and reports within one `CICS` address space. There are some installation-specific generation parameters you can specify in object `RNMSCB3` in the Natural Review source library.

- Set the following parameters in `RNMSCB3` according to your requirements:

Parameter	Explanation	
NATTRAN=	This is the Natural/CICS transaction code for the Natural Review history session. You must specify this parameter to set the correct Natural transaction code (see <a href="#">Step 1: Add CICS Control Table Entries for Natural Review</a> ).	
NPARMS=	Additional dynamic Natural parameters for the Natural Review history session. This parameter is optional.	
CLOSE=	This parameter determines whether any started Natural Review reports are closed automatically during the termination of the Natural Review history session. There are two possible values:	
	CLOSE=YES	All started reports are closed. This is the default setting.
	CLOSE=NO	Started reports are not closed.
DATE=	The date format used in the records stored in the Natural Review repository file. There are two possible values:	
	DATE=OLD	The date format is <i>YY/MM/DD</i> . This is the default setting.
	DATE=NEW	The date format is <i>YYYYMMDD</i> .
EMPTY=	This parameter determines whether empty history records are stored in the Natural Review repository file. A record is considered empty if no transactions occurred within the report time interval. There are two possible values:	
	EMPTY=YES	Empty history records are stored.
	EMPTY=NO	Empty history records are not stored. This is the default setting.
NCTSIZE=	<p>This parameter determines the number of entries in the Natural Call Table (NCT) of Natural Review. The NCT is allocated in CICS shared storage and is used to track the usage of the Natural programs per session.</p> <p>Possible values: 0 - 128.</p> <p>The default setting is NCTSIZE=32.</p>	

- Modify and run the job `RNMI070` to generate the Natural Review System Control Block. The module must be linked with the `NORENT` option. The target link library can be any library defined to CICS.

## Step 9: Link the Natural Review History Session Startup Module

(Job I070, Step 2625)

Natural Review history data is written to the Natural Review repository file by an asynchronous (that is, not terminal-bound) Natural session.

- Modify and run job `RNMLINK` in the Natural Review source library.

It links the CICS-dependant history session startup module `RNMHIST3`. The target link library can be any library defined to CICS.

There can be only one history session within one CICS address space. The Natural objects specific to Natural Review (see [Step 5: Load New Natural Objects](#)) must be loaded to the `FNAT` system file running with the history session.

## Step 10: Activate the Natural Review Modules

- Use the following `CEMT` transaction to activate the nucleus module to which `RNMNUC3` and the modified the Natural parameter module are linked:

```
CEMT SET PROGRAM(. . . .) NEWCOPY
```

- Restart CICS if you cannot activate the nucleus module.

## Step 11: Initialize the Natural Review Repository File

Skip this step if your Natural Review repository file is already initialized.

- Initialize the repository file after loading it in [Step 2: Load the Natural Review Repository File](#):

Logon to the `SYSRNM` library and enter the following at the `NEXT` prompt:

```
INSTALL NM
```

The following messages will then appear:

```
Now creating sample report system response time
Now creating sample report highest response
Natural Review repository initialization complete.
Press <ENTER> to continue
```

During the initialization process, two default (sample) response time reports are added as shown above.



## Installation Verification

You can verify the successful installation of Natural Review by performing the following steps:

1. At any Natural command prompt, enter the following:

```
SYSRNM
```

Natural Review is started and a Natural Review logo screen similar to the example below appears:

```
17:30:01          ***** REVIEW NM UTILITY *****          date

      RRRRRRRR      EEEEEEE  VVV   VVV   III   EEEEEEE  WWW           WWW
      RRRRRRRRRR    EEEEEEE  VVV   VVV   III   EEEEEEE  WWW           WWW
      RRR   RRR   EEE           VVV   VVV   III   EEE           WWW           WWW
      RRR   RRR   EEE           VVV   VVV   III   EEE           WWW           WWW
      RRRRRRRR      EEEEEEE  VVV   VVV   III   EEEEEEE  WWW   W   WWW
      RRRRRRRR      EEEEEEE  VVV   VVV   III   EEEEEEE  WWW   WW  WWW
      RRR   RRR   EEE           VVV   VVV   III   EEE           WWW   WWW  WWW
      RRR   RRR   EEE           VVV   VVV   III   EEE           WWW  WWWWWW WWW
      RRR   RRR   EEEEEEE      VVVVVV      III   EEEEEEE      WWWWW  WWWWW
      RRR   RRR   EEEEEEE      VVVV      III   EEEEEEE      WWW      WWW
```

N A T U R A L     M O N I T O R

A     P R O D U C T     O F     S O F T W A R E     A G

(You can suppress this screen by specifying `BANNER=N` in the text object `CONFIG` in the library `SYSRNM`.)

2. Press **ENTER** to invoke the Natural Review **Main Menu** screen:

```

17:30:17          ***** REVIEW NM UTILITY *****          date
                      - Main Menu -

Code  Function
NM    Natural Monitor System
UP    User Profile System

Command ==>

REV00001 - Welcome to Review NM running under CICS

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help      Exit                                  Fin

```

Alternatively, you can invoke this menu by logging on to the Natural library `SYSRNM` and then entering the following command:

```
MENU
```

3. In the command line of the Natural Review **Main Menu** screen, enter either of the following commands:

```
NM
```

(for **Natural Monitor System**)

or

```
UP
```

(for **User Profile System**)

Depending on the command entered, the main screen of the requested subsystem appears. You can then check your installation parameters and the status of the history session. For detailed information on the functions provided by the subsystems, see the *Natural Review* documentation.

4. If you want to run history reports, start the history session. It runs as an asynchronous (non-terminal) Natural session and writes the collected report data to the repository file each time a report time interval has expired.

You can start and stop the history session either automatically by using the CICS PLTPI/PLTSD (see [Step 1: Add CICS Control Table Entries for Natural Review](#)), or manually outside Natural by using the RVH1 transaction (see [Step 1: Add CICS Control Table Entries for Natural Review](#)) in the following ways:

RVH1	<p>Start the Natural Review history session with the transaction code RVH2 as defined with NATTRAN in <a href="#">Step 8: Build the Natural Review System Control Block</a>.</p> <p>The history session can also be started with the START command of Natural Review (see the <i>Natural Review</i> documentation).</p>
RVH1 STOP	<p>Terminate the Natural Review history session.</p> <p>The history session can also be terminated with the STOP command of Natural Review (<i>Natural Review</i> documentation).</p>
RVH1 TEST	<p>Start the Natural Review history session on the current terminal.</p> <p>This option can be used for debugging purposes, for example, to debug the history session with CEDF (the CICS debugging facility).</p> <p>Note that no Natural terminal I/Os are supported during the normal processing of the history session. Therefore, you have to terminate the history session from another terminal.</p>

5. Check the Natural Review initialization messages on the console log of your CICS system to find out whether the history session has started successfully. The following message should appear: REV20200 - REVIEW NM HISTORY SESSION STARTED.

For more detailed explanations of the messages in Natural Review, enter MSG followed by the message number (for example, MSG 1) in the command line of Natural Review.



# XXI

## Installing Natural for zIIP on z/OS

---



# 26

## Installing Natural for zIIP on z/OS

---

■ Prerequisites .....	296
■ Installation Procedure .....	296
■ Installation Verification .....	298

This document provides information on installing the following Natural for zIIP products on z/OS: Natural Batch for zIIP (product code NAZBT), Natural for CICS for zIIP (product code NAZCI) and Natural for Com-plete for zIIP (product code NAZCO).

### Related Topics:

For information on zIIP usage with Natural, see the *Natural for zIIP* documentation.

## Prerequisites

---

- The z/OS operating system hosting the Natural environment executes on an IBM System z Integrated Information Processor (zIIP).
- The Natural session runs in a z/OS batch, batch server or TSO environment in which Natural Batch for zIIP is installed.

The Natural session runs in a CICS environment in which Natural CICS Interface and Natural for CICS for zIIP are installed.

The Natural session runs in a Com-plete environment in which Natural Com-plete/SMARTS Interface and Natural for Com-plete for zIIP are installed.

The Natural session runs in an IMS TM environment in which Natural IMS TM Interface and Natural for IMS for zIIP are installed.

- In addition to the Natural product license file, a license file is required for each environment in which Natural for zIIP runs.

See also [General Prerequisites and System Support](#) in the section *Overview of the Installation Process*.

## Installation Procedure

---

The steps required to install Natural for zIIP are performed during the installation for base Natural described in [Installing Natural on z/OS](#). These steps are summarized in the following section.

- [Step 1: Install Natural for ZIIP License Files](#)
- [Step 2: Link and Start ASM](#)
- [Step 3: Set the ZIIP Profile Parameter](#)



■ [Step 4: Link the Environment-Dependent Nucleus](#)

## Step 1: Install Natural for zIIP License Files

In addition to the Natural product license file, a license file is required and must be installed for each environment in which Natural for zIIP runs:

- For Natural Batch for zIIP: `NAZvrs.LICS`, see [Prepare, Convert, Assemble and Link the License File](#) in *Installing Natural*.
- For Natural for CICS for zIIP: `NCIvrs.LICS`, see [Prepare, Convert, Assemble and Link the License File for Natural for CICS for zIIP](#) in *Installing Natural CICS Interface on z/OS*.
- Natural for Com-plete for zIIP: `NCFvrs.LICS`, see [Prepare, Convert, Assemble and Link the License File for Natural for Com-plete for zIIP](#) in *Installing Natural Com-plete/SMARTS Interface on z/OS*.
- Natural for IMS for zIIP: `NIIvrs.LICS`, see [Prepare, Convert, Assemble and Link the License File for Natural for Com-plete for zIIP](#) in *Installing Natural IMS TM Interface*.

zIIP support will not be enabled if a Natural for zIIP license file check fails. Appropriate warning messages will then be displayed on the operator console and in the job log.

## Step 2: Link and Start ASM

If you have already installed and activated a Natural Authorized Services Manager (ASM) in your environment, you can skip the following and go to [Set the zIIP Profile Parameter](#).

1. Link the ASM module: see [Link Natural Modules to an APF Library](#) in *Installing Natural*.

The ASM must be of the same Natural version that provides zIIP support.

2. Start the ASM: [Create and Start the Natural Authorized Services Manager](#).

The subsystem ID is the only parameter the ASM requires for Natural for zIIP. Each Natural session must run with the same subsystem ID as the ASM. Otherwise, Natural will issue an appropriate error message. The subsystem ID is defined with the Natural profile parameter `SUBSID` (see the *Natural Parameter* documentation).

## Step 3: Set the zIIP Profile Parameter

- Set the Natural profile parameter `zIIP` to `AUTO` (default) or `ON` or use the corresponding macro `NTzIIP`:

For `NAZvrs.LICS`, see [Build the Natural Parameter Module](#) in *Installing Natural*.

For `NCIvrs.LICS`, see [Build the Natural Parameter Module](#) in *Installing Natural CICS Interface on z/OS*.

For `NCFvrs.LICS`, see [Build the Natural Parameter Module](#) in *Installing Natural Complete/SMARTS Interface on z/OS*.

For `NIIvrs.LICS`, see [Build the Natural Parameter Module](#) in *Installing Natural IMS TM Interface*.

zIIP and NTzIIP are described in the *Parameter Reference* documentation.

### Step 4: Link the Environment-Dependent Nucleus

The license files must be linked to the environment-dependent nucleus. It is not possible to link two or more license files together to the environment-independent nucleus, for example, one CICS license together with one for batch, because they have the same CSECT name `NAZLIC`.

- Link the **environment-dependent nucleus** with the appropriate license file generated in [Install Natural for zIIP License Files](#):

For `NAZvrs.LICS`, see [Link the Nucleus](#) in *Installing Natural*.

For `NCIvrs.LICS`, see [Link the Environment-Dependent Nucleus](#) in *Installing Natural CICS Interface on z/OS*.

Under CICS, the Natural environment-dependent nucleus must be defined to run in the CICS open transaction environment (OTE) as described in [Environment-Dependent Nucleus](#) in *Installing Natural CICS Interface*.

For `NCFvrs.LICS`, see [Link the Nucleus](#) in *Installing Natural Complete/SMARTS Interface on z/OS*.

For `NIIvrs.LICS`, see the link steps for different front-ends described in [Installing Natural IMS TM Interface](#).

## Installation Verification

---

After the last step of the installation procedure has been completed, you can run a Natural session and check whether zIIP support is active.

### ➤ To find out whether zIIP support has been enabled

- Check whether the following message is shown on the operator console or in the job log:

```
NAT7070 Advanced zIIP support enabled successfully.
```

No zIIP-specific message is displayed if your Natural session runs without zIIP enablement.

Or:

Issue the Natural system command `ZIIP` in batch or online mode.

If zIIP support is active, a **zIIP Processing Information** report is displayed indicating that zIIP support has been enabled. See the *System Commands* documentation for details.

If zIIP support is *not* active, a corresponding message appears.

Or:

For batch processing, set the Natural profile parameter `ZIIP=(PRINT=INFO)` or use the corresponding macro `NTZIIP` macro. See the *Parameter Reference* documentation for details.

If zIIP support is active, the **zIIP Processing Information** report (see above) is shown.

If zIIP support is *not* active, a corresponding message appears.

#### ➤ To check whether the correct license file is installed

- Issue the Natural system command `ZIIP LIC`.

A **zIIP License Information** screen appears listing details about the Natural for zIIP product license installed in your current environment.

---