

Natural

Parameter Reference

Version 6.3.12 for OpenVMS

October 2012

This document applies to Natural Version 6.3.12 for OpenVMS.

Specifications contained herein are subject to change and these changes will be reported in subsequent release notes or new editions.

Copyright © 1984-2012 Software AG, Darmstadt, Germany and/or Software AG USA, Inc., Reston, VA, United States of America, and/or their licensors.

Detailed information on trademarks and patents owned by Software AG and/or its subsidiaries is located at <http://documentation.softwareag.com/legal/>.

Use of this software is subject to adherence to Software AG's licensing conditions and terms. These terms are part of the product documentation, located at <http://documentation.softwareag.com/legal/> and/or in the root installation directory of the licensed product(s).

This software may include portions of third-party products. For third-party copyright notices and license terms, please refer to "License Texts, Copyright Notices and Disclaimers of Third-Party Products". This document is part of the product documentation, located at <http://documentation.softwareag.com/legal/> and/or in the root installation directory of the licensed product(s).

Document ID: NATOV-NNATPARMS-6312-20121005

Table of Contents

Preface	ix
1 Introduction to Profile Parameters	1
Profile Parameter Usage	2
Common Profile and Session Parameter Descriptions	2
2 Introduction to Session Parameters	3
Session Parameter Usage	4
How to Set Session Parameters	4
Session Parameter Evaluation	6
3 ACIVERS - Define ACI Version for Use with EntireX Broker ACI	7
4 AD - Attribute Definition	9
AD Parameter Syntax	10
Field Representation	11
Field Alignment	12
Field Input/Output Characteristics	12
Interpretation of Alphanumeric Fields	14
Mandatory Input	14
Length of Input Value	14
Field Upper/Lower Case Characteristics	15
Filler Character	15
5 AL - Alphanumeric Length for Output	17
6 AUTO - Automatic Logon	19
7 AUTORPC - Automatic Natural RPC Execution	21
8 BATCH - Batch Mode Simulation	23
9 BATCHMODE - Batch Mode	25
10 BMBLANK - Display Trailing Blanks	27
11 BMCONTROL - Display Control Characters	29
12 BMFRAME - Window Frame Characters	31
13 BMSIM - Similar Batch Mode Output	33
14 BMTIME - Display Process Time	35
15 BMTITLE - Display Window Title	37
16 BMVERSION - Display Natural Version	39
17 BPID - Specify Buffer Pool ID	41
18 BPNAME - Name of Natural Global Buffer Pool	43
19 BPSFI - Object Search First in Buffer Pool	45
20 CC - Error Processing in Batch Mode	47
21 CD - Color Definition	49
22 CDYNAM - Dynamic Loading of Non-Natural Programs	51
23 CF - Character for Terminal Commands	53
24 CLEAR - Processing of CLEAR Key in NEXT Mode	55
25 CM - Command Mode	57
26 CMOBJIN - Batch Input File for Natural INPUT Data	59
27 CMPRINT - Batch Output File	61
28 CMPRTnn - Additional Report	63

29 CMSYNIN - Batch Input File for Natural Commands and INPUT Data	65
30 CMWRKnn - Natural Work Files	67
31 CO - Compiler Output	69
32 COMPR - Set RPC Buffer Compression	71
33 CP - Default Code Page Name	73
34 CPCVERR - Code Page Conversion Error	75
35 CPOBJIN - Code Page of Batch Input File	77
36 CPPRINT - Code Page of Batch Output File	79
37 CPRPC - Define Code Page Name	81
38 CPSYNIN - Code Page of Batch Input File for Commands	83
39 CV - Attribute Control Variable	85
40 CVMIN - Control Variable Modified at Input	87
41 DBSHORT - Interpretation of Database Field Short Names	89
42 DBUPD - Database Updating	93
43 DC - Character for Decimal Point Notation	95
44 DD - Day Differential	97
45 DF - Date Format	99
46 DFOUT - Date Format for Output	101
47 DFS - Specify RPC Client's Default Server Address	103
48 DFSTACK - Date Format for Stack	105
49 DFTITLE - Output Format of Date in Standard Report Title	107
50 DL - Display Length for Output	109
51 DO - Display Order of Output Data	111
52 DTFORM - Date Format	113
53 DU - Dump Generation	115
54 DY - Dynamic Attributes	117
DY Parameter Syntax	118
Examples	120
55 DYNPARM - Control Use of Dynamic Parameters	121
56 ECHO - Control Printing of Batch Input Data	123
57 ECPMOD - Entire Connection Protocol Mode	125
58 EDITOR - Other Program Editor	127
59 EDTBPSIZE - Software AG Editor Buffer Pool Size	129
60 EDTLFILES - Number of Software AG Editor Logical Files	131
61 EDTRB - Program Editor Ring Buffer	133
62 EJ - Page Eject	135
63 EM - Edit Mask	137
EM Parameter Syntax	138
Examples	139
Blanks in Edit Masks	139
Default Edit Masks	139
Edit Masks for Numeric Fields	140
Edit Masks for Alphanumeric Fields	143
Edit Masks for Binary Fields - Format B	145
Hexadecimal Edit Masks	145

Edit Masks for Date and Time Fields - Formats D and T	147
Edit Masks for Logical Fields - Format L	151
64 EMFM - Edit Mask Free Mode	153
65 EMU - Unicode Edit Mask	155
66 ENDIAN - Endian Mode for Compiled Objects	157
67 ENDMMSG - Display Session-End Message	159
68 ES - Empty Line Suppression	161
69 ESCAPE - Ignore Terminal Commands %% and %	163
70 ESXDB - Database ID Used for Entire System Server DDMs	165
71 ET - Execution of END/BACKOUT TRANSACTION Statements	167
72 ETA - Error Transaction Program	169
73 ETDB - Database for Transaction Data	171
74 ETEOP - Issue END TRANSACTION at End of Program	173
75 ETID - Adabas User Identification	175
76 ETPDB - Databases Containing Entire Transaction Propagator Master Files	177
77 ETPSIZE - Size of Entire Transaction Propagator Buffer	179
78 FC - Filler Character for INPUT Statement	181
79 FC - Filler Character for DISPLAY Statement	183
80 FCDP - Filler Character for Dynamically Protected Input Fields	185
81 FDDM - Natural System File for DDMs	187
82 FDIC - Predict System File	189
83 FL - Floating Point Mantissa Length	191
84 FNAT - Natural System File for System Programs	193
85 FREEGDA - Release GDA in Utility Mode	195
86 FS - Default Format/Length Setting for User-Defined Variables	197
87 FSEC - Natural Security System File	199
88 FUSER - Natural System File for User Programs	201
89 GC - Filler Character for Group Headers	203
90 GFID - Global Format IDs	205
91 HC - Header Centering	207
92 HD - Header Definition	209
93 HE - Helproutine	211
HE Parameter Syntax	212
Execution of Helproutines	214
Examples	214
94 HI - Help Character	217
95 HW - Heading Width	219
96 IA - Input Assign Character	221
97 IC - Insertion Character	223
98 ICU - Unicode Insertion Character	225
99 ID - Input Delimiter Character	227
100 IKEY - Processing of PA and PF Keys	229
101 IM - Input Mode	231
102 INIT-LIB - Library for Automatic Logon	233
103 IP - INPUT Prompting Text	235

104 IS - Identical Suppress	237
105 KC - Check for Statement Keywords	239
106 KCHECK - Check for Statement Keywords	241
107 KD - Key Definition	243
108 KEY - Setting Assignments to PA, PF and CLEAR Keys	245
109 LC - Lower to Upper Case Translation	247
110 LC - Leading Characters	249
111 LCU - Unicode Leading Characters	251
112 LE - Reaction when Limit for Processing Loop Exceeded	253
113 LFILE - Logical System File Definition	255
LFILE Parameter Syntax	256
Example of LFILE Parameter	257
114 LOGONRQ - Logon for RPC Server Request Required	259
115 LS - Line Size	261
Profile Parameter LS	262
Session Parameter LS	262
Specification with Statements	263
116 LT - Limit for Processing Loops	265
117 MADIO - Maximum DBMS Calls between Screen I/O Operations	267
118 MAINPR - Override Default Output Report Number	269
119 MASKCME - MASK Compatible with MOVE EDITED	271
120 MAXBUFF - Maximum Buffer Size	273
121 MAXCL - Maximum Number of Program Calls	275
122 MAXYEAR - Maximum Year for Date/Time Values	277
123 MC - Multiple-Value Field Count	279
124 MFSET - Multi-Fetch Setting	281
125 ML - Position of Message Line	283
126 MP - Maximum Number of Pages of a Report	285
127 MS - Manual Skip	287
128 MSGSF - Display System Error Messages in Short/Full Format	289
129 NATLOG - Natural Log File	291
Examples	292
130 NATVERS - Switching between Natural Environments	295
131 NC - Use of Natural System Commands	297
132 NCFVERS - NCF File Protocol Version	299
133 NENTRY - Left/Right Alignment of Numeric Field Entries	301
134 NL - Numeric Length for Output	303
135 NOAPPLERR - Suppress Message Number Prefix NAT	305
136 NOPROX - Specify Local Domains for Direct Addressing	307
137 NOSSLPRX - Specify Local Domains for Direct Addressing SSL	309
138 OPF - Overwriting of Protected Fields by Helproutines	311
139 OPRB - Database Open/Close Processing	313
OPRB String Syntax	314
140 PARM - Alternative Parameter File	317
141 PC - Control of Personal-Computer Access Method	319

142 PC - Periodic Group Count	321
143 PCHECK - Parameter Checking for Object Calling Statements	323
144 PD - Size of Page Dataset	325
145 PM - Print Mode	327
Profile Parameter PM	328
Session Parameter PM	328
146 PRGPAR - Data to be Passed to Program Receiving Control at Termination	331
147 PROGRAM - Non-Natural Program Receiving Control after Termination	333
148 PROX - Specify URL of Proxy Server	335
149 PROXPORT - Specify Port Number of Proxy	337
150 PS - Page Size for Natural Reports	339
151 PSIGNF - Internal Representation of Positive Sign of Packed Numbers	341
152 RCFIND - Handling of Response Code 113 for FIND Statement	343
153 RCGET - Handling of Response Code 113 for GET Statement	345
154 RDS - Define Remote Directory Server	347
155 RECAT - Dynamic Recataloging	349
156 REINP - Issue Internal REINPUT Statement for Invalid Data	351
157 ROSY - Read-Only Access to System Files	353
158 RPCSDIR - Library for Service Directory	355
159 RTINT - Allow Runtime Interrupt	357
160 RQTOUT - REQUEST DOCUMENT Timeout	359
161 SA - Sound Terminal Alarm	361
162 SB - Selection Box	363
Syntactical Considerations	364
Runtime Considerations	365
163 SD - Time Delay between Two Screens	367
164 SERVER - Start Natural Session as an RPC Server Session	369
165 SF - Spacing Factor	371
166 SG - Sign Position	373
167 SHELL - Grant Shell Access to Natural User	375
168 SSLPRX - Specify URL of SSL Proxy Server	377
169 SSLPRXPT - Specify Port Number of SSL Proxy	379
170 SM - Programming in Structured Mode	381
171 SNAT - Sound a Bell at Syntax Error	383
172 SORTSZE - Size of Sort Buffer	385
173 SRETAIN - Retain Source Format	387
174 SRVCMIT - Server Commit Time	389
175 SRVNAME - Name of RPC Server	391
176 SRVNODE - Name of Node	393
177 SRVTRY - Number of Connect/Reconnect Attempts	395
178 SRVTERM - Server Termination Event	397
179 SRVUSER - User ID for RPC Server Registry	399
180 SRVWAIT - Wait Time of RPC Server	401
181 SSIZE - Size of Source Area Allocated by the Editors	403
182 STACK - Place Data/Commands on the Stack	405

183	STARTUP - Program Name for System Variable *STARTUP	407
184	STEPLIB - Initial Setting for *STEPLIB System Variable	409
185	SUBCHAR - Substitution Character for Default Code Page	411
186	SUTF8 - UTF-8 Format for Sources	413
187	SYMGEN - Generate Symbol Table	415
188	SYNERR - Control of Syntax Errors	417
189	TC - Trailing Characters	419
190	TCU - Unicode Trailing Characters	421
191	TD - Time Differential	423
192	TF - Translation of Database ID/File Number	425
193	THSEP - Dynamic Thousands Separator	427
194	THSEPCH - Thousands Separator Character	429
195	TIMEOUT - Wait Time for RPC Server Response	431
196	TMPSORTUNIQU - Alternate Algorithm for Generating Sort Work File Names	433
197	TQ - Translate Quotation Marks	435
198	TQMARK - Translate Quotation Marks	437
199	TRACE - Define Trace Level for Natural RPC Servers	439
200	TRANSP - Server Transport Protocol	441
201	TRYALT - Try Alternative Server Address	443
202	UC - Underlining Character	445
203	UDB - User Database ID	447
204	ULANG - User Language	449
205	USEDIC - Common Logical Name for Dictionary Servers	451
206	USER - User ID	453
207	USEREP - Repository Usage	455
208	USIZE - Size of User Buffer	457
209	WEBIO - Use Natural Web I/O Interface	459
210	WFOPFA - Opening of Work Files	461
211	WH - Wait for Record in Hold Status	463
212	WORK - Work-File Assignments	465
213	XADB - Database for Coordination of Transaction Processing	467
214	XREF - Creation of XRef Data for Natural	469
	Possibilities of Setting the XREF Parameter	470
	XRef Data Generation	471
	Extended XRef Data Generation (For Internal Use Only)	471
215	YSLW - Year Sliding or Fixed Window	473
216	ZD - Zero-Division Check	475
217	ZP - Zero Printing	477

Preface

This documentation contains detailed information on the Natural profile and session parameters. It is organized under the following headings:

Introduction to Profile Parameters Contains general information on profile parameter usage, including a list of references to related documents.

Introduction to Session Parameters Contains general information on session parameter usage and evaluation.

Parameters in Alphabetical Order Descriptions of all profile parameters and session parameters in alphabetical order.

General information on using parameters can be found in the *Operations* documentation, see *Profile Parameter Usage*.

1 Introduction to Profile Parameters

- Profile Parameter Usage 2
- Common Profile and Session Parameter Descriptions 2

Profile Parameter Usage

As the use of the Natural profile parameters is different on the platforms supported by Natural, general information about parameter usage is included in the corresponding platform-specific documentation.

See the following documents:

- Profile Parameter Usage in the *Operations* documentation
- Creating a New Parameter File in the *Configuration Utility* documentation
- Overview of Profile Parameters in the *Configuration Utility* documentation

Common Profile and Session Parameter Descriptions

If a Natural session parameter with the same name and functionality as a Natural profile parameter exists, the descriptions of both parameters are combined in a single document.

2 Introduction to Session Parameters

- Session Parameter Usage 4
- How to Set Session Parameters 4
- Session Parameter Evaluation 6

Session Parameter Usage

In Natural, session parameters are used:

- to specify certain characters,
- to set processing time limits,
- to set a particular response for a given condition,
- to set various size limits,
- to determine various aspects of output reports.

At the installation of Natural, the Natural administrator sets these parameters to default values which are then valid for all users of Natural.

To see which parameter values apply to your session, you enter the system command `GLOBALS` (described in the *System Commands* documentation).

How to Set Session Parameters

Natural session parameters can be set in several ways:

- via the default parameter file `NATPARM`, which is set when Natural is installed;
- via dynamic parameters specified when invoking Natural (as described in your *Natural Operations* documentation);
- via the system command `GLOBALS`;
- via a `SET GLOBALS` statement (in reporting mode only);
- via a `FORMAT` statement;
- via parameter specification within statements where parameters also are evaluated, for example, `INPUT, DISPLAY, WRITE`;
- via terminal commands.

Instead of the parameter values `ON` and `OFF`, you can also specify `T` (true) or `F` (false) respectively.

Changing Session Parameters at Session Level Using the GLOBALS Command

For your Natural session you can change some of the parameter values set by the Natural administrator.

Within your Natural session, you can change these parameters by issuing the following system command:

GLOBALS

When you issue the GLOBALS command, a screen is displayed showing the parameter values that are currently in effect for your session. On this screen, you can change the values that do not suit your requirements.

A parameter value set with a GLOBALS command remains in effect until the end of the Natural session (and applies to every object you store during the session), unless you change it again with another GLOBALS command.

Changing Session Parameters at Program Level Using the FORMAT Statement

You can change certain parameters for the duration of a single program (report). This is done by using a FORMAT statement in the program, which will override the session-wide settings for these parameters.

Example of a FORMAT Statement:

```
FORMAT AL=10 HC=R
```

Parameters set with a FORMAT statement apply until the end of the executed program, unless they are changed with another FORMAT statement in the program.

Not all session parameters can be changed at program level, while several parameters that can be specified at program level cannot be specified at session level; most of the latter are parameters which affect the format of an output report.

Changing Session Parameters at Statement Level

Most of the parameters you can change with a FORMAT statement you can also change for an individual statement; for example, for a particular DISPLAY, WRITE, INPUT or REINPUT statement.

This is done by specifying the parameter (in parentheses) after the statement name.

Example:

```
DISPLAY (SF=4) NAME JOB-TITLE CURR-CODE SALARY
```

A parameter set at statement level applies only to the statement in which it is specified. The setting at statement level overrides, for that statement only, all other settings of that parameter at other levels.

Changing Session Parameters at Field Level

Within a `DISPLAY`, `WRITE`, `INPUT` or `REINPUT` statement, you can also change some parameters for an individual field or output element.

This is done by specifying the parameter (in parentheses) after the field name.

Example:

```
DISPLAY NAME (AL=10) JOB-TITLE CURR-CODE SALARY
```

The parameter value then applies only to that field. The setting at field level overrides, for that field only, all other settings of that parameter at other levels. However, only some of the parameters that can be set at statement level can also be set at field level.

Session Parameter Evaluation

Parameters specified with the statements `DISPLAY`, `FORMAT`, `PRINT`, `INPUT`, `REINPUT`, `WRITE`, `WRITE TITLE` and `WRITE TRAILER` are processed during program compilation and are therefore included in the corresponding object module for the program.

The following hierarchy is used for evaluation:

1. Parameters set at element/field (highest priority)
2. Parameters set at statement level
3. Parameters set with a `FORMAT` statement
4. The default parameter settings (lowest priority)

Parameters set with a `SET GLOBALS` statement cause the execution time environment to be modified. These modifications remain in effect until overridden by another `SET GLOBALS` statement (or `GLOBALS` system command).

3 ACIVERS - Define ACI Version for Use with EntireX Broker

ACI

This Natural profile parameter specifies the API version to be used with the EntireX Broker ACI.

Possible settings	1 - 9	Single-digit number, identifying the ACI version. Note: The higher the version, the more features are available. For details, see <i>Set the ACI Version in the Natural Remote Procedure Call (RPC)</i> documentation.
Default setting	2	API Version 2 is used.
Dynamic specification	yes	
Specification within session	no	



Notes:

1. ACIVERS can be specified on both the client and the server side.
2. The broker stub in use as well as the called EntireX Broker must support the ACI version defined here. Please, refer to the EntireX documentation for the supported API versions. The setting of ACIVERS enables special features of the EntireX Broker, depending on the API version you are using. For details, see *Setting Up an EntireX Broker Access* in the *Natural Remote Procedure Call* documentation.
3. For information on Natural RPC, see the *Natural Remote Procedure Call (RPC)* documentation.

4 AD - Attribute Definition

- AD Parameter Syntax 10
- Field Representation 11
- Field Alignment 12
- Field Input/Output Characteristics 12
- Interpretation of Alphanumeric Fields 14
- Mandatory Input 14
- Length of Input Value 14
- Field Upper/Lower Case Characteristics 15
- Filler Character 15

With this session parameter, you specify field attributes at field/element or statement level.

Related session parameter: [CD - Color Definition](#)

Possible settings	See AD Parameter Syntax .	You can specify multiple attributes in any sequence.
Default setting	See below.	
Applicable statements	FORMAT	
	DISPLAY INPUT NEWPAGE WITH TITLE PRINT REINPUT WRITE WRITE TITLE WRITE TRAILER	Parameter may be specified at statement level and/or at element level.
	ASSIGN CALLNAT CALLDBPROC COMPUTE MOVE PERFORM SEND METHOD	Parameter may be specified at element level, however, only the attributes specified in the relevant statement description can be used.
Applicable command	none	




Note: The AD parameter may be also specified in function calls, however, only the attributes specified in the section *Function Call* can be used.

The following topics are covered below:

AD Parameter Syntax

AD=[*field-representation*] [*field-alignment*] [*field-i/o-characteristics*]
 [*interpretation-of-alphanumeric-fields*] [*mandatory-input*] [*input-value-length*]
 [*field-upper/lower-case*] [*filler-character*]

You can specify multiple attributes in any sequence. Possible values are:



The meaning of the attributes and the possible values are explained below.

Examples:

```
DISPLAY #FIELD A (AD=R)
INPUT #FIELD B (AD=M)
INPUT (AD=IM) #FIELD A #FIELD B
```

Field Representation

Value	Meaning	Statements	Explanation
B	blinking (*)	ASSIGN	The value of the field is displayed blinking.
C	cursive/italic (*)	COMPUTE	The value of the field is displayed cursive/italic.
D	default intensity	MOVE DISPLAY FORMAT	The value of the field is displayed with normal intensity, that is, not highlighted in any way. This is the default value.
I	intensified	INPUT	The value of the field is displayed intensified.
N	non-display	PRINT	A value entered in the field will not be displayed.
U	underlined	REINPUT	The value of the field is displayed underlined.
V	reverse video (*)	WRITE	The value of the field is displayed reverse video.
Y	dynamic attributes	INPUT DISPLAY PRINT WRITE	Attributes are to be controlled via an attribute control variable (Format C).

* The field representation attributes marked with an asterisk (*) require corresponding hardware features, and will be ignored at runtime if these features are not available.

Field Alignment

Value	Meaning	Statements	Explanation
L	left-justified	DISPLAY FORMAT	The value of the field is displayed left-justified. This is the default value for alphanumeric fields.
R	right-justified	INPUT PRINT REINPUT	The value of the field is displayed right-justified. This is the default value for numeric fields.
Z	leading zeros	WRITE	Numeric values are displayed with leading zeros, right-justified.

Field Input/Output Characteristics

Value	Meaning	Statements	Explanation
A	input field, non-protected	INPUT FORMAT	The value of the field is to be entered in response to the INPUT statement. This is the default value.
	input only	CALLNAT CALLDBPROC PERFORM SEND METHOD Function Call	<p>If you mark a parameter with AD=A, its value will not be passed to the called object (subprogram, stored procedure, subroutine, dialog, method), but it will receive a value from the called object.</p> <p>For a field defined with BY VALUE in the called object's parameter data area, the calling object cannot receive a value. In this case, AD=A only causes the field to be reset to the low value of the respective format (blanks for alphanumeric, binary zeroes for binary and zeroes for numeric fields) before the object is called.</p> <p>For CALLNAT, AD=A may be useful for remote subprograms executed via Natural RPC in a client/server environment to reduce the load of data sent. If a subprogram is executed locally, AD=A fields will be reset to the low value of the respective format before the object is called.</p> <p>If for SEND METHOD, a method is not implemented in Natural, the behavior depends on the method implementation. The parameter is then passed as an initialized variant. Whether the external component is able to return a value is described in the documentation of the external component. It can also be viewed in the Natural Component Browser.</p>
M	output field, modifiable	INPUT FORMAT	The value of the field is to be displayed during INPUT statement execution, and a different value may be entered by the user. The field is an output field and may be modified.
	modifiable	CALLNAT CALLDBPROC	By default, the passed value of a parameter can be changed in the called object (subprogram, stored procedure, subroutine, dialog,

Value	Meaning	Statements	Explanation
		PERFORM SEND METHOD Function Call	<p>method) and the changed value passed back to the calling object, where it overwrites the original value.</p> <p>For a field defined with <code>BY VALUE</code> in the called object's parameter data area, no value is passed back.</p> <p>If, for <code>SEND METHOD</code>, a method is <i>not</i> implemented in Natural, the behavior depends on the method implementation. The parameter is then passed <code>BY REFERENCE</code>. Whether the external component accepts a by reference or by value parameter is described in the documentation of the external component. It can also be viewed in the Natural Component Browser.</p>
0	output field, write-protected	INPUT FORMAT	The value of the field is to be displayed during <code>INPUT</code> execution. The field is an output field and may not be modified.
	non-modifiable	CALLNAT CALLDBPROC PERFORM SEND METHOD Function Call	<p>If you mark a parameter with <code>AD=0</code>, the passed value can be changed in the called object (subprogram, stored procedure, subroutine, dialog, method), but the changed value cannot be passed back to the calling object; that is, the field in the calling object retains its original value.</p> <p>Internally, <code>AD=0</code> is processed in the same way as a call-by-value (see <code>BY VALUE</code> in the section Parameter Data Definition in the description of the <code>DEFINE DATA</code> statement).</p> <p>If for <code>SEND METHOD</code>, a method is implemented in Natural, the parameter is treated like it was defined <code>BY VALUE</code> in the method's parameter data area (see the <i>PARAMETER clause</i> of the <code>INTERFACE</code> statement).</p> <p>If for <code>SEND METHOD</code>, a method is <i>not</i> implemented in Natural, the behavior depends on the method implementation. The parameter is then passed <code>BY VALUE</code>. Whether the external component accepts a call by reference or by value parameter is described in the documentation of the external component. It can also be viewed in the Natural Component Browser.</p>
P	temporarily protected	INPUT REINPUT	Used in conjunction with an attribute control variable (Format C), the <code>DY</code> parameter (dynamic attributes), and the <code>REINPUT</code> statement.



Note: The Field Input/Output Characteristics A, M and 0 of the AD parameter may be also specified in function calls.

Interpretation of Alphanumeric Fields

Value	Meaning	Statements	Explanation
Q	display alphanumeric field as if it were a numeric field	ASSIGN COMPUTE MOVE DISPLAY FORMAT INPUT PRINT REINPUT WRITE	This attribute is available on mainframe computers only. A corresponding hardware feature is required. An alphanumeric field is interpreted as if it were a numeric field. If the field is displayed under the scope of profile or session parameter <code>PM=I</code> , the value of the field is interpreted from left to right instead of right to left.

Mandatory Input

Value	Meaning	Statements	Explanation
E	value mandatory	INPUT FORMAT	A value must be entered in the field in response to an INPUT statement; otherwise an error message will be issued. This is only relevant for input-only fields (<code>AD=A</code>).
F	value optional	INPUT FORMAT	A value can, but need not, be entered in the field in response to an INPUT statement. This is the default value.

Length of Input Value

Value	Meaning	Statements	Explanation
G	value size	INPUT FORMAT	The value entered in the field in response to an INPUT statement must be of the same length as the field. This is only relevant for input-only fields (<code>AD=A</code>).
H	value size	INPUT FORMAT	The value entered in the field in response to an INPUT statement may be shorter than the field. This is the default value.

Field Upper/Lower Case Characteristics

Value	Meaning	Statements	Explanation
T	translate lower to upper case	INPUT FORMAT	The value entered is to be translated to upper case.
W	accept lower case	INPUT FORMAT	Lower case values are to be accepted. AD=W is the default value. Note: To make AD=W effective, you have to specify the value ON for the Natural profile parameter LC.

Filler Character


Value	Meaning	Statements	Explanation
' c '	filler character	INPUT FORMAT	The empty field is to be filled with the specified character c (for display only) if AD=A (input field, non-protected) or AD=M (output field, modifiable) is specified.

Before the value is displayed for a modifiable field (AD=M), field positions that are not occupied by the value are filled with the specified filler character as follows:

- Leading or trailing positions (depending on the field alignment) are filled for format I, N and P fields.
- Trailing positions are filled for format A fields.

If the user enters a value in response to the INPUT statement, before the value has been assigned to the field,

- both leading and trailing filler characters are removed for format I, N and P fields,
- trailing filler characters are removed for format A fields.

 **Caution:** Filler characters that may occur as part of the value in either leading or trailing position should be avoided to prevent undesired results. For example, if the filler character "0" (zero) is defined for a field of format N5 and the value 00100 is entered as input data, leading and trailing zeroes are removed so that only the value 1 remains, and will be assigned to the field. For the same reason, the minus sign "-" should be avoided as a filler character for numeric fields if negative values are to be entered.

5 AL - Alphanumeric Length for Output

With this session parameter, you specify the default output length for an alphanumeric field; that is, when it is specified shorter than the field length, the field will be right-truncated.

Possible settings	1 to n	n = value of LS (line size) parameter minus 1
Default setting	none	
Applicable statements	FORMAT	
	DISPLAY INPUT PRINT WRITE	Parameter may be specified at statement level and/or at element level.
Applicable command	none	



Notes:

1. It is not recommended to use the AL session parameter for input fields (**attribute definition AD=A or AD=M**) in an INPUT statement.
2. Any edit mask specified for a field (see session parameter **EM**) will override the AL session parameter for this field.

Example:

```
FORMAT AL=20
```

See also *Parameters to Influence the Output of Fields* in the *Programming Guide*.

6 AUTO - Automatic Logon

This Natural profile parameter causes an automatic logon to a specific library at the start of the Natural session.

Possible settings	ON	An automatic logon is executed at the start of the Natural session.
	OFF	No automatic logon is performed.
Default setting	OFF	
Dynamic specification	yes	
Specification within session	no	
Application programming interface	USR1005N	See <i>SYSEXT - Natural Application Programming Interfaces</i> in the <i>Utilities</i> documentation.

 **Notes:**

1. The setting contained in the system variable *INIT-USER is used as the user ID for the logon.
2. If used with Natural Security, AUTO=ON disables logons with another user ID (see the *Natural Security* documentation for further information).

 **Notes:**

1. The setting of the profile parameter INIT-LIB is used as library ID for the logon.
2. If used with Natural Security, AUTO=ON disables logons with another user ID, and the INIT-LIB parameter is not evaluated (see the *Natural Security* documentation for further information).

7 AUTORPC - Automatic Natural RPC Execution

This Natural profile parameter determines whether or not Natural RPC will automatically try to execute a subprogram remotely (on the server side) which was not found locally (on the client side).

Possible settings	ON	Natural RPC will automatically try to execute it remotely.
	OFF	Natural RPC will not automatically try to execute it remotely. Note: With AUTORPC=OFF, you can execute CALLNATs remotely using stubs.
Default setting	OFF	
Dynamic specification	yes	
Specification within session	yes	At runtime, this value can be overwritten using the Parameter Maintenance function of the SYSRPC utility.



Notes:

1. AUTORPC is specified on the client side only.
2. For details see *Interface Objects and Automatic RPC Execution* in the *Natural Remote Procedure Call (RPC)* documentation.
3. For information on Natural RPC, see the *Natural Remote Procedure Call (RPC)* documentation.

8

BATCH - Batch Mode Simulation

This Natural profile parameter sets the system variable *DEVICE to BATCH when Natural is started.

Possible settings	ON	When Natural is started with profile parameter BATCH set, error messages are not displayed, but written to a log file. Note: The log file is named <i>natbatch.log</i> and is located in the Natural binary directory.
	OFF	Error messages are displayed but not written to a log file.
Default setting	OFF	
Dynamic specification	yes	This parameter can only be specified dynamically.
Specification within session	no	



Note: To run Natural in batch mode, use the parameter `BATCHMODE` instead of `BATCH`.

9 BATCHMODE - Batch Mode

This Natural profile parameter applies to batch mode only. It enables batch mode and sets the system variable *DEVICE to BATCH when Natural is started. However, it does not overwrite a device setting that results from the parameter [PC=ON](#).

For information on batch mode operation, see *Natural in Batch Mode* in the *Operations* documentation.

Possible settings	ON	Natural will run in batch mode.
Default setting	OFF	Natural will run in interactive mode, or in batch mode simulation.
Dynamic specification	yes	The parameter can only be specified dynamically.
Specification within session	no	

10 BMBLANK - Display Trailing Blanks

This Natural profile parameter is used to control the display of trailing blanks in the batch output file **CMPRINT**.

Possible settings	ON	Trailing blanks are written to CMPRINT .
	OFF	No trailing blanks are written to CMPRINT .
Default setting	ON	
Dynamic specification	yes	
Specification within session	no	



Notes:

1. This Natural profile parameter applies to batch mode only.
2. This parameter applies only if the parameter **BMSIM** is set to MF.
3. Trailing blanks are generated automatically if **BMSIM** is set to MF.
4. **BMBLANK** has no effect if **BMSIM** is set to OS or VM.

11

BMCONTROL - Display Control Characters

This Natural profile parameter controls the output of control characters (such as form feed and line feed) in the batch output file [CMPRINT](#).



Note: This Natural profile parameter applies to batch mode only.

Possible settings	ON	Control characters will be written to CPRINT.
	OFF	No control characters will be written to CPRINT.
Default setting	ON	
Dynamic specification	yes	
Specification within session	no	

12 BMFRAME - Window Frame Characters

With this parameter you can define window frame characters that will be written to the batch output file [CMPRINT](#).



Note: This Natural profile parameter applies to batch mode only.

Possible settings	6 characters	Specify a sequence of 6 characters (see Example).	
		Character Position:	Displays:
	1	Horizontal bar	
	2	Vertical bar	
	3	Upper-left corner	
	4	Upper-right corner	
	5	Lower-left corner	
6	Lower-right corner		
Default setting	- !++++		
Dynamic specification	yes		
Specification within session	no		

Example:

To define the following frame you have to specify `BMFRAME=123456`.

```
31111111111114
2          2
2          2
51111111111116
```


13 BMSIM - Similar Batch Mode Output

This Natural profile parameter is used for the general appearance description of the batch mode output file [CMPRINT](#).



Note: This Natural profile parameter applies to batch mode only.

Possible settings	MF	<p>Forces output similar to Natural for Mainframe Version 2.3. Each line in CMPRINT is filled with trailing blanks.</p> <p>A control character appears at the beginning of each line of CMPRINT. The control character codes are similar to the IBM control character option ASA.</p> <p>The following control character codes are used:</p> <table border="1"> <thead> <tr> <th>Control Code</th> <th>Interpretation</th> </tr> </thead> <tbody> <tr> <td>blank</td> <td>Normal output line without control characters</td> </tr> <tr> <td>0</td> <td>Insert one empty line</td> </tr> <tr> <td>-</td> <td>Insert two empty lines</td> </tr> <tr> <td>+</td> <td>Print this line twice (bold printing)</td> </tr> <tr> <td>1</td> <td>Form feed before printing this line</td> </tr> </tbody> </table>	Control Code	Interpretation	blank	Normal output line without control characters	0	Insert one empty line	-	Insert two empty lines	+	Print this line twice (bold printing)	1	Form feed before printing this line
	Control Code	Interpretation												
	blank	Normal output line without control characters												
	0	Insert one empty line												
	-	Insert two empty lines												
	+	Print this line twice (bold printing)												
	1	Form feed before printing this line												
	VM	<p>Forces output similar to Natural for OpenVMS Version 2.1.</p> <p>The following control character codes are used:</p> <table border="1"> <thead> <tr> <th>Control Code</th> <th>Interpretation</th> </tr> </thead> <tbody> <tr> <td>\n</td> <td>Line feed before printing this line</td> </tr> <tr> <td>\f</td> <td>Form feed before printing this line</td> </tr> </tbody> </table> <p>The <code>FIN</code> command will be generated if it is not specified in the batch command file CMSYNIN.</p>	Control Code	Interpretation	\n	Line feed before printing this line	\f	Form feed before printing this line						
	Control Code	Interpretation												
	\n	Line feed before printing this line												
\f	Form feed before printing this line													
OS	Forces output similar to Natural for UNIX or OpenVMS.													

		The following control character codes are used:	
		Control Code	Interpretation
		\n	Line feed before printing this line
		\f	Form feed before printing this line
Default setting	05		
Dynamic specification	yes		
Specification within session	no		

14 BMTIME - Display Process Time

This Natural profile parameter is used to display the elapsed and used CPU time consumed by the Natural process. This output will be written to the end of the batch output file [CMPRINT](#).



Note: This Natural profile parameter applies to batch mode only.

Possible settings	ON	The elapsed and used CPU time is written to the end of the batch output file.
	OFF	The output is not written to the batch output file.
Default setting	OFF	
Dynamic specification	yes	
Specification within session	no	

The time format is as follows:

DDDxHH:II:SS.UU

Where:

- *DDD* is the number of days (at maximum 999)
- *x* is blank if *DDD* is less or equal to 999,
or + (plus sign) if *DDD* is greater than 999
- *HH* is the number of hours
- *II* is the number of minutes
- *SS* is the number of seconds
- *UU* is the number of hundredths of seconds

Example:

```
Used CPU time:  0 00:00:00.56  
Elapsed time:  0 00:00:16.20
```

15

BMTITLE - Display Window Title

This Natural profile parameter is used to control the displaying of window titles in the batch output file [CMPRINT](#).



Note: This Natural profile parameter applies to batch mode only.

Possible settings	ON	A window title will be displayed in CMPrint.
	OFF	No window title will be displayed in CMPrint.
Default setting	ON	
Dynamic specification	yes	
Specification within session	no	

16

BMVERSION - Display Natural Version

This Natural profile parameter is used to control the display of the Natural version including the startup and termination time.

Possible settings	ON	The Natural version and startup time are written to the very first line of the batch output file <code>CMPRINT</code> , the termination time is written at the end of <code>CMPRINT</code> .
	OFF	The Natural version and startup time are not written to <code>CMPRINT</code> .
Default setting	OFF	
Dynamic specification	yes	
Specification within session	no	

17

BPID - Specify Buffer Pool ID

This Natural profile parameter specifies the name (ID) of the Natural buffer pool.

Possible settings	1 - 8 characters	Name of the Natural buffer pool.
Default setting	NATBP	
Dynamic specification	yes	
Specification within session	no	



Note: Do not delete the default buffer pool NATBP, as it is possible that Natural may not function properly anymore.

18

BPNAME - Name of Natural Global Buffer Pool

This Natural profile parameter specifies the name of the Natural global buffer pool.

Possible settings	1 - 8 characters or ' ' (blank)	Name of the Natural global buffer pool. If BPNAME=' ' (blank) is set, a <i>local</i> Natural buffer pool is used.
Default setting	' ' (blank)	
Dynamic specification	yes	This parameter can only be specified dynamically.
Specification within session	no	

19

BPSFI - Object Search First in Buffer Pool

This Natural profile parameter determines the sequence in which a requested object that is to be executed is searched for in the buffer pool and in the system file(s).

You can choose between two search sequences:

Possible settings	ON	<p>Search Sequence 1 is used (search buffer pool first for all libraries, then the system file(s)).</p> <p>Natural looks for the object in the following sequence until it is found:</p> <ol style="list-style-type: none">1. in the buffer pool, first in the current library, then in one steplib after another, then in the two SYSTEM libraries;2. in the system file(s), first in the current library, then in one steplib after another, then in the two SYSTEM libraries. <p>For performance reasons, it is recommended that you set BPSFI=ON in production environments.</p> <p>Caution: If you set BPSFI=ON, make sure that object names are unique across all libraries that are involved in the search. If objects with the same name exist in different libraries being searched, unpredictable results may occur.</p>
	OFF	<p>Search Sequence 2 is used (alternating search in buffer pool and system file(s) for each library).</p> <p>Natural looks for the object in the following sequence until it is found:</p> <ol style="list-style-type: none">1. in the current library, first in the buffer pool, then in the system file(s);2. in one steplib after another, first in the buffer pool, then in the system file(s) for each steplib;3. in the two SYSTEM libraries, first in the buffer pool, then in the system file(s) for each library.

		BPSFI=OFF is recommended in development environments to always get the most current object from your own current library.
Default setting	OFF	
Dynamic specification	yes	
Specification within session	no	

For further information, see *Steplibs* and *Search Sequence for Object Execution* in the *Using Natural* documentation.

20

CC - Error Processing in Batch Mode

This Natural profile and session parameter specifies the action to be taken if an error is detected during the compilation/execution of a Natural program in batch mode.

Possible settings	ON	Natural flushes the input data stream for the batch input files CMSYNIN and CMOBJIN until a line containing %% in the first two positions is encountered or until an end-of-file condition is detected. If more data are available in the input stream, Natural resumes reading after the line containing %.	
	OFF	Natural attempts to process the next program (or command) in the input stream. If all input is processed, Natural terminates with Return Code 61 and writes the Natural error 9987 (Error occurred during execution/compilation.) to the batch output file (if the profile parameter ENDMSG is set to ON).	
Default setting	OFF		
Dynamic specification	yes		
Spezifikation in Session	yes	Applicable Statements:	
		Applicable command:	
Application programming interface	USR1005N	See <i>SYSEXT - Natural Application Programming Interfaces</i> in the <i>Utilities</i> documentation.	



Notes:

1. This Natural profile and session parameter only applies in batch mode.
2. It does not apply if user-written error-handling routines are used.
3. Within a Natural session, the profile parameter `CC` can be overridden by the session parameter `CC`.

21 CD - Color Definition

With this session parameter, you specify the color attributes for fields. If no color screen is used, this parameter will be ignored at runtime.

Related session parameter: [AD - Attribute Definition](#)

Possible settings	BL	blue
	GR	green
	NE	neutral
	PI	pink
	RE	red
	TU	turquoise
	YE	yellow
Default setting	NE	
Applicable statements	FORMAT	
	DISPLAY INPUT PRINT WRITE	Parameter may be specified at statement level and/or at element level.
	ASSIGN MOVE REINPUT	Parameter may be specified at statement level.
Applicable command	none	

Example:

```
INPUT (CD=RE) #A #B
```

22

CDYNAM - Dynamic Loading of Non-Natural Programs

This Natural profile parameter determines whether or not non-Natural programs are to be loaded dynamically by Natural.

Possible settings	ON	Any number of non-Natural programs can be loaded dynamically during the execution of a Natural program.
	OFF	Dynamic loading of non-Natural programs is not performed by Natural.
Default setting	ON	
Dynamic specification	yes	
Specification within session	no	

23

CF - Character for Terminal Commands

This Natural profile and session parameter specifies the control character for Natural terminal commands; that is, the character which is to be used as the first character of any terminal command.

Possible settings	any special character	A terminal command must begin with the character specified here. The character specified with the CF parameter <ul style="list-style-type: none"> ■ must not be the same as the one specified with the HI parameter (help character) or IA parameter (input assign character). ■ should not be the same as the one specified with the DC parameter (decimal character) or ID parameter (input delimiter character). ■ In the map editor, the control character for terminal commands is always “%” (so as to avoid conflicts with delimiter characters used in maps), no matter which character is defined with the CF parameter. 	
	OFF	No control character for terminal commands is available. Terminal commands issued with SET CONTROL statements, however, are still accepted.	
Default setting	%	A terminal command must begin with the character “%”.	
Dynamic specification	yes		
Specification within session	yes	Applicable statements:	SET GLOBALS
		Applicable command:	GLOBALS
Application programming interface	USR1005N	See SYSEXT - <i>Natural Application Programming Interfaces</i> in the <i>Utilities</i> documentation.	



Notes:

1. Within a Natural session, the profile parameter CF can be overridden by the session parameter CF.

2. Under Natural Security, the setting of this parameter can be overridden by the *Session Parameters* option of the Library Profile.

24 CLEAR - Processing of CLEAR Key in NEXT Mode

This Natural profile parameter causes Natural to execute a specific Natural terminal command whenever CLEAR is pressed during program execution in NEXT mode.

Possible settings	any character	The default action can be overridden by supplying a character which, when appended to the terminal-command control character (as specified with the CF parameter), forms a valid Natural terminal command.
Default setting	%	By default, when the CLEAR key is pressed, Natural responds as if the user had entered the terminal command %%.
Dynamic specification	yes	
Specification within session	no	



Note: Under Natural Security, the setting of this parameter can be overridden by the Session Parameters option of the Library Profile.

Example:

```
CF=%  
CLEAR=R
```

Natural executes the terminal command %R when the CLEAR key is pressed in NEXT mode.

25

CM - Command Mode

This Natural profile parameter can be used to suppress Natural command mode (NEXT and MORE).

Possible settings	ON	NEXT and MORE are available for command input.
	OFF	The Natural session will be terminated whenever NEXT is encountered; the MORE line will be write-protected (no input possible).
Default setting	ON	
Dynamic specification	no	
Specification within session	no	

26

CMOBJIN - Batch Input File for Natural INPUT Data

This Natural profile parameter is used for data intended to be read by Natural `INPUT` statements. These types of data can alternatively be placed in the `CMSYNIN` file immediately following the relevant `RUN` or `EXECUTE` command. The number of characters actually processed is restricted to 512 characters per line.

Possible settings	any string	
Default setting	none	
Dynamic specification	yes	
Specification within session	no	



Notes:

1. This Natural profile parameter applies to batch mode only.
2. If the file name or path assigned to this parameter contains special characters (e.g. backslash) or spaces, the entire string must be enclosed in double quotes, see example below.
3. If the setting for the profile parameter `CMSYNIN` is equal to the setting of `CMOBJIN`, Natural reads input from `CMSYNIN`.
4. If an error occurs, Natural reacts in accordance with the setting of the profile/session parameter `CC`.

Example:

```
CMOBJIN="node:[home.tmp]batch.inp"
```


27

CMPRINT - Batch Output File

This Natural profile parameter applies to batch mode only.

It is used to specify the batch output file for the output report resulting from `DISPLAY`, `PRINT` and `WRITE` statement in a Natural program. In addition, Natural commands from `CMSYNIN` and `INPUT` data from `CMOBJIN` are written to `CMPRINT`.



Note: If the file name or path assigned to this parameter contains special characters (for example, backslash) or spaces, the entire string must be enclosed in double quotes, see example below.

Possible settings	any string	<code>CMPRINT="node:[home.tmp]batch.out"</code>
Default setting	none	
Dynamic specification	yes	
Specification within session	no	

28

CMPRTnn - Additional Report

This Natural profile parameter applies to batch mode only.

It is used for additional reports referenced by any Natural program executed during the session. *nn* is a two digit decimal number in the range from 01 to 31 corresponding to the LPT device used by a report in a DISPLAY, PRINT and WRITE statement.

Possible settings	any string	If the file name or path assigned to this parameter contains special characters, e.g. backslash (\) or spaces, the entire string must be enclosed in double quotes. Example: CMPRT07="node:[home.tmp]report7.txt"
Default setting	none	
Dynamic specification	yes	
Specification within session	no	

In order to allow the user to specify variable print file names, alpha-format system variables and numeric counter markers may be embedded in the file name specification for CMPRT*nn*.

The supported alpha-format system variables are:

- *APPLIC-ID
- *APPLIC-NAME
- *DEVICE
- *ETID
- *INIT-USER
- *LIBRARY-ID
- *NET-USER
- *PID
- *PROGRAM

*USER
*USER-NAME

If any of these strings (in upper case only) is encountered within the print file specification, it will be replaced at run-time with the contents of the appropriate system variable. Additionally, a counter marker (#) may be used. This will be replaced by a 2-digit counter which will automatically be incremented for each print file.

Example:

The specification `CMPRT01=abc_*PID_*ETID_*PROGRAM_#.dat` in a Natural session with process ID 1234, ETID XYZ running a program with the name PRINT which produces print file output to File 01 would produce print files with the following names (assuming the program runs 3 times):

```
abc_1234_XYZ_PRINT_01.dat  
abc_1234_XYZ_PRINT_02.dat  
abc_1234_XYZ_PRINT_03.dat
```

See also *Using Natural in Batch Mode* in the *Operations* documentation.

29 CMSYNIN - Batch Input File for Natural Commands and INPUT Data

This Natural profile parameter applies to batch mode only.

CMSYNIN is used for the batch input file. It contains Natural commands and data to be read by INPUT statements during execution of Natural programs (optionally). The number of characters actually processed is restricted to 512 characters per line.



Note: If the file name or path assigned to this parameter contains special characters, e.g. backslash (\) or spaces, the entire string must be enclosed in double quotes, see example below.

Possible settings	any string	CMSYNIN="node:[home.tmp]batch.cmd"
Default setting	none	
Dynamic specification	yes	
Specification within session	no	

See also *Using Natural in Batch Mode* in the *Operations* documentation.

30 CMWRKnn - Natural Work Files

This Natural profile parameter applies to batch mode only.

CMWRKnn is used for Natural work files referenced by any Natural program executed during the session.

nn is a two digit decimal number in the range from 01 to 32 corresponding to the number used in a READ WORK FILE or WRITE WORK FILE statement.



Note: If the file name or path assigned to this parameter contains special characters, e.g. backslash (\) or spaces, the entire string must be enclosed in double quotes, see example below.

Possible settings	any string	CMWRK05="node:[home.tmp]workfile5.sag"
Default setting	none	
Dynamic specification	yes	
Specification within session	no	

See also *Using Natural in Batch Mode* in the *Operations* documentation.

31 CO - Compiler Output

This Natural profile and session parameter can be used to deactivate or reactivate the compiler operation-in-progress window wherein, by default, the code is displayed as it is processed by the compiler.

Possible settings	ON	A compiler listing is displayed in a special operation-in-progress window on the screen. This setting is useful in the event of a crash because the code display will stop at the position affected. Note: This setting should be used only if actually needed, because it results in a significantly longer compilation time. Especially a CATAL command will take a rather long time to compile all objects. CO=ON is not supported in batch mode.
	OFF	Compiler operation-in-progress window off.
Default setting	OFF	
Dynamic specification	yes	
Specification within session	yes	
Applicable statements	SET GLOBALS	
Applicable command	GLOBALS	

32 COMPR - Set RPC Buffer Compression

This Natural profile parameter can be used to set the RPC buffer compression.

Possible settings	0	No compression will be performed.
	1	The send buffer contains modifiable fields and output fields and the format buffer. The reply buffer contains modifiable fields and input fields.
	2	Same as COMPR=1, additionally the reply buffer also contains the format buffer.
Default setting	1	
Dynamic specification	yes	
Specification within session	yes	At runtime, this value can be overwritten using the Parameter Maintenance function of the SYSRPC utility.



Notes:

1. COMPR is specified on the client side only.
2. COMPR is effective only, if the automatic Natural RPC execution is used (`AUTORPC=ON`) and the `CALLNAT` is executed without a stub. If a stub is used, the compression has already been set during stub generation. For details, see *Using Compression* in the *Natural Remote Procedure Call* documentation.
3. For further information, see the *Natural Remote Procedure Call (RPC)* documentation.

33 CP - Default Code Page Name

This Natural profile parameter defines the default code page for Natural data and Natural sources.

Possible settings	1 - 64 characters	The name of the desired code page.
	' ' (blank)	Reset to system code page.
Default setting	' ' (blank)	System code page.
Dynamic specification	yes	
Specification within session	no	

34

CPCVERR - Code Page Conversion Error

This Natural profile and session parameter specifies whether a conversion error that occurs when converting

- from Unicode to code page or
- from code page to Unicode or
- from one code page to another code page

results in a Natural error or not. Anyway, after the conversion, the target operand will contain the conversion result where all characters which can not be converted will be replaced by a substitution character which is defined by ICU for the affected code page.



Notes:

1. This parameter is not regarded for the conversion of Natural sources when loading them into the source area or during catalog.
2. On mainframe platforms, it is not regarded whether a Unicode field is converted into the code page before an I/O on a terminal emulation. In this case, the substitution character is replaced by the place holder character which is defined in NATCONFIG.

Possible settings	ON	A Natural error NAT3413 is issued, if at least one code point could not be translated correctly during ICU conversion.
	OFF	No error is generated if one or more code points could not be translated correctly during ICU conversion.
Default setting	ON	
Dynamic specification	yes	
Specification within session	yes	
Applicable statements	SET GLOBALS	
Applicable command	GLOBALS	

See also:

- *Profile Parameters in the Unicode and Code Page Support* documentation.
- *Using an Error Transaction Program in the Programming Guide*

35

CPOBJIN - Code Page of Batch Input File

This Natural profile parameter specifies the code page of the batch input file which is defined by the Natural profile parameter [CMOBJIN](#).

Possible settings	1 -64 characters	ICU code page name (IANA name recommended).
	' ' (blank)	The code page resulting from the evaluation of the profile parameter CP is used.
Default setting	' ' (blank)	
Dynamic specification	yes	
Specification within session	no	

See also *Profile Parameters* in the *Unicode and Code Page Support* documentation.

36

CPPRINT - Code Page of Batch Output File

This Natural profile parameter specifies the code page of the batch output file which is defined by the Natural profile parameter [CPPRINT](#).

Possible settings	1 - 64 characters	ICU code page name (IANA name recommended).
	' ' (blank)	The code page resulting from the evaluation of the profile parameter CP is used.
Default setting	' ' (blank)	
Dynamic specification	yes	
Specification within session	no	

See also *Profile Parameters* in the *Unicode and Code Page Support* documentation.

37 CPRPC - Define Code Page Name

This parameter specifies the name of the code page used by the EntireX Broker.



Note: Currently, it applies only to the Natural RPC facility when the transport protocol ACI (that is EntireX Broker) is used.

Possible settings	1 - 40 characters	Valid code page name of EntireX Broker.
Default setting	none	
Dynamic specification	yes	
Specification within session	no	



Notes:

1. CPRPC can be specified on both the client and the server side.
2. For information on the EntireX Broker, refer to the section about Software AG's Internationalization in the EntireX Broker documentation.
3. See also *Unicode and Code Page Support, Configuration and Administration of the Unicode/Code Page Environment, Profile Parameters*.

38

CPSYNIN - Code Page of Batch Input File for Commands

This Natural profile parameter specifies the code page of the batch input file for commands which is defined by the Natural profile parameter [CMSYNIN](#).

Possible settings	1 - 64 characters	ICU code page name (IANA name recommended).
	' ' (blank)	The code page resulting from the evaluation of the profile parameter CP is used.
Default setting	' ' (blank)	
Dynamic specification	yes	
Specification within session	no	

See also *Profile Parameters* in the *Unicode and Code Page Support* documentation.

39 CV - Attribute Control Variable

This session parameter is used to reference an attribute control variable.

Possible settings	B, C, D, I, N, U, V	Field representation attributes (see session parameter AD).
	P	Field protection (see session parameter AD).
	BL, GR, NE, PI, RE, TU, YE	Color (for an explanation of the color codes, see the session parameter CD).
Default setting	none	
Applicable statements	DISPLAY INPUT PRINT PROCESS PAGE WRITE	Parameter may be specified at statement level and/or at element level.
Applicable command	none	



Notes:

1. An attribute control variable is defined with Format C (see *Special Formats* in the *Programming Guide*) and is used to assign field attributes dynamically and/or check the “modified” status of a field in conjunction with an INPUT or PROCESS PAGE statement; see also *Logical Condition Criteria, MODIFIED Option - Check whether Field Content has been Modified* in the *Programming Guide*.
2. By specifying the MODIFIED option of the IF statement, the attribute control variable can be used to check whether the contents of a field has been modified during the execution of an INPUT or PROCESS PAGE statement: `IF #ATTR MODIFIED ...`
3. A single attribute control variable can be applied to several input fields by specifying it once at statement level or multiple times at element level, in which case the “modified” status indication is set if any of the fields referencing the control variable has been modified. If the CV parameter is specified both at statement level and at field level and the attribute control variable

for the individual field is empty, the attribute control variable for the statement will be used for the field.

4. The attribute control variable can be expanded up to three dimensions, for example, `CONTR(*)`, `CONTR(*,*)`, `CONTR(*,*,*)`, depending on the rank of the corresponding array.

Example:

```
DEFINE DATA LOCAL
1 #ATTR(C)
1 #A (N5)
END-DEFINE
...
MOVE (AD=I CD=RE) TO #ATTR
INPUT #A (CV=#ATTR)
...
```


40

CVMIN - Control Variable Modified at Input

This Natural profile parameter determines whether or not an attribute control variable is assigned the status `MODIFIED` when the setting of the field to which the attribute control variable is attached is overwritten by an *identical* setting.

Possible settings	ON	If a field setting is overwritten by the same setting, the corresponding control variable will be assigned the status <code>MODIFIED</code> .
	OFF	If a field setting is overwritten by the same setting, the corresponding control variable will <i>not</i> be assigned the status <code>MODIFIED</code> .
Default setting	OFF	
Dynamic specification	yes	
Specification within session	no	



Note: If an attribute control variable has been assigned the status `MODIFIED`, the `MODIFIED` option evaluates this as `TRUE`. This applies regardless of whether the input was entered manually, read from the stack or supplied in batch mode.

41 DBSHORT - Interpretation of Database Field Short Names

This Natural profile and session parameter can be used to determine the interpretation of database field short names. It corresponds to the option `DBSHORT` of the Natural system command `COMPOPT`.

A database field defined in a DDM is described by two names:

- the short name with a length of 2 characters, used by Natural to communicate with the database (especially with Adabas);
- the long name with a length of 3-32 characters (1-32 characters, if the underlying database type accessed is DB2/SQL), which is supposed to be used to reference the field in the Natural programming code.

Under special conditions, you may reference a database field in a Natural program with its short name instead of the long name. This applies if running in Reporting Mode without Natural Security and if the database access statement contains a reference to a DDM instead of a view.

The decision if a field name is regarded as a short-name reference depends on the name length. When the field identifier consists of two characters, a short-name reference is assumed; a field name with another length is considered as a long-name reference. This standard interpretation rule for database fields can additionally be influenced and controlled by setting the compiler option `DBSHORT` to `ON` or `OFF`:

Possible settings	ON	Using a short name is allowed for referencing a database field. However, a data base short name is <i>not permitted</i> in general (even if <code>DBSHORT=ON</code>) <ul style="list-style-type: none">■ for the definition of a field when a view is created;■ when a <code>DEFINE DATA LOCAL</code> statement was specified;■ when running under Natural Security.
--------------------------	----	--

	OFF	<p>A database field may only be referenced via its long name. Every database field identifier is considered as a long-name reference, regardless of its length.</p> <p>If a two character name is supplied which can only be found as a short name but not as a long name, syntax error NAT0981 is raised at compile time.</p> <p>This makes it possible to use long names defined in a DDM with 2-byte identifier length. This option is essential if the underlying database you access with this DDM is SQL (DB2) and table columns with a two character name exist. For all other database types (for example, Adabas), however, any attempt to define a long field with a 2-byte name length will be rejected at DDM generation.</p> <p>Moreover, if no short-name references are used (what can be enforced via DBSHORT=OFF), the program becomes independent of being compiled without Natural Security.</p>
Default setting	ON	
Dynamic specification	yes	
Specification within session	yes	
Applicable statements	OPTIONS	
Applicable command	DBSHORT option of COMPOPT	

Examples:

Assume the following data base field definition in the DDM EMPLOYEES:

Short Name	Long Name
AA	PERSONNEL-ID

Example 1:

```

OPTIONS DBSHORT=ON
READ EMPLOYEES
  DISPLAY AA      /* data base short name AA is allowed
END
    
```

Example 2:

```
OPTIONS DBSHORT=OFF
READ EMPLOYEES
  DISPLAY AA      /* syntax error NAT0981, because DBSHORT=OFF
END
```

Example 3:

```
OPTIONS DBSHORT=ON
DEFINE DATA LOCAL
1 V1 VIEW OF EMPLOYEES
  2 PERSONNEL-ID
END-DEFINE
READ V1 BY PERSONNEL-ID
  DISPLAY AA      /* syntax error NAT0981, because PERSONNEL-ID is defined in view;
                  /* (even if DBSHORT=ON)
END-READ
END
```


42 DBUPD - Database Updating

This Natural profile parameter indicates whether database updating is to be permitted during the Natural session.

Possible settings	ON	Database update is permitted.
	OFF	Database update is not permitted. A Natural statement which would cause a database update (STORE, UPDATE, DELETE) is not executed and an error message is generated.
Default setting	ON	
Dynamic specification	yes	
Specification within session	no	
Application programming interface	USR1005N	See <i>SYSEXT - Natural Application Programming Interfaces</i> in the <i>Utilities</i> documentation.
	USR1042N *	* Recommended.



Note: The DBUPD setting has no effect on the execution of Natural system commands.

43

DC - Character for Decimal Point Notation

This Natural profile and session parameter determines the character to be used as decimal separator, that is, a point or a comma.

Possible settings	any special character	<p>The character assigned to DC will be in effect for all notations where a decimal separator is possible; that is, variables, constants and edit masks. The character specified with the DC parameter</p> <ul style="list-style-type: none"> ■ must not be the same as the one specified with the IA profile/session parameter (input assign character) or ID profile/session parameter (input delimiter character), ■ should not be the same as the one specified with the CF profile/session parameter (control character for terminal commands) or HI profile parameter (help character). 		
Default setting	. (period)			
Dynamic specification	yes			
Specification within session	yes	Applicable statements:	SET GLOBALS	Parameter is evaluated at runtime.
		Applicable command:	GLOBALS	Parameter may be specified dynamically with the GLOBALS system command.
Application programming interface	USR1005N	See SYSEXT - <i>Natural Application Programming Interfaces</i> in the Utilities documentation.		



Notes:

1. Within a Natural session, the profile parameter DC can be overridden by the session parameter DC.

2. If you change DC in your parameter file, you must resave the DDM you are using in your Natural program which stores a new .NSD file on disk.
3. Under Natural Security, the setting of this parameter can be overridden by the Session Parameters option of the *Library Profile*.

44 DD - Day Differential

This Natural profile parameter is used to adjust the current machine date (as read by using the internal machine time) by adding/subtracting any number of days to/from it. This makes it possible to re-run an application that was to be run at a certain date but for some reason could not be run at that date.

The DD profile parameter is specified as follows:

DD=+nn

or

DD=-nn

where *nn* is the number of days.

Possible settings	-10953 to +10953	Machine date is adjusted. Specification of "+" is optional.
	0	No adjustment is made.
Default setting	0	
Dynamic specification	yes	
Specification within session	no	
Application programming interface	USR1005N	See <i>SYSEXT - Natural Application Programming Interfaces</i> in the <i>Utilities</i> documentation.

See also the profile parameter [TD](#).

45 DF - Date Format

With the DF session parameter, you determine the length of a date when converted into alphanumeric representation without an edit mask being specified.

Possible settings	S	8-byte representation with 2-digit year component and delimiters (<i>yy-mm-dd</i>). With DF=S, only 2 digits are provided for the year information; this means that if the date value contained the century, this information would be lost during the conversion.
	I	8-byte representation with 4-digit year component and no delimiters (<i>yyyymmdd</i>). See Note .
	L	10-byte representation with 4-digit year component and delimiters (<i>yyyy-mm-dd</i>). See Note .
Default setting	S	
Applicable statements	FORMAT	
	INPUT DISPLAY WRITE PRINT	Parameter may be specified at statement level and/or at element level.
	MOVE COMPRESS STACK RUN FETCH	Parameter may be specified at element level.
Applicable command	none	



Notes:

1. The DF parameter is evaluated at compilation time.

2. The sequence of the day, month and year components and the delimiter characters used are determined by the profile parameter `DTFORM`.
3. When the value of a date field is converted into alphanumeric format (for example, in a `MOVE`, `DISPLAY`, `WRITE` or `INPUT` statement) and no edit mask is specified for the conversion, the default date format as determined by the profile parameter `DTFORM` is used as edit mask.
4. The same is true for the input validation of a date variable used in an `INPUT` statement: If no edit mask is specified, the input is validated according to the date format determined by the `DTFORM` parameter.
5. By using `DF=I` or `DF=L`, you can gradually change your applications to use 4-digit year representations and at the same time continue to make use of the flexibility provided by the profile parameter `DTFORM`.
6. See also *Date Format for Alphanumeric Representation - DF Parameter* in the *Programming Guide*.

46

DFOUT - Date Format for Output

This Natural profile and session parameter determines the format in which the settings of date variables are displayed by `INPUT`, `DISPLAY`, `PRINT` and `WRITE` statements.

Possible settings	S	Date variables are displayed with a 2-digit year component, and delimiters as determined by the profile parameter <code>DTFORM</code> .	
	I	Date variables are displayed with a full 4-digit year component and no delimiters.	
Default setting	S		
Dynamic specification	yes		
Specification within session	yes	Applicable statements:	SET GLOBALS
		Applicable command:	GLOBALS
Application programming interface	USR1005N	See <i>SYSEXT - Natural Application Programming Interfaces</i> in the <i>Utilities</i> documentation.	



Notes:

1. Within a Natural session, the profile parameter `DFOUT` can be overridden by the session parameter `DFOUT`.
2. The *profile parameter* `DFOUT` is evaluated at runtime.
3. It applies to date fields in `INPUT`, `DISPLAY`, `PRINT` and `WRITE` statements for which no explicit edit mask is specified and for which the *session parameter* `DF` is not set.

4. The sequence of the day, month and year components in the date settings is determined by the [DTFORM](#) profile parameter.
5. See also *Processing of Date Information* in the *Programming Guide*.

47

DFS - Specify RPC Client's Default Server Address

This Natural profile parameter can be used to define an RPC default server address by specifying up to 4 subparameters.

Possible settings	See <i>DFS Parameter Syntax</i> .	
Default setting	none	Subparameter defaults, see <i>DFS Parameter Syntax</i> .
Dynamic specification	yes	See below.
Specification within session	yes	At runtime, this value can be overwritten using the Natural application programming interface USR2007N.
Application programming interface	USR2007N	See <i>Application Programming Interfaces for Use with Natural RPC</i> in the <i>Natural Remote Procedure Call (RPC)</i> documentation and <i>SYSEXT - Natural Application Programming Interfaces</i> in the <i>Utilities</i> documentation.



Notes:

1. DFS is specified on the client side only.
2. DFS determines the server name, the server node, the logon indicator and the transport protocol. The default server address will be used only if no appropriate server is found in the service directory. For further information, see *Specifying RPC Server Addresses* in the *Natural Remote Procedure Call (RPC)* documentation.

DFS Parameter Syntax

The parameter syntax is as follows:

DFS=(*server-name,server-node,logon-indicator,transport-protocol-name,service-directory-indicator*)

Where:

Syntax Element	Value	Explanation
<i>server-name</i>	1 - 192 characters	Valid server name. See also parameter SRVNAME . There is no default, the value must be specified.
<i>server-node</i>	1 - 192 characters	Node name. See also parameter SRVNODE . There is no default, the value must be specified.
<i>logon-indicator</i>	L	The client initiates a Natural logon to the server with the library name of the current library on the client. On Windows platforms: Instead of specifying L, check the selection box.
	(blank)	Blank means that no server logon will be executed. If nothing is specified, this is the default.
<i>transport-protocol-name</i>	ACI	The transport protocol to be used. ACI is the only possible value and the default.
<i>service-directory-indicator</i>	SERVDIR	A service directory must be present before the DFS profile parameter is evaluated.
	NOSERVDIR	No service directory is used before the DFS profile parameter is evaluated; that is, a service directory needs not be available on the client side. If nothing is specified, SERVDIR is the default.

48

DFSTACK - Date Format for Stack

This Natural profile and session parameter determines the format in which the settings of date variables are placed on the stack via a `STACK`, `RUN` or `FETCH` statement.

Possible settings	S	Date variables are placed on the stack with a 2-digit year component, and delimiters as determined by the profile parameter <code>DTFORM</code> . Example: <i>yy-mm-dd</i>	
	C	Same as <code>DFSTACK=S</code> . In addition, if the century used when the setting is read from the stack is not the same as that of the original date setting, Natural will issue a runtime error.	
	I	Date variables are placed on the stack with a full 4-digit year component and no delimiters. Example: <i>yyyymmdd</i>	
Default setting	S		
Dynamic specification	yes		
Specification within session	yes	Applicable statement:	SET GLOBALS
		Applicable command:	GLOBALS
Application programming interface	USR1005N	See <i>SYSEXT - Natural Application Programming Interfaces</i> in the <i>Utilities</i> documentation.	



Notes:

1. Within a Natural session, the profile parameter `DFSTACK` can be overridden by the session parameter `DFSTACK`.
2. The profile parameter `DFSTACK` does not apply to `STACK`, `RUN` or `FETCH` statements for which the session parameter `DF` is set.
3. See also *Processing of Date Information* in the *Programming Guide*.

49

DFTITLE - Output Format of Date in Standard Report Title

This Natural profile and session parameter determines the output format of the date in the default title line of a report page (as output with a DISPLAY, WRITE or PRINT statement).

Possible settings	S	The date is output with a 2-digit year component and delimiters. Example: <i>yy-mm-dd</i>	
	L	The date is output with a 4-digit year component and delimiters. Example: <i>yyyy-mm-dd</i>	
	I	The date is output with a 4-digit year component and no delimiters. Example: <i>yyyymmdd</i>	
Default setting	S		
Dynamic specification	yes		
Specification within session	yes	Applicable statement:	SET GLOBALS
		Applicable command:	GLOBALS
Application programming interface	USR1005N	See <i>SYSEXT Utility - Natural Application Programming Interfaces in the Utilities</i> documentation.	



Notes:

1. Within a Natural session, the profile parameter DFTITLE can be overridden by the session parameter DFTITLE.
2. DFTITLE is evaluated at runtime and determines whether the date is displayed with a 2-digit or 4-digit year component with or without delimiters.

3. It has no effect on a user-defined page title (as specified with a `WRITE TITLE` statement).
4. The sequence of the day, month and year components and the delimiter characters used are determined by the profile parameter `DTFORM`.
5. See also *Processing of Date Information* and *Date Format for Default Page Title - DFTITLE Parameter* in the *Programming Guide*.

50 DL - Display Length for Output

With this session parameter, you specify the display length for a field of format A or U. The default display length is the length of the field.

Possible settings	1 to n	n = value of LS (line size) parameter minus 1
Default setting	none	
Applicable statements	FORMAT	
	DISPLAY INPUT PRINT WRITE	Parameter may be specified at statement level and/or at element level.
Applicable command	none	

Example:

```
FORMAT DL=20
```

For further information and an example of the DL session parameter usage, see the following topics in the *Programming Guide*:

- *Parameters to Influence the Output of Fields*
- *Output Length - AL and NL Parameters*
- *Display Length for Output - DL Parameter*

51 DO - Display Order of Output Data

This Natural profile and session parameter specifies how fields are to be interpreted for display on terminals that support bidirectional data.

Possible settings	L	Specifies that the data from the application is in logical display order. Note: The field characters are displayed according to their character property (left-to-right or right-to-left).	
	V	Specifies that the data from the application is in visual order. Note: 1. All fields are inverted by Natural before they are sent to the terminal. 2. This option is required for old applications written for terminals which support inverse (right-to-left) print mode, activated by profile parameter PM=I or terminal command %VON.	
Default setting	L		
Dynamic specification	yes		
Specification within session	yes	Applicable statement:	SET GLOBALS
		Applicable command:	GLOBALS



Notes:

1. The I/O device must be able to create the correct display order depending on the character properties. This is for instance the case if an application runs in a browser under Natural Web I/O Interface. For other terminal types, this parameter does not have any effect.
2. For detailed information on how to use the setting PM=I, see *Bidirectional Language Support in the Unicode and Code Page Support* documentation.

52

DTFORM - Date Format

This Natural profile parameter indicates the default format in which dates are to be provided automatically by Natural as part of the default title on Natural reports, as date constants and date input.

Possible settings	Value	Area	Date Format
	E	Europe	DD/MM/YYYY
	G	Germany	DD.MM.YYYY
	I	International	YYYY-MM-DD
	U	USA	MM/DD/YYYY
Default setting	I		
Dynamic specification	yes		
Specification within session	no		
Application programming interface	USR1005N	See <i>SYSEXT - Natural Application Programming Interfaces</i> in the <i>Utilities</i> documentation.	



Notes:

1. The first day of a week is assumed to be Monday - unless DTFORM=U is specified, in which case Sunday is used.
2. For date constants, the year component (YYYY) consists of all four digits. Only the last two digits of the year component are used for reports, date input, the Natural system function VAL, and when the date is moved to an alphanumeric field.
3. The output format of the date in a default report page title is also specified by the profile parameter [DFTITLE](#).
4. See also *Processing of Date Information* and *Default Edit Mask for Date - DTFORM Parameter* in the *Programming Guide*.

53 DU - Dump Generation

This Natural profile and session parameter determines whether a disassembled object code dump is to be generated.

Possible settings	ON	<p>When one of the system commands CHECK, STOW, CATALOG, RUN or CATALL is executed, a disassembled object code file is produced.</p> <p>This dump file is written into the directory which is defined in the Natural TMP directory option in the Natural Configuration Utility; see <i>Local Configuration File, Installation Assignments</i>.</p> <p>The name of this dump file consists of the source file name and the extension .DIA. If the source file has not been saved, the name of the dump file is GEN.DIA. If the program contains database access statements, dump files with the extension .ADA (for Adabas) or .SQL (for SQL databases) are also created. If XREF data are generated, a dump file .XRF is created.</p> <p>Note: DU=ON may create a large dump file (depending on the size of the source file), which can cause significant degradation in system performance.</p>
	OFF	No dump file is generated.
Default setting	OFF	
Dynamic specification	yes	
Specification within session	yes	
Applicable statements	SET GLOBALS	
Applicable command	GLOBALS	



Note: Within a Natural session, the profile parameter DU can be overridden by the session parameter DU.

54

DY - Dynamic Attributes

- DY Parameter Syntax 118
- Examples 120

This session parameter is used to assign attributes for dynamic attribute field display.

Possible settings	See <i>DY Parameter Syntax</i> .	
Default setting	none	
Applicable statements	DISPLAY INPUT PRINT WRITE	Parameter may be specified at statement level and/or at element level.
Applicable command	none	

Special identification characters (escape characters) are used to indicate the beginning and end of attribute definitions.

An alphanumeric field which is processed with an INPUT, DISPLAY, WRITE or PRINT statement, and which contains escape characters, is split into subfields at the escape character position. The corresponding attribute is then assigned to the subfield. A blank is substituted for the escape character.



Note: For a part of a field for which a DY specification applies, the current field presentation and color attributes remain in effect, unless new settings are defined in the DY entry. This means, the field color is only changed by a DY attribute if the DY parameter itself defines a new color. The same applies to the **field representation attributes**, such as (AD=B,C,D,I,N,U,V).

The following topics are covered below:

DY Parameter Syntax

```
DY={{escape-character1} [color-attribute] [i/o-characteristics]
[field-representation-attribute]} ... {escape-character2}
```

The possible settings are explained below.

escape-character1

An escape character which denotes the beginning of the attribute definition. Any special character or a hexadecimal number preceded by an apostrophe ('xx) may be used.

color-attribute

The color attribute to be assigned. See also session parameter CD (color definition).

BL	blue
GR	green
NE	neutral
PI	pink
RE	red
TU	turquoise
YE	yellow

i/o-characteristics

Value	Meaning
P	Subfield is to be write-protected.

A P may be specified to make the subfield write-protected. See also session parameter [AD](#) (attribute definition).

field-representation-attribute

Additional attributes to be assigned. See also session parameter [AD](#) (attribute definition).

Value	Meaning
B	blinking (*)
C	cursive/italic (*)
D	default intensity
I	intensified
N	non-display
U	underlined
V	reverse video (*)

* The field representation attributes marked with an asterisk (*) require corresponding hardware features, and will be ignored at runtime if these features are not available.

escape-character2

An escape character which denotes the end of the attribute definition. Any special character (*c*) or a hexadecimal number preceded by an apostrophe (*'xx*) may be used.

You may specify up to eight escape sequences (escape characters and attributes) before the character indicating the end of the attribute definitions.

Examples

Example 1:

```
DY=<U>
```

The text string:

```
THIS <i s> UNDERLINED
```

is printed as:

```
THIS i s UNDERLINED
```

Example 2:

```
DY=<BL|RE/GR>
```

Assigns:

Blue to <

Red to |

Green to /

> switches back to the initial field color.

Example 3:

```
DY=<P>;
```

The text string:

```
Do not overwrite <this>
```

is printed as:

```
Do not overwrite this
```

(where this is protected)

55

DYNPARM - Control Use of Dynamic Parameters

This Natural profile parameter enables/disables the use of Natural dynamic parameters.

Possible settings	ON	Dynamic parameters supplied during Natural startup are processed.
	OFF	Dynamic parameters supplied during Natural startup are not processed. Note: If DYNPARM is set to OFF in the Natural default parameter file NATPARM, no alternative user-defined parameter files can be used when starting Natural.
Default setting	ON	
Dynamic specification	no	
Specification within session	no	

See *Dynamic Assignment of Parameter Values* for additional information on the use of dynamic parameters.

56

ECHO - Control Printing of Batch Input Data

This Natural profile parameter is used to enable or disable the printing of input data provided to Natural during batch mode processing.

Possible settings	ON	Natural prints the input data provided during batch mode processing to the batch output file CMPRINT.
	OFF	Natural does <i>not</i> print input data provided during batch processing.
Default setting	ON	
Dynamic specification	yes	
Specification within session	no	



Notes:

1. This Natural profile parameter only applies in batch mode.
2. It is also possible to suppress printing of a *single input line* by preceding it with a line containing the terminal command for record suppression %*.
3. Input read from CMSYNIN in command (NEXT) mode is echoed to the batch output file CMPRINT always.

57

ECPMOD - Entire Connection Protocol Mode

This Natural profile parameter determines the protocol that is used when downloading workfiles.

Possible settings	ON	The TCP/IP protocol is used.
	OFF	The ZMODEM protocol is used.
Default setting	ON	
Dynamic specification	yes	
Specification within session	no	

58

EDITOR - Other Program Editor

This Natural profile parameter can be used to invoke a program editor other than the standard editor provided by Software AG.

Possible settings	any character string	Name of the editor you want to use. Specification, see below.
Default setting	NATEDIT	Standard editor provided by Software AG.
Dynamic specification	no	
Specification within session	no	



Note: If an external editor is being used, the 4-digit line numbers at the beginning of each Natural source line have to be added manually, if an existing source is edited.

To use an external editor, specify the path and editor name:

```
path-name editor-name command-to-specify-line %l command-to-specify-file %f
```

The string before %l is replaced by the ASCII representation of the line number. The string before %f is replaced by the file name as known by Natural.

The use of an external editor is not recommended as code page conflicts may arise. These conflicts can - but not necessarily must - deteriorate your source code.

Examples:

```
$ EDIT/TPU %f
$ EDIT/TPU/COM=mydir:NATKEY.TPU %f
$ EDIT/TPU /START_POSITION=%1 %f
```

A sample TPU file named *NATKEY.TPU* is located in the Natural profile directory (`PROFILE_PATH`).

59

EDTBPSIZE - Software AG Editor Buffer Pool Size

This Natural profile parameter is used to set the size of the Software AG Editor buffer pool.

Possible settings	0 - 4000	Size of the Software AG Editor buffer pool in KB.
Default setting	400	
Dynamic specification	no	
Specification within session	no	

60

EDTLFILES - Number of Software AG Editor Logical Files

This Natural profile parameter is used to set the maximum number of the Software AG Editor sessions a user can open at a time.

Possible settings	10 - 999	Maximum number of Software AG Editor sessions.
Default setting	100	
Dynamic specification	no	
Specification within session	no	

61 EDTRB - Program Editor Ring Buffer

This Natural profile parameter can be used to determine whether the ring buffer of the program editor is to be used or not.

Possible settings	ON	Ring buffer is used.
	OFF	Ring buffer is not used.
Default setting	OFF	
Dynamic specification	no	
Specification within session	no	

For further information, see *Multiple Editor Sessions*.

62 EJ - Page Eject

This Natural profile and session parameter is used to specify whether a page eject is to be performed as a result of a logical page break, a break between program input and output, and the “normal end” message.

Possible settings	ON	A page eject is performed.		
	OFF	No page eject is performed. Note: This setting may be used to save paper during test runs where page ejects are not needed.		
Default setting	ON			
Dynamic specification	yes			
Specification within session	yes	Applicable statement:	SET GLOBALS	Parameter is evaluated at runtime.
		Applicable command:	GLOBALS	Parameter may be specified dynamically with the GLOBALS system command.
Application programming interface	USR1005N	See <i>SYSEXT - Natural Application Programming Interfaces</i> in the <i>Utilities</i> documentation.		



Notes:

1. Within a Natural session, the profile parameter EJ can be overridden by the session parameter EJ.
2. The EJ setting can in turn be overridden by an EJECT statement.
3. This parameter only applies to the first report (Report 0). For additional reports, the statement EJECT with report specification (*rep*) has to be used.

4. Under Natural Security, the setting of this parameter can be overridden by the Session Parameters option of the Library Profile.

63

EM - Edit Mask

- EM Parameter Syntax 138
- Examples 139
- Blanks in Edit Masks 139
- Default Edit Masks 139
- Edit Masks for Numeric Fields 140
- Edit Masks for Alphanumeric Fields 143
- Edit Masks for Binary Fields - Format B 145
- Hexadecimal Edit Masks 145
- Edit Masks for Date and Time Fields - Formats D and T 147
- Edit Masks for Logical Fields - Format L 151

With this session parameter, you can specify an edit mask for an input and/or output field that is used in one of the statements listed in the following table under *Applicable statements*.

Possible settings	See EM Parameter Syntax .	
Default setting	none	
Applicable statements	FORMAT	Parameter may be specified dynamically with the FORMAT statement.
	DEFINE DATA DISPLAY INPUT PRINT PROCESS PAGE/PROCESS PAGE UPDATE WRITE	Parameter may be specified at statement level and/or at element level.
	MOVE EDITED	Parameter may be specified at element level.
Applicable command	none	



Notes:

1. For information on Unicode edit masks, see session parameter [EMU](#).
2. The parameter EM can also be used with U format fields. For information on Unicode format, see *Unicode and Code Page Support in the Natural Programming Language, Session Parameters*, EMU, ICU, LCU, TCU versus EM, IC, LC, TC.
3. See also *Edit Masks - EM Parameter* in the *Programming Guide*.

The following topics are covered below:

EM Parameter Syntax

For input fields, values must be entered exactly matching the edit mask. If you would like to display the edit mask for an input field, the field should be defined as modifiable ([AD=M](#)).

For a database field, a default edit mask may have been defined in the DDM. If you specify with the EM parameter an edit mask for a database field, this edit mask specified will be used instead of any default edit mask which may be defined for the field in the DDM.

If you specify EM=OFF for a field, no edit mask will be used for the field, not even one that may be defined in the DDM.

At statement level of a DISPLAY, FORMAT, INPUT or WRITE statement, no detail field edit mask may be specified, except EM=OFF.

An edit mask overrides any settings for the session parameters [AL](#), [NL](#) and [SG](#).

The characters 9, H, X and Z represent significant print positions in numeric (9, Z), hexadecimal (H), and alphanumeric (X) edit masks. For the difference between 9 and Z, see [Edit Masks for Numeric Fields](#), below.

Examples

```
DISPLAY AA(EM=OFF) AB(EM=XX.XX)
WRITE SALARY (EM=ZZZ,ZZ9)
```

You may replace a sequence of the same significant characters with a numeric notation, such as x(8) for xxxxxxxx. The following examples demonstrate the abbreviated notation which may be used for the significant characters of numeric (Z, 9), hexadecimal (H), alphanumeric (X) and date (N, L) edit masks:

```
EM=9(4)-9(5)      is equivalent to: EM=9999-99999
EM=H(10)          is equivalent to: EM=HHHHHHHHHHH
EM=X(6)..X(3)     is equivalent to: EM=XXXXXX..XXX
EM=YYYY-L(8)-DD-N(8) is equivalent to: EM=YYYY-LLLLLLLLL-DD-NNNNNNNN
```

Blanks in Edit Masks

Blanks behind the equal sign (=) of the EM parameter are not allowed (for example: EM=<blank>XXX).

Blanks within an edit mask are represented by the character on your keyboard that in hexadecimal code corresponds to H'20' (ASCII) or H'5F' (EBCDIC), that is, the character ^ (or ¬).

Default Edit Masks

If no edit mask is specified for a field, a default edit mask is assigned to the field depending on the field format:

Field Format	Default Edit Mask
A	X
B	H
N, P, I	Z9
F	scientific representation
D	depends on default date format (as set with the profile parameter DTFORM)
T	HH:II:SS

Field Format	Default Edit Mask
L	blank / X

Edit Masks for Numeric Fields

An edit mask specified for a field of format N, P, I, or F must contain at least one 9 or Z.

If more 9s or Zs exist than the number of positions contained in the field value, the number of print positions in the edit mask will be adjusted to the number of digits defined for the field value.

If fewer 9s or Zs exist, the high-order digits before the decimal separator and/or low-order digits after the decimal separator will be truncated.

The following topics are covered below:

- [Characters for the Definition of Numeric Edit Masks](#)
- [Sign Characters](#)
- [Literal Leading Characters](#)
- [Literal Insertion and Trailing Characters](#)
- [Trailing Sign Characters](#)
- [Examples of Numeric Edit Masks](#)

Characters for the Definition of Numeric Edit Masks

Character	Function
9	Position to be displayed (one digit of the field value).
. (period)	The first period inserted is used as a decimal separator. Subsequent periods are treated as literal characters. Note: At this point, the period represents the sign currently defined as decimal separator character. If another character is chosen (for example, a comma) with the session or profile parameter DC , this character is to be used instead.
Z	Zero suppression for leading zeros. This is the default for numeric fields. The letter Z may be repeatedly specified to represent floating zero suppression. Z must not be specified to the right of the decimal separator character. A zero value may be displayed as blanks using all Zs in the edit mask (see also session parameter ZP).

The 9s or Zs can be preceded by one or more other characters.

Sign Characters

If the first character before the 9s or Zs is +, -, S or N, a sign may be displayed:

Character	Function
+	A floating sign is to be displayed preceding (leading sign character) or following (trailing sign character) the number. The sign may be generated as a plus or minus depending on the value of the field.
-	A floating minus is to be displayed preceding (leading sign character) or following (trailing sign character) the number if the value of the field is negative.
S	A sign is to be displayed to the left of the column. A plus sign is displayed for a positive value and a minus sign is displayed for a negative value.
N	A minus sign is to be displayed to the left of the column if the value of the field is negative.

Literal Leading Characters

Any number of literal leading characters can appear before the first displayable position (as indicated by Z or 9). These must follow any sign character. If there is no sign character and the first literal leading character is +, -, S or N, it must be enclosed in apostrophes. If a literal leading character is H, X, Z or 9, it must be enclosed in apostrophes.

The first literal leading character specified will appear in the output only if the value contains leading zeros and the edit mask is defined with Z (leading zero suppression). This character will then be used as a filler character displayed instead of a blank for leading zeros. Subsequent literal leading characters will be displayed as they are input.

Literal Insertion and Trailing Characters

Literal insertion and trailing characters can also be used. The symbol (^) can be used to represent a leading, inserted, or trailing blank. By enclosing significant characters (9, H, Z, X) in apostrophes, it is possible to use any characters as leading, insertion, or trailing characters. Insignificant edit mask characters need not be enclosed in apostrophes. Within the same edit mask notation, it is possible to have groups of leading, insertion, and/or trailing character strings, some of which are bounded by apostrophes and some of which are not.

Trailing Sign Characters

A trailing sign character can be specified for numeric edit masks by using the + or - character as the last character in the edit mask. A + will produce a trailing + or - sign depending on the value of the field. A - will produce a trailing space or - sign depending on the value of the field. If a leading and trailing sign are specified in the edit mask, both will be produced.

Examples of Numeric Edit Masks

The table below lists the results obtained from the original values shown at the top of each column as they are output without editing mask. All values used as column headings represent format N fields. The lines below the top column represent the formats obtained using the different editing masks:

Value	0000.03 (N4.2)	-0054 (N4)	+0087 (N4)	0962 (N4)	1830 (N4)
Edit Mask					
EM=9.9	0.0	4.	7.	2.	0.
EM=99	00	54	87	62	30
EM=S99	+00	-54	+87	+62	+30
EM=+Z9	+0	-54	+87	+62	+30
EM=-9.99	0.03	-4.	7.	2.	0.
EM=N9	0	-4	7	2	0
EM=*9.99	0.03	4.	7.	2.	0.
EM=Z99	00	54	87	962	830
EM=*EURZZ9.9	EUR**0.0	EUR*54.	EUR*87.	EUR962.	EUR830.
EM=999+	000+	054-	087+	962+	830+
EM=999-	000	054-	087	962	830
IC=\$ EM=ZZZ.99	\$.03	\$54.	\$87.	\$962.	\$830.
EM=H(6)					
- ASCII:	303030303033	30303574	30303837	30393632	31383330
- EBCDIC:	F0F0F0F0F0F3	F0F0F5D4	F0F0F8F7	F0F9F6F2	F1F8F3F0

By combining edit masks with the parameters IC and TC, negative numbers can be displayed in varying formats using a DISPLAY statement.

Edit Masks for Alphanumeric Fields

An alphanumeric edit mask which is only to be used with A format fields must contain at least one X which represents a character to be displayed. An H as the first character designates a **hexadecimal edit mask**. A blank is represented by a (^) symbol. All other characters except closing parentheses are permissible including leading, trailing, and insertion characters. It is also possible to specify leading, insertion, or trailing characters enclosed within apostrophes. If the character X, a closing parenthesis, or a quotation mark is specified as an insertion character, it must be enclosed within apostrophes.

If leading characters are used before the first displayable position X of an alphanumeric edit mask, the first of these leading characters will not be displayed, but is used as filler character and replaces all leading blanks in the alphanumeric output field.

Example:

```
DEFINE DATA LOCAL
1 #X (A4) INIT <' 34'>
END-DEFINE
WRITE #X (EM=*A:X:)
      6X #X (EM=*A:XX:)
      6X #X (EM=*A:XXX:)
      6X #X (EM=*A:XXXX:)
      6X #X (EM=1234XXXX5678)
END
```

Output Produced:

```
A:*:      A:**:      A:**3:      A:**34:      23411345678
```

Trailing characters which immediately follow the last permissible print position will be displayed.

If the number of positions specified with the mask is smaller than the field length, the overhanging field content is not displayed.

If the number of positions specified with the mask is higher than the field length, the mask is truncated on the first overhanging position.

Example:

```

DEFINE DATA LOCAL
  1 #TEXT (A4) INIT <'BLUE'>
END-DEFINE
WRITE #TEXT (EM=X-X-X)           displays as 'B-L-U'           .. only three bytes of field ←
WRITE #TEXT (EM=X-X-X-X-X)     displayed
                                displays as 'B-L-U-E-'           .. mask definition was ←
                                truncated to (EM=X-X-X-X-)

```

Example of Alphanumeric Edit Masks

The following program lists the alphanumeric edit masks for a field that is defined with format/length A4 and contains the value BLUE.

```

** Example 'EMMASK1': Edit mask
*****
DEFINE DATA LOCAL
  1 #TEXT (A4)
END-DEFINE
*
ASSIGN #TEXT = 'BLUE'
WRITE NOTITLE 'MASK 1:' 5X #TEXT (EM=X.X.X.X)
/             'MASK 2:' 5X #TEXT (EM=X^X^X^X)
/             'MASK 3:' 5X #TEXT (EM=X--X--X)
/             'MASK 4:' 5X #TEXT (EM=X-X-X-X-X-X)
/             'MASK 5:' 5X #TEXT (EM=X' 'X' 'X' 'X)
/             'MASK 6:' 5X #TEXT (EM=XX...XXX)
/             'MASK 7:' 5X #TEXT (EM=1234XXXX)
END

```

Output of Program EMMASK1:

```

MASK 1:      B.L.U.E
MASK 2:      B L U E
MASK 3:      B--L--U
MASK 4:      B-L-U-E-
MASK 5:      B L U E
MASK 6:      BL...UE
MASK 7:      234BLUE

```

Edit Masks for Binary Fields - Format B

Edit masks for binary fields may be set using X or H notation. For binary fields, the X notation is supported as if H had been specified instead of X.

Hexadecimal Edit Masks

If the character H is specified as the first character in an edit mask, the content of an alphanumeric or numeric field will be displayed in hexadecimal format. Each H represents two print positions that will occur for each byte in the source field. Characters other than H serve as insertion or trailing characters in the mask. The number of positions to be displayed will be adjusted to the length of the edit mask if the mask is shorter than the field. The length of the edit mask will be adjusted to the length of the field if the field length is shorter than the edit mask.

Insertion or trailing characters may be optionally specified bounded by apostrophes.

All fields displayed with a hexadecimal edit mask are treated as alphanumeric. Therefore, if the edit mask is shorter than the field to be edited, numeric or alphanumeric positions will be displayed from left to right disregarding any decimal separator positions.

If a hexadecimal edit mask is used as an input edit mask, every 0-9, a-f, A-F, blank and hex zero are accepted as a hex digit.



Note: Blank and hex zero are regarded as 0 and a lower-case letter (a-f) is regarded as an upper-case letter.

Edit Mask Examples for Hexadecimal Fields:

The tables below list the hexadecimal edit masks with results obtained from the original fields and values shown above each column. All numeric values (-10, +10, 01) to which edit masks have been applied originated in fields defined with N2 format. The alphanumeric value AB originated from a field defined with format/length A2.

ASCII:

Value =>	AB	-10	+10	01
EM=HH	4142	3170	3130	3031
EM=H^H	41 42	31 70	31 30	30 31
EM=HH^H	4142	3170	3130	3031
EM=H-H	41-42	31-70	31-30	30-31
EM=H	41	31	31	30

EBCDIC:

Value =>	AB	-10	+10	01
EM=HH	C1C2	F1D0	F1F0	F0F1
EM=H:H	C1 C2	F1 D0	F1 F0	F0 F1
EM=HH:H	C1C2	F1D0	F1F0	F0F1
EM=H-H	C1-C2	F1-D0	F1-F0	F0-F1
EM=H	C1	F1	F1	F0

Example Program Using Hexadecimal Edit Masks:

```

** Example 'EMMASK2': Edit mask
*****
DEFINE DATA LOCAL
1 #TEXT1 (A2)
1 #TEXT2 (N2)
END-DEFINE
*
ASSIGN #TEXT1 = 'AB'
    
```

```

ASSIGN #TEXT2 = 10
*
WRITE NOTITLE
    'MASK (EM=HH) : ' 18T #TEXT1 (EM=HH)      30T #TEXT2 (EM=HH)
  / 'MASK (EM=H^H) : ' 18T #TEXT1 (EM=H^H)    30T #TEXT2 (EM=H^H)
  / 'MASK (EM=HH^H) : ' 18T #TEXT1 (EM=HH^H)  30T #TEXT2 (EM=HH^H)
  / 'MASK (EM=H-H) : ' 18T #TEXT1 (EM=H-H)    30T #TEXT2 (EM=H-H)
  / 'MASK (EM=H)   : ' 18T #TEXT1 (EM=H)      30T #TEXT2 (EM=H)
END

```

Output of Program EMMASK2 (ASCII):

```

MASK (EM=HH) : 4142      3130
MASK (EM=H^H) : 41 42    31 30
MASK (EM=HH^H) : 4142    3130
MASK (EM=H-H) : 41-42    31-30
MASK (EM=H)   : 41       31

```

Output of Program EMMASK2 (EBCDIC):

```

MASK (EM=HH) : C1C2      F1F0
MASK (EM=H^H) : C1 C2    F1 F0
MASK (EM=HH^H) : C1C2    F1F0
MASK (EM=H-H) : C1-C2    F1-F0
MASK (EM=H)   : C1       F1

```

Edit Masks for Date and Time Fields - Formats D and T

In edit masks for fields which are defined with format D (date) or T (time), the characters described in the following sections can be specified.

- [Date - Format D, and Time - Format T](#)
- [Syntactical Restrictions for Date Characters](#)
- [Hints for Input Edit Mask](#)
- [Hints for Week Display \(WW or ZW\) in Output Edit Mask](#)
- [Time - Format T - only](#)

- Examples of Date and Time Edit Masks

Date - Format D, and Time - Format T

Character	Usage
DD	Day.
ZD	Day, with zero suppression.
MM	Month.
ZM	Month, with zero suppression.
YYYY	Year, 4 digits (see the section Hints for Input Edit Mask).
YY	Year, 2 digits (see the section Hints for Input Edit Mask).
Y	Year, 1 digit. Must not be used for input fields.
WW	Number of week (see the sections Hints for Input Edit Mask and Hints for Week Display in Output Edit Mask).
ZW	Number of week, with zero suppression (see the sections Hints for Input Edit Mask and Hints for Week Display in Output Edit Mask).
JJJ	Julian day.
ZZJ	Julian day with zero suppression.
NN . . . or N(<i>n</i>)	Name of day (language-dependent). The maximum length is determined by the number of Ns or by <i>n</i> . If the name is longer than the maximum length, it will be truncated; if it is shorter, the actual length of the name will be used.
0	Number of week day. The profile parameter <code>DTFORM</code> determines whether Monday or Sunday is considered the first day of the week. With <code>DTFORM=U</code> : (Sunday = 1, Monday = 2, etc.). With <code>DTFORM=other</code> : (Monday = 1, Tuesday = 2, etc.).
LL . . . or L(<i>n</i>)	Name of month (language-dependent). The maximum length is determined by the number of L characters or by <i>n</i> . If the name is longer than the maximum length, it will be truncated; if it is shorter, the actual length of the name will be used.
R	Year in Roman numerals (maximum 13 digits). Must not be used for input fields.

Syntactical Restrictions for Date Characters

For *Input* and *Output* edit masks, you *may not* use the following:

text			characters		
month	with	month name	MM or ZM	with	LL or L(<i>n</i>)
day name	with	week day number	NN or N(<i>n</i>)	with	0

For *Input* edit masks, you *may not* use the following:

text			characters		
1-digit year	nor	a year in Roman numerals	Y	nor	R
Day	without	month or month name	DD or ZD	without	MM or ZM or LL or L(<i>n</i>)
Week	without	year	WW or ZW	without	YYYY or YY
Month	without	year	MM or ZM	without	YYYY or YY
Julian day	without	year	JJJ or ZZJ	without	YYYY or YY
Day name	without	week	NN or N(<i>n</i>)	without	WW or ZW
Week day number	without	week	0	without	WW or ZW
Julian day	with	month	JJJ or ZZJ	with	MM or ZM
Julian day	with	week	JJJ or ZZJ	with	WW or ZW
Month	with	week	MM or ZM	with	WW or ZW

Hints for Input Edit Mask

The range of valid year values (YYYY) is 1582 - 2699.

If only year (YY or YYYY) but no month or day is specified within an input edit mask, the values for month and day will both be set to 01. If only year (YY or YYYY) and month (MM) but no day is specified within an input edit mask, the value for day will be set to 01.

If a 2-digits year (YY) is used, the century used to fill up the year representation is the current century by default. However, this does not apply when a Sliding or Fixed Window is set. For more details, please refer to profile parameter [YSLW](#) in the Natural Parameter Reference documentation.

If a week number (WW or ZW) but no number of week day (0) or name of day (NN . . .) is specified, the first day of the week is assumed.

Hints for Week Display (WW or ZW) in Output Edit Mask

When `DTFORM=U` (USA format) is set, the week starts on Sunday; whereas for all other `DTFORM` settings the first weekday is Monday. Whether a week is week 52/53 of the old year or week 01 of the new year depends on which year contains more days of the week. In other words, if Thursday (Wednesday for `DTFORM=U`) of that week is in the previous year, the week belongs to the previous year; if it is in the next year, the week belongs to the next year.

If the number of week (WW or ZW) and a year representation (YYYY or YY or Y) is in the same edit mask, the display for year always corresponds to the week number, regardless of the year in the underlying date field.

Example:

```
DEFINE DATA LOCAL
1 D (D)
END-DEFINE
MOVE EDITED '31-12-2003' TO D(EM=DD-MM-YYYY)
DISPLAY D(EM=DD-MM-YYYY_N(10)) D(EM=DD-MM-YYYY/WW)
```

Although the underlying date is the 31 Dec. 2003, when the week number WW is contained in the edit mask, it displays as:

```
-----D-----D-----
31-12-2003_Wednesday 31-12-2004/01
```

Time - Format T - only

Character	Usage
T	Tenths of a second.
SS	Seconds.
ZS	Seconds, with zero suppression.
II	Minutes.
ZI	Minutes, with zero suppression.
HH	Hours.
ZH	Hours, with zero suppression.
AP	AM/PM element.

Examples of Date and Time Edit Masks

```
** Example 'EMDATI': Edit mask for date and time variables
*****
*
WRITE NOTITLE
' DATE INTERNAL :' *DATX (DF=L) /
'           :' *DATX (EM=N(9)' 'ZW.'WEEK 'YYYY) /
'           :' *DATX (EM=ZZJ'.DAY 'YYYY) /
'   ROMAN      :' *DATX (EM=R) /
'   AMERICAN   :' *DATX (EM=MM/DD/YYYY)      12X 'OR ' *DAT4U /
'   JULIAN     :' *DATX (EM=YYYYJJJ)        15X 'OR ' *DAT4J /
'   GREGORIAN  :' *DATX (EM=ZD.' 'L(10)''YYYY) 5X 'OR ' *DATG ///
```



```

*
' TIME INTERNAL : ' *TIMX                14X 'OR ' *TIME /
'               : ' *TIMX (EM=HH.II.SS.T) /
'               : ' *TIMX (EM=HH.II.SS' 'AP) /
'               : ' *TIMX (EM=HH)
END

```

Output of Program EMDATI:

```

DATE INTERNAL : 2005-01-12
               : Wednesday 2.WEEK 2005
               : 12.DAY 2005
  ROMAN       : MMV
  AMERICAN    : 01/12/2005          OR   01/12/2005
  JULIAN      : 2005012             OR   2005012
  GREGORIAN   : 12.January2005     OR   12January 2005

TIME INTERNAL : 16:04:14           OR   16:04:14.8
               : 16.04.14.8
               : 04.04.14 PM
               : 16

```

Edit Masks for Logical Fields - Format L

For fields of format L (logical fields), edit masks can be defined as follows:

```
(EM=[false-string]/true-string)
```

The *false-string* must not be longer than 31 characters.

Example of Edit Masks for Logical Field

```

** Example 'EMLOGV': Edit mask for logical variables
*****
DEFINE DATA LOCAL
1 #SWITCH (L)  INIT <true>
1 #INDEX  (I1)
END-DEFINE
*
FOR #INDEX 1 5
  WRITE NOTITLE #SWITCH (EM=FALSE/TRUE) 5X 'INDEX =' #INDEX
  WRITE NOTITLE #SWITCH (EM=OFF/ON)      7X 'INDEX =' #INDEX
  IF #SWITCH
    MOVE FALSE TO #SWITCH

```

```
ELSE
  MOVE TRUE TO #SWITCH
END-IF
/*
SKIP 1
END-FOR
END
```

Output of Program EMLOGV:

```
TRUE      INDEX = 1
ON        INDEX = 1

FALSE     INDEX = 2
OFF       INDEX = 2

TRUE      INDEX = 3
ON        INDEX = 3

FALSE     INDEX = 4
OFF       INDEX = 4

TRUE      INDEX = 5
ON        INDEX = 5
```

64

EMFM - Edit Mask Free Mode

This Natural profile parameter is used to activate/deactivate the Edit Mask Free mode at session startup.

Possible settings	ON	Edit Mask Free Mode is activated.
	OFF	Edit Mask Free Mode is deactivated.
Default setting	OFF	
Dynamic specification	yes	
Specification within session	no	Within a running Natural session, you may override this setting with the terminal control command %FM+ or %FM-.



Notes:

1. The Edit Mask Free mode allows you to omit literals during input into a field with a numeric edit mask.
2. For additional information, see *Numeric Edit Mask Free Mode* in the INPUT statement description in the *Statements* documentation.

65

EMU - Unicode Edit Mask

With this session parameter, you can specify a Unicode edit mask for an input and/or output field that is used in one of the statements listed in the following table under *Applicable statements*.

Possible settings	The syntax of the session parameter EMU is identical to that of the session parameter EM (see <i>EM Parameter Syntax</i>). Note: See also <i>Unicode Edit Masks - EMU Parameter</i> in the <i>Programming Guide</i> .	
Default setting	none	
Applicable statements	DEFINE DATA DISPLAY INPUT PRINT WRITE MOVE EDITED PROCESS PAGE	Parameter may be specified at statement level and/or at element level.
Applicable command	none	



Notes:

1. Edit masks which are defined with EMU are kept in Unicode format so that the content is independent of the installed system code page.
2. For further information and an example, see also *Unicode and Code Page Support in the Natural Programming Language, Session Parameters*, section EMU, ICU, LCU, TCU versus EM, IC, LC, TC.

66

ENDIAN - Endian Mode for Compiled Objects

This Natural profile and session parameter specifies the architecture for which the compiler should generate GP. See also *Portable Natural Generated Programs* in the *Programming Guide*.

Possible settings	DEFAULT	Endian mode is derived from the architecture currently used.
	LITTLE	The compiler generates GP for Little Endian mode.
	BIG	The compiler generates GP for Big Endian mode.
Default setting	DEFAULT	
Dynamic specification	yes	
Specification within session	yes	
Applicable statements	none	
Applicable command	GLOBALS	



Note: Within a Natural session, the profile parameter settings can be overwritten by the session parameter ENDIAN.

67

ENDMSG - Display Session-End Message

This Natural profile parameter is used to suppress the display the default message NAT9995 that is displayed at the end of the Natural session to indicate that the Natural session has been ended normally.

Possible settings	ON	Message NAT9995, NAT9978 or NAT9987 is written to the batch output file CMPRINT at the end of the session.
	OFF	Message NAT9995, NAT9978 or NAT9987 does not appear in CMPRINT .
Default setting	ON	
Dynamic specification	yes	
Specification within session	no	



Notes:

1. If Natural terminates with a startup error, then Natural message NAT9987 will be used instead of NAT9995.
2. If Natural terminates with a runtime error, then Natural message NAT9978 will be used instead of NAT9995.

68 ES - Empty Line Suppression

With this session parameter, you can suppress the printing of empty lines generated by a DISPLAY or WRITE statement.

Possible settings	ON	A line resulting from a DISPLAY or WRITE statement which contains all blank values will not be printed. Note: This setting is particularly useful when displaying arrays (for example, multiple-value fields or fields contained within a periodic group) to avoid printing a large number of empty lines.
	OFF	Empty line suppression is disabled.
Default setting	OFF	
Specification within session	yes	
Applicable statements	FORMAT	
	DISPLAY WRITE	Parameter may be specified at statement level and/or at element level.
Applicable command	none	



Notes:

1. To achieve empty suppression for numeric values, the field must be specified with ZP=OFF and ES=ON in order to have null values printed as blanks. See also the session parameters IS and ZP.
2. See also *Parameters to Influence the Output of Fields* in the *Programming Guide*.

Example:

```
DISPLAY (ES=ON) NAME CITY
```

69

ESCAPE - Ignore Terminal Commands %% and %.

This Natural profile parameter can be used to disable the terminal commands %% and %..

Possible settings	ON	Enables the use of terminal commands %% and %..
	OFF	The terminal commands %% and %.. will be ignored; that is, it will not be possible to leave the currently active Natural program or the Natural session respectively by entering %% or %..
Default setting	ON	
Dynamic specification	yes	
Specification within session	no	

70

ESXDB - Database ID Used for Entire System Server DDMs

This Natural profile parameter specifies the database ID used for Entire System Server's DDMs.

Possible settings	1 - 254	Database ID. To activate this parameter, a database ID in the range of 1 to 254 must be specified.
	0	With ESXDB=0, the Entire System Server Interface is not active.
Default setting	0	
Dynamic specification	no	
Specification within session	no	



Notes:

1. This Natural profile parameter applies to the Entire System Server Interface.
2. Entire System Server's DDMs are cataloged with DBID=148. If you are using an Adabas database with this DBID, specify a different number for ESXDB. For information on how to do this, please refer to *Setting up the Entire System Server Interface* in the *Operations* documentation.

71 ET - Execution of END/BACKOUT TRANSACTION

Statements

This Natural profile parameter specifies for which databases END TRANSACTION and BACKOUT TRANSACTION statements are to be executed.

Possible settings	ON	END TRANSACTION and BACKOUT TRANSACTION statements are executed for all databases which have been referenced since the beginning of the Natural session or since the last execution of an END TRANSACTION and BACKOUT TRANSACTION statement.
	OFF	END TRANSACTION and BACKOUT TRANSACTION statements are executed only for the databases affected by the transaction (and - if applicable - for the database to which transaction data are written).
Default setting	OFF	
Dynamic specification	yes	
Specification within session	no	



Note: Any updates to a database which are not executed under the control of Natural (that is, by native invocation of the database link routines) do not affect the Natural transaction logic.

72

ETA - Error Transaction Program

This Natural profile parameter provides the name of the program which receives control if an error condition is detected during Natural program execution.

Possible settings	1 to 8 characters	Program name for error transaction.
	' ' (blank)	With ETA=' ', no error transaction program is called.
Default setting	' ' (blank)	
Dynamic specification	yes	
Specification within session	yes	
Application programming interface	USR1041N	USR1041N is a sample error transaction program delivered in source form. See <i>SYSEXT - Natural Application Programming Interfaces</i> in the <i>Utilities</i> documentation.



Notes:

1. The setting of this parameter can be modified by a user program by way of assignment to the system variable *ERROR-TA or, if Natural Security is installed, within the Natural Security library profile; see *Components of a Library Profile* in the *Natural Security* documentation.
2. For further information, see *Using an Error Transaction Program* in the *Programming Guide*.

73

ETDB - Database for Transaction Data

This Natural profile parameter specifies the database in which transaction data, as supplied with an `END TRANSACTION` statement is to be stored.

Possible settings	1 - 65535, except 255	Database ID. Note: Database ID 255 is reserved for logical system files for Software AG products, see profile parameter LFILE .
	0	The transaction data is written to the database specified with the profile parameter UDB .
Default setting	0	
Dynamic specification	yes	
Specification within session	no	

Other transaction processing related parameters: [ET](#) | [ETEOP](#)

74

ETEOP - Issue END TRANSACTION at End of Program

This Natural profile parameter determines whether or not an implicit END TRANSACTION statement is to be issued at the end of a Natural program (that is, before NEXT mode is reached).

Possible settings	ON	Natural will issue an implicit END TRANSACTION statement at the end of a Natural program.
	OFF	Natural will not issue any implicit END TRANSACTION statement at the end of a Natural program.
Default setting	OFF	
Dynamic specification	yes	
Specification within session	no	

75

ETID - Adabas User Identification

This Natural profile parameter is used as an identifier for Adabas-related information; for example, for identification of data stored as a result of an `END TRANSACTION` statement.

Possible settings	1 - 8 characters	This setting is used as the user ID setting in an Adabas open call. Note: The Adabas user ID has its own syntax. Please consult your <i>Adabas Command Reference</i> documentation if you want to use special characters for the setting of ETID.
	OFF	The ETID is set to ' ' (blanks), but Natural Security is allowed to set the ETID.
	' ' (blank)	The ETID is set to ' ' (blanks). This value is passed to Adabas on an open call without being modified by Natural Security.
	\$\$	The ETID is replaced by the process ID.
Default setting	' ' (blank)	
Dynamic specification	yes	
Specification within session	no	



Notes:

1. If the ETID is not specified neither in NATPARM nor dynamically, Natural uses the setting of *INIT-USER to fill the ETID.
2. The ETID might also be used by Natural for work-file name generation. This might cause problems when running multiple instances on one machine or again, if special characters are used for the setting of ETID. Please refer to the Natural parameter [TMPSORTUNIQ](#) for a solution.

76 ETPDB - Databases Containing Entire Transaction

Propagator Master Files

This Natural profile parameter specifies the databases that contain Entire Transaction Propagator master files.

Possible settings	1 - 255	Database IDs; for details, see the <i>Entire Transaction Propagator</i> documentation. Mark all databases in the parameter's database list that contain master files.
	0	Entire Transaction Propagator is not to be used.
	' ' (blank)	
Default setting	' ' (blank)	
Dynamic specification	no	
Specification within session	no	



Note: This Natural profile parameter only applies if Software AG's Entire Transaction Propagator is installed.

77

ETPSIZE - Size of Entire Transaction Propagator Buffer

This Natural profile parameter determines the size of the Entire Transaction Propagator buffer.

Possible settings	10 - 63	Size of the Entire Transaction Propagator buffer in KB. Note: 1. If Entire Transaction Propagator is to be used, an appropriate value has to be specified for this parameter; see the <i>Entire Transaction Propagator</i> documentation. 2. If the requested space is not available, the Entire Transaction Propagator cannot be used.
	0	Entire Transaction Propagator is not used.
Default setting	0	
Dynamic specification	no	
Specification within session	no	



Note: This Natural profile parameter only applies if Entire Transaction Propagator is installed.

78

FC - Filler Character for INPUT Statement

This Natural profile parameter is used to specify the default filler character to be used for fields displayed by an `INPUT` statement.

Possible settings	any character	Default filler character.
Default setting	blank	
Dynamic specification	yes	
Specification within session	no	



Notes:

1. The default filler character is used to pre-fill fields non-protected input fields (field attribute specification `AD=A`) when fields are written to a terminal by an `INPUT` statement.
2. For modifiable input fields (field attribute specification `AD=M`), it is used to fill the rest of the field.

79

FC - Filler Character for DISPLAY Statement

With this session parameter, you specify the filler character which will appear on either side of a heading produced by a `DISPLAY` statement across the full column width.

Possible settings	any character	Filler character for individual headings.
Default setting	blank	
Specification within session	yes	
Applicable statements	DISPLAY FORMAT	
Applicable command	none	



Notes:

1. FC only applies if the column width is determined by the field length and not by the header (see also session parameter `HW`); otherwise the FC setting will be ignored.
2. Unlike the `GC` parameter, which applies to headings across a group of columns, the `FC` parameter applies to individual columns.

Example:

```
DISPLAY (FC=*)
```


80

FCDP - Filler Character for Dynamically Protected Input

Fields

This Natural profile and session parameter can be used to suppress the display of filler characters for input fields that have been made write-protected dynamically (that is, to which the attribute `AD=P` has been assigned via an attribute control variable).

Possible settings	ON	Dynamically protected input fields are displayed filled with filler characters. This may suggest to the users that they could enter something in the fields.
	OFF	Dynamically protected input fields are displayed filled with blanks.
Default setting	ON	
Dynamic specification	yes	
Specification within session	yes	
Applicable statements	SET GLOBALS	
Applicable command	GLOBALS	
Application programming interface	USR1005N	See <i>SYSEXT - Natural Application Programming Interfaces</i> in the <i>Utilities</i> documentation.



Notes:

1. Depending on the setting of the `FCDP` parameter, dynamically protected input fields are displayed filled either with blanks or with the defined filler characters.
2. Within a Natural session, the profile parameter `FCDP` can be overridden by the session parameter `FCDP`.

Example:

```

DEFINE DATA LOCAL
1 #FIELD1 (A5)
1 #FIELD2 (A5)
1 #CVAR1 (C) INIT <(AD=P)>
1 #CVAR2 (C)
END-DEFINE
*
INPUT #FIELD1 (AD=Y'_' CV=#CVAR1) /* field is protected
      #FIELD2 (AD=Y'_' CV=#CVAR2) /* field is not protected
...
END

```

Execution of the above program will display the following:

FCDP=ON:

#FIELD1 _____ #FIELD2 _____

FCDP=OFF:

#FIELD1 #FIELD2 _____

81

FDDM - Natural System File for DDMs

This Natural profile parameter is used to specify five subparameters for the Natural system file for DDMs.

Possible settings	See <i>FDDM Parameter Syntax</i> .	
Default setting	none	
Dynamic specification	yes	
Specification within session	no	



Notes:

1. If this system file is defined, all DDMs are stored on the specified path. DDMs stored in libraries will no longer be accessible from Natural. This is similar to Natural on mainframes, where all DDMs are stored in the system file `FDIC`.
2. If the FDDM system file is undefined (*database-ID* and *file-number*=0), the DDMs are stored in the libraries as supplied before. The system file FDDM is displayed as an inactive environment.
3. For information on system files, refer to: System Files in the Natural Operations documentation.

FDDM Parameter Syntax

The parameter syntax is as follows:

```
FDDM=(database-ID,file-number,password,cipher-key,RO)
```

Where:

Syntax Element	Value	Explanation
<i>database-ID</i>	1 - 65535	Database identification of the database in which the Natural system file for DDMs is located. Note: Database ID 255 is reserved for logical system files for Software AG products, see Natural profile parameter LFILE .
<i>file-number</i>	1 - 5000	File number of the database file in which the Natural system file for DDMs is located.
<i>password</i>	1 - 8 characters	The password is only required if the Natural user-program system file has been password-protected using the Adabas security feature. Note: The password is reserved for future use; currently, it is ignored.
<i>cipher-key</i>	1 - 8 numeric characters	The cipher key is only required if the Natural user-program system file has been ciphered using the Adabas security feature. Note: The cipher key is reserved for future use; currently, it is ignored.
RO	-	Indicates that the Natural user-program system file is "read-only" and is only specified if modifications on the file are to be disabled.

Examples:

```
FDDM=(22,5)
FDDM=(22,5,,12345)
FDDM=(22,5,,,RO)
```

82

FDIC - Predict System File

This Natural profile parameter defines the database ID, file number, password and cipher key for the Predict system file (FDIC), which Predict uses to retrieve and/or store data.

Possible settings	See <i>FDIC Parameter Syntax</i> .	
Default setting	none	
Dynamic specification	yes	
Specification within session	no	



Notes:

1. In a remote development environment, a Development Server File is used instead, see the *SPoD - Natural's Single Point of Development* and the *Natural Development Server* documentation.
2. For information on system files, refer to *System Files* in the *Operations* documentation.

FDIC Parameter Syntax

The parameter syntax is as follows:

```
FDIC=(database-ID,file-number,password,cipher-key,RO)
```

Where:

Syntax Element	Value	Explanation
<i>database-ID</i>	1 - 65535, except 255	Database identification of the database in which the Predict system file is located. Note: 1. Database ID 255 is reserved for logical system files for Software AG products, see Natural profile parameter LFILE .

Syntax Element	Value	Explanation
		2. If no FDIC is available, do not enter anything in the DBID field.
<i>file-number</i>	1 - 5000	File number of the database file in which the Predict system file is located. Note: If no FDIC is available, do not enter anything in the DBID field.
<i>password</i>	1 - 8 characters	Password for the Predict system file. Note: 1. A password is only required if the Predict system file has been password-protected using the Adabas security feature. 2. The password feature is reserved for future use; currently, it is ignored.
<i>cipher-key</i>	1 - 8 numeric characters	Cipher key for the Predict system file. Note: 1. A cipher key is only required if the Predict system file has been ciphered using the Adabas security feature. 2. The cipher key feature is reserved for future use; currently, it is ignored.
RO	-	Read only option - not supported on this platform.

Examples:

```
FDIC=(10,5,PASSW1,12345678)
FDIC=(1,200,,12345678)
FDIC=(1,5)
FDIC=(,5)
```


83

FL - Floating Point Mantissa Length

With this session parameter, you specify the mantissa length of a floating point variable during input or output.

Possible settings	1 - 16	Mantissa length. Note: The total length is FL + 6 for sign, exponent, and decimal character.
Default setting	none	
Specification within session	yes	
Applicable statements	DISPLAY FORMAT INPUT PRINT WRITE	
Applicable command	none	

Example:

```
DISPLAY FL=5 -> +1.2345E+03
```


84

FNAT - Natural System File for System Programs

This Natural profile parameter defines the database ID, file number, password, cipher key and read-only flag for the Natural system file for Natural system programs (FNAT).

Possible settings	See <i>FNAT Parameter Syntax</i> .	
Default setting	none	
Dynamic specification	yes	
Specification within session	no	



Notes:

1. The Natural system file is the file from which all Natural system programs are retrieved and upon which all system commands operate. Error texts and Natural help information related to the Natural system libraries are also contained in this system file.
2. For information on system files, refer to *System Files* in the *Operations* documentation.

FNAT Parameter Syntax

The parameter syntax is as follows:

```
FNAT=(database-ID,file-number,password,cipher-key,RO)
```

Where:

Syntax Element	Value	Explanation
<i>database-ID</i>	1 - 254	Database identification of the database in which the Natural system file is located. Note: Database ID 255 is reserved for logical system files for Software AG products, see Natural profile parameter LFILE .
<i>file-number</i>	1 - 255	File number of the database file in which the Natural system file is located.
<i>password</i>	1 - 8 characters	Password for the Natural system file. Note: 1. A password is only required if the Natural system file has been password-protected using the Adabas security feature. 2. The password feature is reserved for future use; currently, it is ignored.
<i>cipher-key</i>	1 - 8 numeric characters	Cipher key for the Natural system file. Note: 1. A cipher key is only required if the Natural system file has been ciphered using the Adabas security feature. 2. The cipher key feature is reserved for future use; currently, it is ignored.
RO	-	Read-only option. Note: 1. RO indicates that the Natural system file is “read-only”. 2. RO is only specified if modifications on the file are to be disabled.

Examples:

```
FNAT=( ,102)
FNAT=(99,102,, ,RO)
FNAT=(99,102,PASSW2)
```

85

FREEGDA - Release GDA in Utility Mode

This Natural profile parameter controls whether current user global data area (GDA) and application-independent variables (AIV) are to be reset or not when a utility is invoked in utility mode (see *Utility Activation* in the *Utilities* documentation), that is, by using the direct command that corresponds to the utility's name.

Possible settings	ON	The current user GDA and AIV variables are reset before a utility is started. Note: This behavior corresponds to the previous situation when the utility was invoked using the system command <code>LOGON library-name</code> .
	OFF	The current user GDA and AIV variables are preserved when a utility is started. Note: This will increase the data size correspondingly and may lead to thread problems under certain operating systems.
Default setting	ON	
Dynamic specification	yes	
Specification within session	no	

86

FS - Default Format/Length Setting for User-Defined

Variables

This Natural profile and session parameter determines whether a default format/length setting is to be in effect for the definition of user-defined variables in reporting mode.



Note: See also *Format and Length of User-Defined Variables* in the *Programming Guide*.

Possible settings	ON	No default format/length is assigned by Natural for a newly introduced variable in reporting mode. Note: The format/length of all user-defined variables must be explicitly specified.
	OFF	A user-defined variable in a Natural program for which no format/length is specified is assigned the default format/length N7.
Default setting	OFF	
Dynamic specification	yes	
Specification within session	yes	
Applicable statements	SET GLOBALS	
Applicable command	GLOBALS	
Application programming interface	USR1005N	See <i>SYSEXT - Natural Application Programming Interfaces</i> in the <i>Utilities</i> documentation.



Notes:

1. This Natural profile and session parameter only applies to reporting mode; it has no effect in structured mode.
2. Within a Natural session, the profile parameter FS can be overridden by the session parameter FS.

3. Under Natural Security, the setting of this parameter can be overridden by the Session Parameters option of the Library Profile.

87

FSEC - Natural Security System File

This Natural profile parameter defines the database ID, file number, password, and cipher key for the Natural Security system file (FSEC), which is used by Natural Security to retrieve/store its security information.

Possible settings	See FSEC Parameter Syntax .	
Default setting	none	
Dynamic specification	yes	
Specification within session	no	



Notes:

1. This Natural profile parameter only applies if Natural Security is used.
2. For information on system files, refer to *System Files* in the *Operations* documentation.

FSEC Parameter Syntax

The FSEC parameter syntax is as follows:

```
FSEC=(database-ID,file-number,password,cipher-key,RO)
```

Where:

Syntax Element	Value	Explanation
<i>database-ID</i>	1-65535, except 255	Database identification of the database in which the Natural Security system file is located. Note: 1. Database ID 255 is reserved for logical system files for Software AG products, see Natural profile parameter LFILE .

Syntax Element	Value	Explanation
		2. If no FSEC system file is available, do not enter anything in the file number field.
<i>file-number</i>	1-5000	File number of the database file in which the Natural Security system file is located. Note: If no FSEC system file is available, do not enter anything in the file number field.
<i>password</i>	1 - 8 characters	Password for the Natural Security system file. Note: 1. A password is only required if the Natural Security system file has been password-protected using the Adabas security feature. 2. The password feature is reserved for future use; currently, it is ignored.
<i>cipher-key</i>	1 - 8 numeric characters	Cipher key for the Natural Security system file.
R0	-	Read-only option. Note: The R0 option is not supported on this platform.

Examples:

```
FSEC=(10,8)
FSEC=10,5,PASSW1,12345678
FSEC=1,200,,12345678
```

88

FUSER - Natural System File for User Programs

This Natural profile parameter defines the database ID, file number, password, and cipher key for the Natural user-program system file (FUSER).

Possible settings	See <i>FUSER Parameter Syntax</i> .	
Default setting	none	
Dynamic specification	yes	
Specification within session	no	



Notes:

1. The Natural user-program system file (FUSER) is the database file from which all user-written Natural programs are retrieved.
2. For information on system files, refer to: *System Files* in the *Operations* documentation.

FUSER Parameter Syntax

The FUSER parameter syntax is as follows:

```
FUSER=(database-ID,file-number,password,cipher-key,RO)
```

Where:

Syntax Element	Value	Explanation
<i>database-ID</i>	1-254	Database identification of the database in which the Natural user-program system file is located. Note: Database ID 255 is reserved for logical system files for Software AG products, see Natural profile parameter LFILE .

Syntax Element	Value	Explanation
<i>file-number</i>	1-255	File number of the database file in which the Natural user-program system file is located.
<i>password</i>	1 to 8 characters	<p>Password for the Natural user-program system file.</p> <p>Note:</p> <ol style="list-style-type: none"> 1. A password is only required if the Natural user-program system file has been password-protected using the Adabas security feature. 2. The password feature is reserved for future use; currently, it is ignored.
<i>cipher-key</i>	1 to 8 numeric characters	<p>Cipher key for the Natural user-program system file.</p> <p>Note:</p> <ol style="list-style-type: none"> 1. A cipher key is only required if the Natural user-program system file has been ciphered using the Adabas security feature. 2. The cipher key feature is reserved for future use; currently, it is ignored.
RO	-	<p>Read-only option.</p> <p>Note:</p> <ol style="list-style-type: none"> 1. RO indicates that the Natural user-program system file is “read-only”. 2. RO is only specified if modifications on the Natural user-program system file are to be disabled.

Examples:

```
FUSER=(22,5)
FUSER=(22,5,,RO)
FUSER=(22,5,PASSW2)
```

89

GC - Filler Character for Group Headers

With this session parameter, you specify the filler character which will appear on either side of a group heading produced by a `DISPLAY` statement across all field columns that belong to that group.

Possible settings	any character	Filler character for group headers.
Default setting	blank	
Specification within session	yes	
Applicable statements	DISPLAY FORMAT	
Applicable command	none	



Note: Unlike the `FC` parameter, which applies to individual columns, the `GC` parameter applies to headings across a group of columns.

Example:

```
DISPLAY (GC=*)
```


90

GFID - Global Format IDs

This Natural profile and session parameter is used to control Natural's internal generation of global format IDs so as to influence Adabas's performance concerning the re-usability of format buffer translations.

Possible settings	ON	Global format IDs are generated for all views.
	OFF	Global format IDs are not generated.
	VID	Global format IDs are generated only for views in local/global data areas, but not for views defined within programs.
Default setting	ON	
Dynamic specification	yes	
Specification within session	yes	
Applicable statements	OPTIONS	
Applicable Commands:	GFID option of COMPOPT.	



Note: For details on global format IDs, see the Adabas documentation.

91 HC - Header Centering

This session parameter determines the placement of column headers.

Possible settings	C	Headers will be centered.
	L	Headers will be left-justified.
	R	Headers will be right-justified.
Default setting	C	
Specification within session	yes	
Applicable statements	DISPLAY FORMAT	
Applicable command	none	

Example:

```
DISPLAY (HC=L)
```

92

HD - Header Definition

With this session parameter, you define which default text is to be used when

- the field is output with a `DISPLAY` statement;
- an equal sign (=) is placed immediately before the field in a `WRITE` or `INPUT` statement.

Possible settings	<code>'text'</code>	120 alphanumeric or Unicode characters at maximum.
Default setting	none	
Applicable statements	<code>DEFINE DATA</code>	Parameter may be specified at field level and/or element level.
Applicable command	none	

93

HE - Helproutine

- HE Parameter Syntax 212
- Execution of Helproutines 214
- Examples 214

With this session parameter, you assign a helproutine or a help map to a field.

Possible settings		See <i>HE Parameter Syntax</i> below.
Default setting	none	
Specification within session	yes	
Applicable statements	INPUT	
Applicable command	none	

Helproutines can be created with the Natural program editor, help maps with the Natural map editor.

The helproutine or help map may then be invoked during processing of an INPUT statement or a map by choosing either of the following methods:

- In the field for which to invoke the help request, enter the help character, that is, a question mark (?) by default, and press ENTER.

Or:

- Place the cursor in the field for which to invoke the help request and press the PF key defined as help function key with the SET KEY statement.

The following topics are covered below:

HE Parameter Syntax

The syntax of this parameter is:

$$HE=operand1 \left[, \left\{ \begin{array}{l} operand2 \\ = \\ nX \end{array} \right\} \right] \dots 20$$

Operand Definition Table:

Operand	Possible Structure	Possible Formats	Referencing Permitted	Dynamic Definition
<i>operand1</i>	C S	A	no	no
<i>operand2</i>	C S A	A U N P I F B D T L C O	no	no

Syntax Element Description:

Syntax Element	Description
<i>operand1</i>	<i>operand1</i> is the name of the helproutine or help map to be invoked. The name may be a 1 to 8 character alphanumeric constant or user-defined variable. If a variable is used, it must have been previously defined. The name may contain an ampersand (&); at execution time, this character will be replaced by the one-character code corresponding to the current value of the Natural system variable *LANGUAGE. This feature allows the use of multi-lingual helproutines or help maps.
<i>operand2</i>	You may specify 1 to 20 parameters (<i>operand2</i>) which are passed to the helproutine or help map. They may be specified as constants or as user-defined variables which contain the values of the parameters.
=	<p>The equals sign (=) is used to pass an object or a field name to a helproutine or help map:</p> <ul style="list-style-type: none"> ■ If the equals sign is entered in the HE= specification at statement level, the name of the object (as contained in the system variable *PROGRAM) being executed is passed to the helproutine or help map. In Example 3, the object name passed is PROGRAM1. ■ If the equals sign is entered in the HE= specification at field level, the name of the field is passed to the helproutine or help map. In Example 3, the field name passed is #PARM1. <p>If the equals sign is used as a parameter, the corresponding parameter in the helproutine or help map must be specified with format/length A65.</p>
<i>nX</i>	The notation <i>nX</i> can be used to specify parameters to be omitted, that is, for which no values are to be passed. The corresponding receiving parameters in the called helproutine's DEFINE DATA PARAMETER statement must be defined as OPTIONAL.



Notes:

1. The operands must be separated either by the input delimiter character (as specified with the session parameter **ID**) or by a comma. However, a comma must not be used for this purpose if the comma is defined as decimal character (with the session parameter **DC**).
2. If parameters are specified, the helproutine must begin with a DEFINE DATA PARAMETER statement which defines fields that correspond with the parameters in format and length.
3. The value of the field for which a helproutine is specified may be referenced within the helproutine. This is done by specifying a field in the DEFINE DATA PARAMETER statement which corresponds in format and length with the original field. In the block of fields defined within the DEFINE DATA PARAMETER statement, this field must always be defined behind the parameters, if present.
4. If the field for which a helproutine is specified is an array element, its indices may be referenced by the helproutine. To do so, you specify index parameters with format I (integer), N (numeric unpacked), or P (packed numeric) at the end of the DEFINE DATA PARAMETER statement. You may specify up to three index parameters according to array dimensions.

Execution of Helproutines

If a helproutine or help map is requested - by entering a question mark (?) in the field, or by pressing the help key (as defined with a `SET KEY` statement), or via a `REINPUT USING HELP` statement - all other data that may have been entered into fields are not assigned to the program variables until all help requests have been processed.



Note: Only one help request per `INPUT` statement is possible; that is, if help is requested for more than one field (for example, by entering question marks in multiple fields), only the first help request will be executed.

Examples

Example 1:

```
/* MAIN PROGRAM
DEFINE DATA
1 #A(A20/1:3)
END-DEFINE
...
SET KEY PF1=HELP
...
INPUT #A (2) (HE='HELPA',=)
...
END
```

Example 2:

```
/* HELP-ROUTINE 'HELPA'
DEFINE DATA PARAMETER
1 #VARNAME (A65)
1 #PARM1 (A20)
1 #VARINDEX (I2)
END-DEFINE
...
```


Example 3:

```
* Program 'PROGRAM1'
*
DEFINE DATA LOCAL
1 #PARM1 (A65) INIT <'valueparm1'>
END-DEFINE
SET KEY PF1 = HELP
FORMAT KD=ON
*
INPUT (AD=M HE='HELP1',=)
  'Enter ? for name of executed object:'
  / #PARM1
*
INPUT (AD=M)
  'Enter ? for field name:'
  / #PARM1 (HE='HELP1',=)
*
END
```

Parameter Data Area in Example Helproutine HELP1:

```
* Helproutine 'HELP1'
*
DEFINE DATA PARAMETER
1 #FLD1 (A65)
END-DEFINE
...
```


94

HI - Help Character

This Natural profile parameter defines the character which is to be used to invoke a field-specific helproutine or a map helproutine (if defined for a given map).

Possible settings	any special character	The character which is to be used to invoke a field-specific helproutine or a map helproutine. Note: 1. The character specified with the profile parameter HI must not be the same as the one specified with the profile/session parameter CF (control character for mainframe terminal commands). 2. It should not be the same as the one specified with the profile/session parameter DC (decimal character), profile/session parameter IA (input assign character) or profile/session parameter ID (input delimiter character).
	blank	Note: When HI=' ' is set, a help key must be defined in the Natural application, using the SETKEY statement correspondingly; otherwise it is not possible to invoke a helproutine for any field.
Default setting	?	Question mark.
Dynamic specification	yes	
Specification within session	no	
Application programming interface	USR0350N	See SYSEXT - <i>Natural Application Programming Interfaces</i> in the <i>Utilities</i> documentation.

95

HW - Heading Width

With this session parameter you determine the width of a column output with a `DISPLAY` statement.

Possible settings	ON	The width of a <code>DISPLAY</code> column is determined by either the length of the heading text or the length of the field, whichever is longer. Note: This is true even if no heading text is output, either because the <code>DISPLAY</code> statement contains the keyword <code>NOHDR</code> or the <code>DISPLAY</code> statement is a subsequent <code>DISPLAY</code> (see also the <code>DISPLAY</code> statement).
	OFF	The width of a <code>DISPLAY</code> column is determined by the length of the field. Note: <code>HW=OFF</code> only applies to <code>DISPLAY</code> statements which do not create headers (that is, either a first <code>DISPLAY</code> statement with <code>NOHDR</code> option or a subsequent <code>DISPLAY</code> statement).
Default setting	ON	
Specification within session	yes	
Applicable statements	<code>DISPLAY</code> <code>FORMAT</code>	
Applicable command	none	

Example:

```
DISPLAY (HW=OFF)
```


96 IA - Input Assign Character

This Natural profile and session parameter defines the character to be used as the assignment character for the input parameter processing in INPUT statements, either in keyword/delimiter mode or when processing data from the Natural stack.

Possible settings	any special character	Assignment character for the input parameter processing in INPUT statements.
Default setting	=	Equals sign.
Dynamic specification	yes	
Specification within session	yes	
Applicable statements	SET GLOBALS	
Applicable command	GLOBALS	
Application programming interface	USR1005N	See <i>SYSEXT - Natural Application Programming Interfaces</i> in the <i>Utilities</i> documentation.



Notes:

1. The character specified with the IA parameter must not be the same as the character specified with the profile/session parameters **CF** (control character for mainframe terminal commands), **DC** (decimal character) or **ID** (input delimiter character) and should not be the same as the one specified with the profile parameter **HI** (help character).
2. Within a Natural session, the profile parameter IA can be overridden by the session parameter IA.
3. Under Natural Security, the setting of this parameter can be overridden by the *Session Parameters* option of the Library Profile.

Example:

In the following example, it is assumed that, for the beginning, the default input assign character (=) applies.

```
** Example 'IACHAR': Input Assign character
*****
DEFINE DATA LOCAL
1 #A (A1)
1 #B (A1)
END-DEFINE
*
INPUT #A #B
*
WRITE 'Field #A:' #A / 'Field #B:' #B
*
END
```

1. Enter the command

```
IACHAR #A=Y,#B=X
```

The program produces the following output:

```
Page          1                               05-01-19  11:05:51
Field #A: Y
Field #B: X
```

2. Enter the command

```
GLOBALS IA=:
```

This sets the input assign character to colon (:).

3. Then enter the command

```
IACHAR #B:X,#A:Y
```

The program produces the following output:

```
Page          1                               06-11-13  12:12:24
Field #A: Y
Field #B: X
```


97 IC - Insertion Character

With this session parameter, you specify the character string to be inserted in the column immediately preceding the value of a field output with a `DISPLAY` statement. The width of the output column is increased accordingly.

Possible settings	any character	Character string to be inserted. You can specify a string of one to ten characters. Note: Insertion characters may optionally be specified within apostrophes, in which case any characters can be specified. Any character string specified which contains a closing parenthesis or a quotation mark must be enclosed within apostrophes. A blank in a character string not enclosed within apostrophes is represented by a circumflex (^).
Default setting	none	
Specification within session	yes	
Applicable statements	<code>FORMAT</code>	Parameter may be specified dynamically with the <code>FORMAT</code> statement.
	<code>DISPLAY</code>	Parameter may be specified at statement level and/or at element level.
Applicable command	none	



Notes:

1. The insertion character is inserted between leading spaces and the field value whereas the leading character is output in front of the leading space.
2. For numeric values, the insertion characters will be placed before the first significant digit printed.
3. The `IC` and `LC` parameters are mutually exclusive.
4. The parameter `IC` can also be used with `U` format fields.

5. For information on Unicode format, see also *Unicode and Code Page Support in the Natural Programming Language, Session Parameters, EMU, ICU, LCU, TCU versus EM, IC, LC, TC* in the *Unicode and Code Page Support* documentation.
6. The difference between the session parameters `LC`, `LCU` and `IC`, `ICU` will be evident, if the corresponding field is output right justified (session parameter `AD=R`).
7. See also *Parameters to Influence the Output of Fields* in the *Programming Guide*.

Examples:

```
DISPLAY AA(IC=*)  
DISPLAY SALARY(IC='$')
```

98

ICU - Unicode Insertion Character

With this session parameter, you specify the character string to be inserted in the column immediately preceding the value of a field output with a `DISPLAY` statement. The width of the output column is enlarged accordingly.

Possible settings	any character	Character string to be inserted. You can specify a string of one to ten characters. Note: Insertion characters may optionally be specified within apostrophes, in which case any characters can be specified. Any character string specified which contains a closing parenthesis or a quotation mark must be enclosed within apostrophes. A blank in a character string not enclosed within apostrophes is represented by a circumflex (^).
Default setting	none	
Specification within session	yes	
Applicable statements	FORMAT	Parameter may be specified dynamically with the <code>FORMAT</code> statement.
	DISPLAY	Parameter may be specified at statement level and/or at element level.
Applicable command	none	



Notes:

1. The session parameter `ICU` is identical to the session parameter `IC`. The difference is that the insertion characters are always stored in Unicode format. This allows you to specify insertion characters with mixed characters from different code pages, and assures that always the correct character is displayed independent of the installed system code page.
2. For numeric values, the insertion characters will be placed before the first significant digit printed.
3. The parameters `ICU` and `LCU` are mutually exclusive.

See also:

- *Parameters to Influence the Output of Fields in the Programming Guide*
- *Unicode and Code Page Support in the Natural Programming Language, Session Parameters, EMU, ICU, LCU, TCU versus EM, IC, LC, TC in the Unicode and Code Page Support documentation.*

99

ID - Input Delimiter Character

This Natural profile and session parameter defines the character to be used as a delimiter character for INPUT statements in keyword/delimiter mode.

Possible settings	any special character	Input delimiter character.
Default setting	,	Comma (,). Note: If the input delimiter character is to be a comma (,), it must be specified as ID=' , ' when using the dynamic parameter facility, because the comma character separates individual parameters.
Dynamic specification	yes	
Specification within session	yes	
Applicable statements	SET GLOBALS	
Applicable command	GLOBALS	
Application programming interface	USR1005N	See SYSEXT - <i>Natural Application Programming Interfaces</i> in the <i>Utilities</i> documentation.



Notes:

1. The character specified with this parameter must not be the same as the one specified with the profile/session parameter **DC** (decimal character) or **IA** (input assign character), and it should not be the same as the one specified with the **CF** parameter (control character for mainframe terminal commands) or **HI** parameter (help character).
2. The period (.) should not be used as input delimiter, because this might lead to situations in which a program termination period would be misinterpreted as input delimiter. An asterisk (*) should not be used either.
3. Within a Natural session, the profile parameter **ID** can be overridden by the session parameter **ID**.

4. Under Natural Security, the setting of this parameter can be overridden by the Session Parameters option of the Library Profile.

100

IKEY - Processing of PA and PF Keys

This Natural profile parameter specifies the action to be taken when a video-terminal program-attention key (PA key) or program-function key (PF key) is used to enter data, and the key has not been defined to the Natural program with the `SET KEY` statement.

Possible settings	ON	Natural reacts as if ENTER had been pressed.
	OFF	A REINPUT message is generated, prompting the user to press a valid key.
Default setting	OFF	
Dynamic specification	yes	
Specification within session	no	

101

IM - Input Mode

This Natural profile and session parameter determines the default mode for video-terminal input.

Possible settings	F	Forms mode.
	D	Delimiter mode.
Default setting	F	
Dynamic specification	yes	
Specification within session	yes	
Applicable statements	SET GLOBALS	
Applicable command	GLOBALS	
Application programming interface	USR1005N	See <i>SYSEXT - Natural Application Programming Interfaces</i> in the <i>Utilities</i> documentation.



Notes:

1. Within a Natural session, the setting of the profile parameter `IM` can be overridden by the session parameter `IM`.
2. Under Natural Security, the setting of this parameter can be overridden by the Session Parameters option of the Library Profile.
3. For information on delimiter mode and forms mode, see the `INPUT` statement.

102

INIT-LIB - Library for Automatic Logon

This Natural profile parameter specifies the name of the library to be used for an automatic logon (see the profile parameter [AUTO](#)) when Natural is started.

Possible settings	1-8 characters	Valid library name.
Default setting	none	
Dynamic specification	no	
Specification within session	no	



Note: If Natural Security is installed, INIT-LIB is not evaluated; the library to be used for automatic logon is read from the FSEC system file (see the *Natural Security* documentation for further information).

103

IP - INPUT Prompting Text

This session parameter is used to control prompting text in `INPUT` statements.

Possible settings	ON	Even if no text is specified preceding the input/output in an <code>INPUT</code> statement, the name of the field will be generated by default as a text element preceding the field as prompting text.
	OFF	No automatic prompting text will be generated for input/output fields in an <code>INPUT</code> statement. Only fields explicitly preceded with a text element will receive the text as prompting text.
Default setting	ON	
Specification within session	yes	
Applicable statements	FORMAT INPUT	
Applicable command	none	

Example:

```
FORMAT IP=OFF
```

104 IS - Identical Suppress

With this session parameter, you can suppress the printing of identical information in successive lines created by a `WRITE` or `DISPLAY` statement.

Possible settings	ON	A value which is identical to the previous value for the field will not be displayed. Note: If a <code>DISPLAY</code> or <code>WRITE</code> statement is used to create multiple output lines using the <code>VERT</code> or slash (/) notation, <code>IS=ON</code> applies only to the first line.
	OFF	No automatic suppression will be used.
Default setting	OFF	
Specification within session	yes	
Applicable statements	<code>DISPLAY</code> <code>FORMAT</code> <code>WRITE</code>	
Applicable command	none	



Notes:

1. The `IS` parameter setting can be suspended for one record by issuing the `SUSPEND IDENTICAL SUPPRESS` statement.
2. The `IS` parameter may be used in combination with the parameters `ES` and `ZP` to cause empty line suppression.
3. See also *Parameters to Influence the Output of Fields* in the *Programming Guide*.

Example:

```
FORMAT IS=ON
```


105

KC - Check for Statement Keywords

This parameter corresponds to the Natural profile parameter [KCHECK](#).

106

KCHECK - Check for Statement Keywords

This profile parameter checks field declarations in a programming object against a set of critical Natural keywords.

Possible settings	ON	The check for keywords is performed. If a variable name defined matches one of these keywords, a syntax error is reported when the programming object is checked or cataloged.
	OFF	No check for keywords is performed.
Default setting	OFF	
Dynamic specification	yes	
Specification within session	yes	
Applicable statements	OPTIONS	
Applicable command	KCHECK	Option of system command COMPOPT



Notes:

1. The section *Performing a Check for Natural Reserved Keywords* contains a list of the keywords that are checked by the KCHECK parameter.
2. The document *Natural Reserved Keywords* in the *Programming Guide* contains an overview of Natural keywords and reserved words.

107

KD - Key Definition

This session parameter is used to display the names assigned to the PF keys (see the SET KEY statement).

Possible settings	ON	The names assigned to the PF keys are displayed.
	OFF	The names assigned to the PF keys are not displayed.
Default setting	OFF	
Specification within session	yes	
Applicable statements	FORMAT	
Applicable command	none	



Notes:

1. The PF key assignment information will always be displayed automatically in the two bottom lines of the physical screen with any output created by the INPUT, WRITE, DISPLAY, and PRINT statement.
2. As the key assignment display requires two lines, the logical page size (see the session parameter PS) must be reduced by two.

Example:

```
FORMAT KD=ON
```


108

KEY - Setting Assignments to PA, PF and CLEAR Keys

This Natural profile parameter is used to assign settings to the CLEAR key, program attention keys (PA keys) and program function keys (PF keys) on video terminals.

Possible settings	any character string	Settings can be assigned to the keys PA1 to PA3, PF1 to PF24 and to the CLEAR key. Note: The setting assigned to each key can be any character string. The character string must represent a Natural system command or a user command (user program). If the setting contains embedded blanks, it must be enclosed in apostrophes.
Default setting	none	
Dynamic specification	no	
Specification within session	yes	
Application programming interface	USR4005N	See <i>SYSEXT - Natural Application Programming Interfaces</i> in the <i>Utilities</i> documentation.



Notes:

1. Assignments made with the profile parameter `KEY` are only valid when specified from within the Natural direct command window.
2. The entire string specified with the profile parameter `KEY` must be enclosed in parentheses (except `KEY=OFF`). `KEY=OFF` un-assigns all keys.

Examples:

```
KEY=OFF  
KEY PF4=OFF  
KEY PF3="EDIT MAP"  
KEY CLR=LOGOFF  
KEY OFF
```


109

LC - Lower to Upper Case Translation

This Natural profile parameter controls lower-case to upper-case translation of input characters.

Possible settings	ON	No translation of lower-case characters to upper case is performed.
	OFF	Natural translates all lower-case characters, except input from the Natural stack which was placed there by the <code>STACK</code> statement, to upper case.
Default setting	ON	
Dynamic specification	yes	
Specification within session	no	To disable or enable lower-case to upper-case translation dynamically within the active Natural session, you should use the terminal commands <code>%L</code> or <code>%U</code>
Application programming interface	USR1005N	See <i>SYSEXT - Natural Application Programming Interfaces</i> in the <i>Utilities</i> documentation.



Note: This parameter does not apply to Natural stack data which was placed on the Natural stack by the `STACK` statement.

110 LC - Leading Characters

With this session parameter, you can specify leading characters that are displayed immediately before a field output by a `DISPLAY` statement. The width of the output column is increased accordingly.

Possible settings	any character	Up to 10 characters may be specified. Note: 1. Leading characters may optionally be specified enclosed within apostrophes, in which case, any characters can be specified. 2. Any character string specified which contains a closing parenthesis or a quotation mark must be enclosed within apostrophes. 3. A circumflex (^) is used to represent a blank in a character string not enclosed within apostrophes.
Default setting	none	
Specification within session	yes	
Applicable statements	<code>FORMAT</code>	Parameter may be specified dynamically with the <code>FORMAT</code> statement.
	<code>DISPLAY</code>	Parameter may be specified at statement level and/or at element level.
Applicable command	none	



Notes:

1. The session parameters `LC` and `IC` are mutually exclusive.
2. The parameter `LC` can also be used with `U` format fields.
3. For information on Unicode format, see also *Unicode and Code Page Support in the Natural Programming Language, Session Parameters, EMU, ICU, LCU, TCU versus EM, IC, LC, TC*.

4. See also *Parameters to Influence the Output of Fields* in the *Programming Guide*.

Example:

```
DISPLAY {LC=*}
```

111 LCU - Unicode Leading Characters

With this session parameter, you can specify leading characters that are displayed immediately before a field output by a `DISPLAY` statement. The width of the output column is enlarged accordingly.

Possible settings	any character	Up to 10 characters may be specified. Note: 1. Leading characters may optionally be specified enclosed within apostrophes, in which case, any characters can be specified. 2. Any character string specified which contains a closing parenthesis or a quotation mark must be enclosed within apostrophes. 3. A circumflex (^) is used to represent a blank in a character string not enclosed within apostrophes.
Default setting	none	
Specification within session	yes	
Applicable statements	<code>FORMAT</code>	Parameter may be specified dynamically with the <code>FORMAT</code> statement.
	<code>DISPLAY</code>	Parameter may be specified at statement level and/or at element level.
Applicable command	none	



Notes:

1. The session parameter `LCU` is identical to the session parameter `LC`. The difference is that the leading characters are always stored in Unicode format. This allows you to specify leading characters with mixed characters from different code pages, and assures that always the correct character is displayed independent of the installed system code page.

2. The session parameters LCU and ICU are mutually exclusive.

See also:

- *Parameters to Influence the Output of Fields in the Programming Guide*
- *Unicode and Code Page Support in the Natural Programming Language, Session Parameters, EMU, ICU, LCU, TCU versus EM, IC, LC, TC in the Unicode and Code Page Support documentation.*

112

LE - Reaction when Limit for Processing Loop Exceeded

This Natural profile and session parameter controls the action to be taken if the limit of retrieved records was exceeded in a READ, FIND or HISTOGRAM processing loop.

Possible settings	ON	The database loop will be terminated when the limit is reached. The program flow will continue normally with the statement following the terminated database loop. When the execution of the Natural object is complete, error NAT0957 (Database loop limit reached with 'LE=ON' .) is raised. Note: LE=ON applies only to programs which are loaded from a library located in the system file FUSER, that is, library SYSTEM, or with a (library) name that does not start with the prefix SYS.
	OFF	The database loop will be terminated when the limit is reached. The program flow will continue normally with the statement following the terminated database loop. When the execution of the Natural object is complete, no error message appears.
Default setting	OFF	
Dynamic specification	yes	
Specification within session	yes	
Applicable statements	SET GLOBALS	
Applicable command	GLOBALS	
Application programming interface	USR1005N	See <i>SYSEXT - Natural Application Programming Interfaces</i> in the Utilities documentation.



Notes:

1. The LE parameter applies to READ, FIND and HISTOGRAM statements with a limit specified (see *Example*).
2. The limit may be specified either globally for a Natural object by using the LIMIT statement or by specifying an explicit limit value supplied in the database processing loop.
3. Within a Natural session, the profile parameter LE can be overridden by using the session parameter LE.

Example:

```
DEFINE DATA LOCAL
1 EMPL-VIEW VIEW OF EMPLOYEES
  2 NAME
END-DEFINE
READ (10) EMPL-VIEW BY NAME
  WRITE NAME
END-READ
END
```

LE=OFF: after 10 records the loop ends without a message.

LE=ON: after 10 records the loop ends with an error message NAT0957 (Database loop limit reached with 'LE=ON').

113

LFILE - Logical System File Definition

- LFILE Parameter Syntax 256
- Example of LFILE Parameter 257

This Natural profile parameter specifies information concerning the physical database file to be associated with a logical system file for Software AG products.

Possible settings	See <i>LFILE Parameter Syntax</i> .	
Default setting	none	
Dynamic specification	yes	
Specification within session	no	
Application programming interface	USR0011N	See <i>SYSEXT - Natural Application Programming Interfaces</i> in the <i>Utilities</i> documentation.
	USR2004N (recommended)	



Notes:

1. LFILE and NTFILE can be used for Software AG products which have their own system files (for example, Con-nect, Natural Review) to specify where such a system file is to be located. Such products use Database ID 255 and a logical file number (FNR) in their data definition modules (DDMs). With the LFILE parameter, you specify which physical database ID (DBID) and file number (and, if applicable, password and cipher key) are associated with that logical file number.
2. Natural records the physical file information and uses it for any database calls to Database ID=255 and File number=*logical-ID*.

LFILE Parameter Syntax

The LFILE parameter is specified as follows:

```
LFILE=(logical-FNR,physical-DBID,physical-FNR,password,cipher-key,RO)
```

Where:

Syntax Element	Value	Explanation
<i>logical-FNR</i>	1 - 251	Logical file number (LFL). This parameter is mandatory.
<i>physical-DBID</i>	0 - 65535, except 255	Physical database ID (DBID). Database ID 255 is reserved for logical system files for Software AG products.
<i>physical-FNR</i>	1 - 5000	Physical file number (FNR).
<i>password</i>	1 - 8 characters.	Password and cipher key are only required if the database file has been password-protected and/or ciphered using the Adabas security feature. With FDDM, FNAT and FUSER, the password and the cipher key are reserved for future use; currently they are ignored.
<i>cipher-key</i>	1 - 8 numerical digits.	

Syntax Element	Value	Explanation
<i>options</i>	R0	Flag for read-only access. The R0 flag is not supported on this platform.



Note: To define different logical files, the LFILE parameter must be specified multiple times (separated by a comma or a blank); see [Example of LFILE Parameter](#).

Example of LFILE Parameter

```
LFILE=(180,73,10),LFILE=(251,40,9,TEST99)
```


114

LOGONRQ - Logon for RPC Server Request Required

This Natural profile parameter determines whether or not logon data are required for an RPC server request.

Possible settings	ON	A logon is required; that is, the server only accepts requests from clients which include logon data in the RPC server request. For conversational requests, the logon data is only necessary when the conversation is opened. Note: If the Natural RPC server runs under Natural Security, you are strongly recommended to set LOGONRQ=ON. For further information, see <i>Using Natural RPC with Natural Security in the Natural Remote Procedure Call (RPC)</i> documentation.
	OFF	A logon is <i>not required</i> . Logon data will be processed nevertheless.
Default setting	OFF	
Dynamic specification	yes	
Specification within session	no	



Notes:

1. LOGONRQ is specified on the server side only.
2. For Natural clients, the logon data can be requested either by setting the LOGON option of the SYSRPC Service Directory Maintenance or by using the **logon indicator** of parameter DFS.
3. For information on Natural RPC, see the *Natural Remote Procedure Call (RPC)* documentation.

115

LS - Line Size

- Profile Parameter LS 262
- Session Parameter LS 262
- Specification with Statements 263

This Natural profile and session parameter specifies the maximum number of characters permitted per line for `DISPLAY`, `INPUT` and `WRITE` statements.

The following topics are covered below:

Profile Parameter LS

When used as a profile parameter, `LS` is honored in batch mode only and defines the physical line size. In online mode, the line size is always set to the physical screen width.

Possible settings	35 - 250	Maximum number of characters permitted per line.
	0	Use physical line size (mostly 132).
Default setting	0	
Dynamic specification	yes	

Session Parameter LS

Possible settings	2 - 250	Maximum number of characters permitted per line.
	0	Only permitted with the statement <code>SET GLOBALS</code> or with the system command <code>GLOBALS</code> . The value 0 will be replaced by the physical line size.
Default setting	Physical line size.	
Applicable command	<code>GLOBALS</code>	
Applicable statements	<code>FORMAT</code> <code>SET GLOBALS</code>	
Application programming interface	<code>USR1005N</code>	See <i>SYSEXT - Natural Application Programming Interfaces</i> in the <i>Utilities</i> documentation.



Notes:

1. At logon to a library, `LS` is reset to the physical line size.
2. Under Natural Security, the setting of this parameter can be overridden by the Session Parameters option of the Library Profile.

Specification with Statements

When specified with a statement, the LS parameter is evaluated at compilation time.

Applicable statements	DISPLAY INPUT WRITE	Parameter may be specified at statement level.
------------------------------	---------------------------	--

116

LT - Limit for Processing Loops

This Natural profile and session parameter is used to limit the number of database records which can be retrieved within Natural applications.

Possible settings	1 - 2147483647 0	Maximum number of records that can be retrieved. All retrieved records (including records rejected by means of a WHERE clause) are counted and compared with this limit. LT=0 defines that no limit is in effect for the number of retrieved records. Note: Within a session, you can specify a value in the range of 0 to <i>n</i> , where <i>n</i> is the value of profile parameter LT at session start.
Default setting	99999999	
Dynamic specification	yes	
Specification within session	yes	
Applicable statements	SET GLOBALS	Note: When the LT parameter is used in conjunction with the statement SET GLOBALS or the system command GLOBALS, the limit value that can be set may not exceed the LT value defined in the Natural parameter file NATPARM.
Applicable command	GLOBALS	
Application programming interface	USR1005N	See <i>SYSEXT - Natural Application Programming Interfaces</i> in the <i>Utilities</i> documentation.



Notes:

1. The limit set with the LE parameter applies to all statements retrieving records from the database; that is, statements that initiate processing loops, such as READ, FIND, HISTOGRAM or SELECT, and statements that retrieve only a single record, such as FIND UNIQUE, FIND NUMBER, FIND FIRST, GET (SAME) and SELECT SINGLE.
2. All retrieved records are counted and the result of the count is compared with the LT limit. The count also includes those records which were rejected by a WHERE clause of a FIND, READ or

HISTOGRAM statement. The LT limit does not affect the statements STORE, UPDATE, DELETE, END TRANSACTION and BACKOUT TRANSACTION.

3. When a record is retrieved from the database, the count of retrieved records is incremented before it is compared with the current value of the LT parameter. If the incremented count exceeds the current LT value, Natural error NAT1003 (“Global limit for database calls reached”) is raised. The count of retrieved records is reset to zero whenever a Natural program is started on Level 1. The count is not reset if the program on Level 1 invokes another Natural object (for further information, see *Multiple Levels of Invoked Objects* in the *Programming Guide*). Therefore the LT parameter limits the number of records retrieved from the database by a Level 1 program and objects invoked by that program on a level other than 1.
4. If the value of the LT parameter is dynamically changed within a program by using a SET GLOBALS LT=*n* statement, the new limit value becomes effective for the next statement that retrieves a record from the database.
5. Within a Natural session, the profile parameter LT can be overridden by using the session parameter LT.

117 MADIO - Maximum DBMS Calls between Screen I/O

Operations

This Natural profile parameter is used to specify the maximum number of DBMS calls permitted between two screen I/O operations (also in batch mode).

Possible settings	30 - 32767	Maximum number of DBMS calls.
	0	MADIO=0 indicates that no limit is to be in effect.
Default setting	512	
Dynamic specification	yes	
Specification within session	no	
Application programming interface	USR1005N	See <i>SYSEXT - Natural Application Programming Interfaces</i> in the <i>Utilities</i> documentation.
	USR1068N *	* Recommended.



Note: If the specified limit is exceeded, the Natural program is interrupted and the user is notified with an appropriate Natural error message.

118

MAINPR - Override Default Output Report Number

This Natural profile parameter is used to override the default output report number for all Natural reports. It must be set to a valid printer number (0 - 31).

Possible settings	0 - 31	Valid printer number.
Default setting	0	
Dynamic specification	yes	
Specification within session	no	
Application programming interface	USR6002N	See <i>SYSEXT - Natural Application Programming Interfaces</i> in the <i>Utilities</i> documentation.



Notes:

1. Specifying a MAINPR setting is the same as changing all of the DISPLAY, PRINT, WRITE or INPUT statements' printer references from the default setting (0) to the desired printer number.
2. A physical printer corresponding to the report number specified must be defined to Natural as described in the *Configuration Utility* documentation, section *Device/Report Assignments*.

119

MASKCME - MASK Compatible with MOVE EDITED

This Natural profile parameter is used to control Natural's compiler.

Possible settings	ON	The range of valid year values that match the YYYY mask characters is 1582 - 2699 to make the MASK option compatible to MOVE EDITED.
	OFF	The range of valid year values that match the YYYY mask characters is 0000 - 2699.
Default setting	OFF	
Dynamic specification	yes	
Specification within session	yes	
Applicable statements	OPTIONS	
Applicable command	MASKCME	Option of COMPOPT

120

MAXBUFF - Maximum Buffer Size

This Natural profile parameter is used in a Natural RPC environment to specify the maximum buffer sizes.

Possible settings	1 - 2097147	Maximum buffer size in KB.
	0	No buffer is allocated.
Default setting	0	
Dynamic specification	yes	
Specification within session	no	



Notes:

1. MAXBUFF can be specified on both the client and the server side.
2. On the server side, it determines the size of the buffer provided by the server to receive the client request including data and to send back the result. The buffer must be large enough to hold the largest of the following two data areas for all client requests; that is, the request received by the client, and the result sent back to the client. If the size of the buffer is too small for a request, a temporary buffer with the required size is allocated and used for this request. For further information, see *Stubs and Automatic RPC Execution* in the *Natural Remote Procedure Call (RPC)* documentation.
3. On the client side, it determines the size of the buffer provided for the automatic execution of Natural RPC calls. This buffer is used to build the client request including data and to receive the result from the server. The buffer must be large enough to hold the largest of the following two data areas for all requests sent by the client.
4. The size of the data exchanged between the client and server is provided by the stub generation function of the SYSRPC utility. To calculate the size for automatic RPC execution, you may use the SYSRPC CSMASS command; see *Calculating Size Requirements* in the *SYSRPC Utility* documentation.

Dependency on ACIVERS Settings

In case of an EntireX Broker node, special considerations apply if you are using Entire Net-Work as a transport layer. With Entire Net-Work, the receive buffer length passed to the EntireX Broker stub is restricted by the startup parameter `IUBL` and must not exceed 32 KB. Depending on the setting of the Natural profile parameter `ACIVERS`, the receive buffer length is set as follows:

- `ACIVERS=1`: 32000
- `ACIVERS=2`: 30K
- `ACIVERS>2`: the value specified with `MAXBUFF`

For further information, see the *Natural Remote Procedure Call (RPC)* documentation.

121

MAXCL - Maximum Number of Program Calls

This Natural profile parameter is used to specify the maximum number of program calls permitted between two screen I/O operations.

Possible settings	10 - 32767	Maximum number of program calls.
	0	MAXCL=0 indicates that no limit is to be in effect.
Default setting	50	
Dynamic specification	yes	
Specification within session	no	
Application programming interface	USR1005N	See <i>SYSEXT - Natural Application Programming Interfaces</i> in the <i>Utilities</i> documentation. * Recommended.
	USR1068N *	



Note: If the specified limit is exceeded, the Natural program is interrupted and the user is notified with an appropriate Natural error message.

122

MAXYEAR - Maximum Year for Date/Time Values

This Natural profile parameter sets the maximum value for the year part of date and time values that can be entered as constants or as terminal input.

Possible settings	2699	The maximum year that can be entered is 2699; that is, the maximum date value that can be entered is 2699-12-31.
	9999	The maximum year that can be entered is 9999; that is, the maximum date value that can be entered is 9999-12-31.
Default setting	2699	
Dynamic specification	yes	
Specification within session	no	



Notes:

1. MAXYEAR=9999 changes the maximum date value that can be entered from 2699-12-31 to 9999-12-31.
2. Before setting the value for MAXYEAR to 9999, you should carefully check your application for arithmetic operations or assignments of date or time values to fields that have data formats other than date or time, and perform the necessary changes. Otherwise, unexpected overflows leading to Natural errors at execution time may occur.

For example, you should check for

- redefinitions of date/time fields with P6/P12 fields
- assignments of date/time values to non-date/time fields such as `P6 := D`
- arithmetic operations with date/time values where the result is assigned to a non-date/time field, for example: `P6 := D + 7`
- input of date/time fields that is used in arithmetic operations with non-date/time fields later on, for example:

```
INPUT D(D)
P6 := D + 1
```

The use of the Natural Engineer is recommended to check your application.

The setting of MAXYEAR affects

- checking of date/time constants by the compiler, for example: `P6 := D'2699-12-31'`
- INPUT statements with input or modifiable date/time fields
- MOVE EDITED statements with source or target date/time fields
- IS (D) option in logical condition criteria
- MASK option in logical condition criteria with four-digit year check (YYYY)
- VAL system function with date field as target operand

You should ensure that the MAXYEAR settings are the same for

- cataloging and executing a Natural application
- Natural RPC servers and Natural RPC clients

See also:

- *Formats D - Date, and T - Time* in the *Programming Guide*
- *Date and Time Constants* in the *Programming Guide*
- Session parameter [EM](#) in the *Parameter Reference* documentation

123

MC - Multiple-Value Field Count

With this session parameter, you determine the number of values of a multiple-value field to be output by default when the field is specified without an index in a `DISPLAY` or `WRITE` statement.

Possible settings	1 - 191	Number of values.
Default setting	1	
Specification within session	yes	
Applicable statements	DISPLAY FORMAT INPUT PRINT WRITE	
Applicable command	none	



Note: This parameter may be used in reporting mode only.

Example:

```
FORMAT MC=5
```


124

MFSET - Multi-Fetch Setting

This Natural profile parameter specifies whether multi-fetch is used to retrieve records from Adabas databases.

Possible settings	NEVER	Always use single-fetch.
	OFF	Use single-fetch as default. This can be overwritten on statement level.
	ON	Use multi-fetch as default. This can be overwritten on statement level.
Default setting	OFF	
Dynamic specification	yes	
Specification within session	no	

125

ML - Position of Message Line

This profile and session parameter specifies the line to be used for the display of applications which do not set the message line position explicitly by using the `SET CONTROL 'M'` statement.

Possible settings	B	Natural messages are displayed at the bottom of the screen.
	T	Natural messages are displayed at the top of the screen.
Default setting	B	
Dynamic specification	yes	
Specification within session	yes	
Applicable statements	SET CONTROL 'M'	
Applicable command	GLOBALS	
Application programming interface	USR1005N	See <i>SYSEXT - Natural Application Programming Interfaces</i> in the <i>Utilities</i> documentation.



Notes:

1. For information on the operand 'M', see the Natural terminal command %M (Control of Message Line).
2. The profile parameter ML does not exist in the Configuration Utility. Use session parameter ML instead.
3. Within a Natural session, the profile parameter ML can be overridden by the session parameter ML.

126

MP - Maximum Number of Pages of a Report

This Natural profile and session parameter specifies the maximum number of pages to be produced for a report.

Possible settings	1 - 99999	The value specified is the number of physical pages and has no effect on the starting page number used. The program will be terminated with an error message if the MP value is exceeded.
	0	No page limit is defined.
Default setting	0	
Dynamic specification	no	
Specification within session	no	
Applicable statements	DISPLAY FORMAT PRINT WRITE	
Applicable command	none	



Note: Within a Natural session, the setting of profile parameter MP can be reduced, but not increased by the `FORMAT` statement. The value specified with the session parameter MP applies only to the specified report.

127

MS - Manual Skip

With this session parameter, you control the cursor positioning during the processing of an INPUT statement.

Possible settings	ON	See example below. Note: The setting MS=ON is not supported under BS2000/OSD.
	OFF	The cursor will be positioned to the next input field as soon as the value for the current field is entered with all positions.
Default setting	OFF	
Specification within session	yes	
Applicable statements	FORMAT INPUT	
Applicable command	none	

Example:

```
INPUT (MS=ON) #A #B
```


128

MSGSF - Display System Error Messages in Short/Full

Format

This Natural profile parameter can be used to avoid truncation of Natural system error messages.

Possible settings	ON	System error messages will be displayed in full; that is, program name, line number and actual message text.
	OFF	System error messages will be displayed in short form; that is, only the actual message text will be displayed (but not the program name and line number).
Default setting	ON	
Dynamic specification	yes	
Specification within session	yes	

By default, a Natural system error message consists of the following:

- the name of the program,
- the number of the line that caused the error,
- the actual text of the message.

Depending on the size of the window in which the message is displayed, the text may be truncated. With this parameter, you can avoid such truncation.

129

NATLOG - Natural Log File

- Examples 292

This Natural profile parameter is used to log messages that will not (or could not) be written to the standard output in interactive mode or to the output file `CMPRINT` in batch mode.

Possible settings	OFF	Disables the log mechanism.
	ERR	Logs error messages.
	INF	Logs information and success messages.
	WRN	Logs warning messages.
	ALL	Logs all types of messages.
Default setting	OFF	
Dynamic specification	yes	
Specification within session	no	



Notes:

1. The location of the `NATLOG` file is the `TEMP` directory of Natural (specified in the local configuration file `NATURAL.INI`). If this path is unknown, Natural creates the file in the current directory.
2. Natural tries to create the following file name, if the `user-ID/et-ID` information could be retrieved: `NATURAL_<user-ID>_<et-ID>.LOG`
3. If `user-ID` and `et-ID` could not be retrieved, then the following file name is used: `NATURAL.LOG`.
4. Example File Names: A Natural batch process is running with `user-ID=SYSTEM` and `et-ID=14`, then the resulting file name is `NATURAL_SYSTEM_14.LOG`.
5. If the `user-ID` could not be retrieved (which is the case if an error occurs during the initialization phase of Natural), then the resulting file name is `NATURAL.LOG`.

Examples

The following example shows the contents of a Natural log file. At top of the file, there is a header with some environment information, for example the Natural Version, the parameter file currently in use and so on. Two entries follow. The first one an entry which displays the I/O channels needed for batch mode. The second entry shows an error message. Both messages are counted in the statistics summary.

Example `NATLOG` Output Contents for OpenVMS:

```

# #####
#           N a t u r a l   L o g   F i l e
# #####
#
# Logging started at : 28-May-2008 15:28:19.048
#
# Natural Version      : V v.r.s   Software AG 2008
# Server Type         : (none)
# Device              : BATCH (real)
# BufferPool Name     : BPNATAN2
# Parameter File      : NATPARAM
#
# User ID             : NATURAL
# ET ID               : TEST
# Network User ID    : NATURAL
#
# Host Name           : NATAN2
# Machine Class      : VMS
# Operating System   : OVMS/IA6V8.3-1H1
#
# Process ID         : 21E51D3A
#
# NATLOG Option      : ALL
#
# #####
# -----
# 15:28:19.052 NATURAL      INFORMATIONAL  STATISTICS:  INF=1  WRN=0  ERR=0
# -----
Value of parameter CMSYNIN (command file)
alf9$user:[tmp]batch.cmd
Value of parameter CMOBJIN (input file)

Value of parameter CMPRINT (output file)
alf9$user:[tmp]batch.out
# -----
# 15:28:19.069 NATURAL      ERROR          STATISTICS:  INF=1  WRN=0  ERR=1
# -----
Natural Startup Error: 42
Batch mode driver error.
Parameter CMOBJIN not set.

```


130

NATVERS - Switching between Natural Environments

This Natural profile parameter enables you to access various Natural environments, that is, various *err*, *txt*, *bin*, *etc*, *samples* and *tmp* subdirectories.

Possible settings	any character string	Determines the Natural version.
Default setting	<i>v.r.s</i>	Note: A DEFAULT-VERSION entry in <i>SAG.INI</i> is no longer necessary.
Dynamic specification	yes	This parameter can only be specified dynamically.
Specification within session	no	

Where *v.r.s* is the current version of Natural. In the following sample programs, the characters *v.r.s* stand for the *version, release, system maintenance level*.

The NATVERS value you enter is used by Natural to determine the *SAG.INI* section you want to use with your Natural session. By default, the Natural installation creates a section in the *SAG.INI* file that points to the installed Natural environment.

The Natural installation automatically identifies the Natural version and creates the section [NATURAL=*v.r.s*] in your *SAG.INI* file that points to the installed Natural environment. This might look as in the following example:

```
[NATURAL-v.r.s]  
PROD_API=C:\Program Files\Software AG\v.r.s\Bin\natprd32.dll  
NATGUI_BMP=C:\Program Files\Software AG\Natapps\Pic  
NATDIR=C:\Program Files\Software AG  
NATINI=C:\Program Files\Software AG\v.r.s\Etc  
[NATURAL-v.r.s-END]
```

If you want to access environments other than the one that was installed automatically, create a new section for each environment as shown in the following example:

```
[NATURAL-Serverv.r.s]
NATVERS=v.r.s
PROD_API=\\Server\Program Files\Software AG\v.r.s\Bin\natprd32.dll
NATGUI_BMP=\\Server\Program Files\Software AG\Natapps\Pic
NATDIR=\\Server\Program Files\Software AG
NATINI=\\Server\Program Files\Software AG\v.r.s\Etc
[NATURAL-Serverv.r.s-END]
```

Replaced settings are still contained in the *SAG.INI* file and can be used by specifying them with *NATVERS* to switch to the corresponding Natural environments.

131

NC - Use of Natural System Commands

This Natural profile parameter controls whether Natural system commands can be used during the Natural session or not.

Possible settings	ON	System commands cannot be used. Exceptions: FIN, LAST, LOGOFF, LOGON, RENUMBER, RETURN, SETUP and TECH. Note: 1. If you have Natural Security installed, any system command restrictions you set with Natural Security are valid, regardless of the setting of the NC profile parameter. 2. In a Natural Development Server environment on mainframe computers, the value OFF will be assumed for the Natural Development Server, even if NC=ON has been specified. 3. If NC=ON has been specified on the client side, subsequent system commands issued on the client side will be rejected as described above.
	OFF	All system commands can be used.
Default setting	OFF	
Dynamic specification	yes	
Specification within session	yes	
Applicable statements		
Applicable command		
Application programming interface	USR1005N	See SYSEXT - <i>Natural Application Programming Interfaces</i> in the <i>Utilities</i> documentation.



Notes:

1. Within a Natural session, the profile parameter `NC` can be overridden by the session parameter `NC`.
2. Natural terminal commands and user-created commands (object module names) are not affected by the `NC` parameter.
- 3.

132

NCFVERS - NCF File Protocol Version

This Natural profile parameter enables downward compatibility with Natural Versions lower than Version 6.1. It specifies the protocol version of the Entire Connection format file (.NCF) to be used. This Entire Connection format is generated when work files of type ENTIRE CONNECTION or DEFAULT work files with the file extension .NCD are written.

Possible settings	0	A format file of Entire Connection Protocol Version 0 is written. The format files created are compatible with those of Natural Versions lower than Version 6.1.
	2	A format file of Entire Connection Protocol Version 2 is written, which is created by Natural Version 6.1 or 6.2.
	3	A format file of Entire Connection Protocol Version 3 is written, which is created by Natural Version 6.3.
Default setting	3	
Dynamic specification	no	
Specification within session	no	



Note: For information on the work file types ENTIRE CONNECTION and the Entire Connection format, refer to and *Work File Formats* in the *Operations* documentation.

133

NENTRY - Left/Right Alignment of Numeric Field Entries

This Natural profile parameter defines the alignment of input entered in numeric INPUT fields (that is, fields of format I, N, P or F).

Possible settings	LEFT	The characters entered in a numeric INPUT field are left justified.
	RIGHT	The characters entered in a numeric INPUT field are right justified.
Default setting	LEFT	
Dynamic specification	no	
Specification within session	no	

134

NL - Numeric Length for Output

This session parameter determines the default input/output length for a numeric field used in a DISPLAY, INPUT, PRINT or WRITE statement.

Possible settings	<i>nn.m</i>	<p>The length is specified as <i>nn.m</i>, where <i>nn</i> represents the number of positions before the decimal separator, and <i>m</i> represents the number of positions after the decimal separator.</p> <p>The <i>m</i> notation is optional. The value of <i>m</i> must not exceed 7. The total of <i>nn+m</i> must not exceed 29.</p> <p>Note:</p> <ol style="list-style-type: none">1. If NL is set less than the field length, values are truncated. No error is produced when relevant digits are truncated.2. If NL is set greater than the field length, values are expanded with blanks. No error is produced when an input field is truncated.
Default setting	none	
Specification within session	yes	
Applicable statements	DISPLAY FORMAT INPUT PRINT WRITE	
Applicable command	none	



Notes:

1. The NL parameter must not be specified for groups.
2. Any edit mask specified for a field will override the NL parameter for this field.

3. See also *Parameters to Influence the Output of Fields* in the *Programming Guide*.

Example:

```
DISPLAY #AA(NL=20) #AB(NL=3.2)
```

135

NOAPPLERR - Suppress Message Number Prefix NAT

This Natural profile parameter is used to suppress the message number prefix "NAT" with user-supplied error messages.

Possible settings	ON	The prefix "NAT" is not displayed in error messages.
	OFF	The prefix "NAT" is displayed in error messages.
Default setting	OFF	
Dynamic specification	yes	
Specification within session	no	

136

NOPROX - Specify Local Domains for Direct Addressing

This Natural profile parameter specifies the domain(s) which shall be addressed directly, that is, not via the proxy.

Possible settings		See <i>Example</i> .
Default setting	none	
Dynamic specification	no	
Specification within session	no	

Example:

```
"*.software-ag.de; sagus.software-ag.com"
```


137 NOSSLPRX - Specify Local Domains for Direct

Addressing SSL

This Natural profile parameter specifies the domain(s) which shall be addressed directly, that is, not via the SSL proxy.

Possible settings		See <i>Example</i> .
Default setting	none	
Dynamic specification	no	
Specification within session	no	

Example:

```
"*.software-ag.de; sagus.software-ag.com"
```


138

OPF - Overwriting of Protected Fields by Helproutines

This Natural profile and session parameter specifies whether the content of a write-protected field (attribute definition `AD=P`) can be overwritten by a helproutine assigned to the field.

Possible settings	ON	A helproutine assigned to a field can overwrite the field's content, even if the field is write-protected.
	OFF	Helproutines cannot overwrite the contents of write-protected fields.
Default setting	ON	
Dynamic specification	yes	
Specification within session	yes	
Applicable statements	SET GLOBALS	
Applicable command	GLOBALS	
Application programming interface	USR1005N	See <i>SYSEXT - Natural Application Programming Interfaces</i> in the <i>Utilities</i> documentation.



Notes:

1. The `OPF` profile parameter only applies to the field for which a helproutine is invoked; it does not affect parameters explicitly passed to the helproutine. This means that the `OPF` profile parameter takes no effect if the field for which help is invoked is also explicitly specified as a parameter to be passed to the helproutine.
2. In addition, in reporting mode you can change the `OPF` setting using the statement `SET GLOBALS`.
3. Within a Natural session, the profile parameter `OPF` can be overridden by the session parameter `OPF`.

139

OPRB - Database Open/Close Processing

- OPRB String Syntax 314

This Natural profile parameter controls the use of the Adabas C open/close commands during a Natural session.

Possible settings	OFF	If the OPRB parameter is set to OFF, a Natural session starts with an Adabas OP command requesting UPD (access/update) to the Natural system file. Natural also issues RELEASE CID (Adabas RC) commands to release all ISN lists (ISN lists specified in a RETAIN clause of a Natural FIND statement are not released).
	OPRB=(<i>string</i>)	You can specify an open request in accordance with the syntax described below. See also the examples listed.
Default setting	OFF	
Dynamic specification	no	
Specification within session	no	

This Natural profile parameter is required if any of the following conditions is true:

- An explicit list of Adabas files to be accessed/updated is to be provided. This is necessary, for example, if Adabas cluster updating or exclusive file control is to be requested.
- The Adabas record buffer to be used with the initial Adabas OP command can be explicitly provided. To access databases you have to specify the DBIDs and file numbers with their corresponding access rights at the OPRB string.
- The character set for Adabas format W is to be provided. To access databases you have to specify the DBIDs and the required encoding name.

Entries may not contain blanks, must be enclosed in parenthesis and must follow the rules defined in the relevant Adabas documentation.

In addition to the Adabas syntax, internal file numbers can be specified by using the *x-y* notation (that is, all numbers between *x* and *y*).

OPRB String Syntax

DBID=(*x*) specifies the database for the following access right entries:

ACC=(<i>file-list</i>)	Specifies access permission (read) for the files in the file list.
UPD=(<i>file-list</i>)	Specifies update permission (read/write) for the files in the file list.
EXU=(<i>file-list</i>)	Specifies exclusive update permission (exclusive read/write) for the files in the file list.

<code>WCODE=<i>encoding</i></code>	Specifies the encoding for W fields in the Adabas user session (Adabas for Mainframes). Required encoding code for Adabas on Mainframes is 4095.
<code>WCHARSET=<i>charset</i></code>	Specifies the default character set used for W fields in record and value buffers in the Adabas user session (Adabas for UNIX, OpenVMS and Windows). Required encoding names for Adabas on UNIX, OpenVMS and Windows are UTF-16LE or UTF-16BE.

The trailing record buffer dot (.) can be omitted in the OPRB string because it is appended automatically.

DBID=0 specifies the default record buffer entry and can be omitted if it is the first DBID listed in the OPRB string. This default record buffer is taken if there is no specific entry for the requested database.

Combinations of the keywords ACC, UPD, EXU and WCODE or WCHARSET must follow the rules as defined in the relevant Adabas documentation. Natural issues an OP command at the start of a Natural session and a CL command at the end of the session. At the end of a Natural program, only the required RC commands are issued to release held ISN lists.

Example 1:

```
(ACC=2,3,4,DBID=15,UPD=3,4,ACC=5)
```

The following entries were defined:

```
'UPD=3,4,ACC=5.' for DB 15  
'ACC=2,3,4.' for other databases (DB 0)
```

Example 2:

```
(DBID=15,ACC=2-7)
```

The following entry was defined:

```
'ACC=2,3,4,5,6,7.' for DB 15; access to other databases is not permitted.
```

Example 3:

```
(DBID=0,ACC=2,3,4,5.)
```

The following entry was defined:

```
'ACC=2,3,4,5.' for all databases (DB 0).
```



Note: If you have Natural Security installed, open/close processing works the same way as without Natural Security; the `OPRB` parameter in the security profile is provided for future use only.

Example 4:

```
(DBID=0,ACC=2,3,4,5,DBID=12,WCHARSET='UTF-16LE',UPD=3-10)
```

The following entry was defined:

```
'ACC=2,3,4,5.' for all databases (DB 0).
```

```
WCHARSET='UTF-16LE',UPD=3,4,5,6,7,8,9,10. for DB 12.
```

140

PARM - Alternative Parameter File

This Natural profile parameter can be used for Natural startup (Studio/Runtime/Server) in order to specify an alternative parameter file Natural is to run with.

Possible settings	1 - 8 characters	Any valid file name.
Default setting	none	
Dynamic specification	yes	This parameter can only be specified dynamically.
Specification within session	no	



Notes:

1. If no PARM parameter is specified, Natural will start using the default NATPARM parameter file containing all default settings for each single parameter. Use the Natural Configuration Utility in order to create your own new parameter file.
2. See *Creating a New Parameter File* in the *Configuration Utility* documentation.

141

PC - Control of Personal-Computer Access Method

This Natural profile parameter determines whether support of the personal-computer access method is to be provided using Natural Connection.

Possible settings	ON	Personal-computer support is enabled. The Natural statements READ PC FILE or WRITE PC FILE can be used (for uploading or downloading); see UPLOAD PC FILE and DOWNLOAD PC FILE. Note: With PC=ON, the system variable *DEVICE will always contain the value PC.
	OFF	No personal-computer support is to be provided.
	NAM	Field names are sent when data are uploaded/downloaded. Note: This value is for mainframe environments only.
	NONAM	No field names are sent when data are uploaded/downloaded. Note: This value is for mainframe environments only.
Default setting	OFF	
Dynamic specification	yes	
Specification within session	yes	



Notes:

1. This Natural profile parameter only applies if Natural Connection is installed.
2. The files used for the PC access method have to be defined with the profile parameter [WORK](#).

142

PC - Periodic Group Count

This session parameter determines the number of periodic group occurrences to be output by default if a periodic group (or a field contained within a periodic group) is specified without an index in a DISPLAY or WRITE statement.

Possible settings	1 - 191	Number of values.
Default setting	1	
Specification within session	yes	
Applicable statements	FORMAT	
	INPUT	Parameter may be specified at statement level and/or at element level.
	DISPLAY	
	WRITE	
PRINT		
Applicable command	none	



Note: This session parameter may be used in reporting mode only.

Example:

```
FORMAT PC=5
```


143

PCHECK - Parameter Checking for Object Calling

Statements

This Natural profile parameter is used to control Natural's compiler.

Possible settings	ON	<p>The compiler checks the number, format, length and array index bounds of the parameters that are specified in an object calling statement, such as <code>CALLNAT</code>, <code>PERFORM</code>, <code>INPUT USING MAP</code>, <code>PROCESS PAGE USING</code>, <code>helproutine</code> calls. Also, the OPTIONAL feature of the <code>DEFINE DATA PARAMETER</code> statement is considered in the parameter check.</p> <p>The parameter check is based on a comparison of the parameters of the calling statement with the <code>DEFINE DATA PARAMETER</code> definitions for the object to be called.</p> <p>It requires that</p> <ul style="list-style-type: none">■ the name of the object to be called is defined as an alphanumeric constant (not as an alphanumeric variable),■ the object to be called is available as a cataloged object. <p>Otherwise, <code>PCHECK=ON</code> will have no effect.</p> <p>Problems in Using the <code>CATALL</code> Command with <code>PCHECK=ON</code></p> <p>When a <code>CATALL</code> command is used in conjunction with <code>PCHECK=ON</code>, you should consider the following:</p> <p>If a <code>CATALL</code> process is invoked, the order in which the programming objects are compiled depends primarily on the type of the object and secondarily on the alphabetical name of the object. The object type sequence used is: <code>DDMs</code>, <code>GDA</code>s, <code>LDA</code>s, <code>PDA</code>s, classes, maps, external subroutines, subprograms, functions, adapters, <code>helproutines</code>, programs. Within objects of the same type, the alphabetical order of the name determines the sequence in which they are cataloged.</p>
--------------------------	----	--

		<p>As mentioned above, the parameters of the object calling statement are checked against the compiled form of the called object. If the calling object (the one which is being compiled and includes the object calling statement) is cataloged before the invoked object, the PCHECK result may be wrong if the parameters in the object calling statement and in the called object were changed. In this case, the new object image of the called object has not yet been produced by the CATAL command.</p> <p>This causes the <i>new</i> parameter layout in the object calling statement to be compared with the <i>old</i> parameter layout of the DEFINE DATA PARAMETER statement of the called subprogram.</p> <p>Solution:</p> <ul style="list-style-type: none"> ■ Set compiler option PCHECK to OFF. ■ Perform a general compile with CATAL on the complete library, or if just one or a few objects were changed, perform a separate compile on these objects. ■ Set compiler option PCHECK=ON. ■ On the complete library, perform a general compile with the function CHECK of system command CATAL enabled.
	OFF	No parameter check is performed.
Default setting	OFF	
Dynamic specification	yes	
Specification within session	yes	
Applicable statements	OPTIONS	
Applicable command	PCHECK	Option of system command COMPOPT

144

PD - Size of Page Dataset

This Natural profile and session parameter specifies the maximum number of pages (screens) which can be stored at the same time in the Natural system file (FUSER) with the screen-paging utility.

Within a Natural session, the profile parameter PD can be overridden by the session parameter PD.

Possible settings	0 or 1 - 255	Maximum number of pages (screens).
Default setting	50	
Dynamic specification	yes	
Specification within session	yes	
Applicable statements	SET GLOBALS	
Applicable command	GLOBALS	



Notes:

1. If the number of stored screens exceeds the setting of PD, wrap-around technique is used for the system file, which means that the oldest page is overwritten.
2. For further information on the screen page utility, see the terminal commands %E, %I, %O, %P and %S.

145

PM - Print Mode

- Profile Parameter PM 328
- Session Parameter PM 328

The following topics are covered below:

Profile Parameter PM

The Natural profile parameter PM specifies how fields are to be printed or displayed.



Notes:

1. PM=I affects any system controlled output screen items, that is, system variables and PF key lines. Moreover, all non-alphanumeric fields, for example, numeric and date are affected. In addition, for Natural Web I/O Interface terminals the field sequence is changed from left to right into right to left. The field inversion routine is supplied as assembler module NATPM in the Natural source library and can be modified in case of need.
2. For detailed information on how to use the setting PM=I, see *Bidirectional Language Support* in the *Unicode and Code Page Support* documentation.

Possible settings	I	The default screen direction when running programs is right-to-left.
	R	The default screen direction when running programs is left-to-right.
Default setting	R	
Dynamic specification	yes	
Specification within session	yes	
Application programming interface	USR1005N	See SYSEXT - <i>Natural Application Programming Interfaces</i> in the <i>Utilities</i> documentation.

Session Parameter PM

This session parameter PM is used to indicate how fields are to be displayed.

Possible settings	PM=I	The field direction is reversed.
	PM=N	The field is ignored (that is, not printed) for hardcopy output.
Default setting	none	The default field direction is used and it is regarded for hardcopy output.
Applicable statements	COMPRESS DEFINE DATA DISPLAY FORMAT INPUT	

	MOVE PRINT WRITE	
--	------------------------	--

For detailed information on how to use the setting $PM=I$, see *Bidirectional Language Support* in the *Unicode and Code Page Support* documentation.

146 PRGPAR - Data to be Passed to Program Receiving

Control at Termination

This Natural profile parameter specifies data to be passed to the program that receives control when Natural terminates (see also profile parameter [PROGRAM](#)).

Possible settings	any valid character string	Data to be passed.
Default setting	blank	No data is passed.
Dynamic specification	no	
Specification within session	no	

147 PROGRAM - Non-Natural Program Receiving Control after Termination

This Natural profile parameter specifies the non-Natural program which is to receive control after the termination of the Natural session.

Possible settings	1 - 12 characters	Non-Natural program
Default setting	none	
Dynamic specification	yes	
Specification within session	no	
Application programming interface	USR6204N (for all platforms)	See <i>SYSEXT - Natural Application Programming Interfaces in the Utilities</i> documentation.



Note: Data for the program specified with the profile parameter PROGRAM can be supplied with the TERMINATE statement.

148

PROX - Specify URL of Proxy Server

This Natural profile parameter specifies the Uniform Resource Locator (URL) of the (Intranet) proxy server through which all requests have to be routed (optional).

Possible settings	URL of proxy server
Default setting	none
Dynamic specification	no
Specification within session	no

149

PROXPORT - Specify Port Number of Proxy

This Natural profile parameter specifies the port number of the proxy, if any is set.

Possible settings	4 characters at maximum	Port number of proxy.
Default setting	80	
Dynamic specification	no	
Specification within session	no	

150

PS - Page Size for Natural Reports

This Natural profile and session parameter specifies the maximum number of lines per page to be used for Natural reports created with the `DISPLAY` or `WRITE` statement.

Possible settings	1 - 250	Maximum number of lines per page.
	0	The physical page size is to be used. Note: <ol style="list-style-type: none">1. If PS=0 is specified for the first report to be output (Report 0), the physical-device page-size minus 1 will be used.2. If PS=0 is specified for Reports 1 - 31, this will cause automatic new-page processing to be inhibited, that is, no automatic page-break processing will be performed.
Default setting	0	
Dynamic specification	yes	
Specification within session	yes	
Applicable statements	DISPLAY FORMAT INPUT SET GLOBALS WRITE	
Applicable command	GLOBALS	
Application programming interface	USR1005N	See <i>SYSEXT - Natural Application Programming Interfaces in the Utilities</i> documentation.



Notes:

1. When used as a profile parameter, the PS parameter is honored in batch mode only and defines the physical page size.
2. In online mode, the physical page size is always set to the physical screen height.
3. See also *Page Size - PS Parameter* in the *Programming Guide*.
4. Under Natural Security, the setting of this parameter can be overridden by the Session Parameters option of the Library Profile.

151 PSIGNF - Internal Representation of Positive Sign of Packed Numbers

This Natural profile parameter can be used to define the internal representation of the positive sign of packed numbers.

Possible settings	ON	The positive sign of a packed number is represented internally as H'F'.
	OFF	The positive sign of a packed number is represented internally as H'C'.
Default setting	OFF	
Dynamic specification	yes	
Specification within session	yes	
Applicable statements	OPTIONS	
Applicable command	PSIGNF	Option of system command COMPOPT

152

RCFIND - Handling of Response Code 113 for FIND

Statement

This Natural profile parameter specifies the action to be taken if Adabas Response Code 113 (requested ISN not found) is returned during the execution of a `FIND` statement processing loop.

Possible settings	ON	Response Code 113 causes the program to be terminated.
	OFF	Response Code 113 will be ignored, and processing of the <code>FIND</code> loop will continue by reading the next record.
Default setting	ON	
Dynamic specification	yes	
Specification within session	no	

153

RCGET - Handling of Response Code 113 for GET

Statement

This Natural profile parameter specifies the action to be taken if Adabas Response Code 113 (requested ISN not found) is returned during the execution of a GET statement.

Possible settings	ON	Response Code 113 causes the program to be terminated.
	OFF	Response Code 113 will be ignored, the system variable *ISN will be set to 0, and processing will continue.
Default setting	ON	
Dynamic specification	yes	
Specification within session	no	

154

RDS - Define Remote Directory Server

This Natural profile parameter allows you to define up to 10 remote directory servers in a Natural RPC environment. For each remote directory server, you specify up to 5 subparameters.

Possible settings	See <i>RDS Parameter Syntax</i> .	
Default setting	none	Subparameter defaults, see <i>RDS Parameter Syntax</i> .
Dynamic specification	yes	
Specification within session	no	



Notes:

1. RDS is specified on the client side only.
2. For information on Natural RPC, see the *Natural Remote Procedure Call (RPC)* documentation.

RDS Parameter Syntax

The parameter syntax is as follows:

Using 1 server:

```
RDS=(server-name,server-node-name,subprogram,logon-indicator,transport-protocol-name)
```

Using 2-10 servers:

RDS=((*server-name,server-node-name,subprogram,logon-indicator,transport-protocol-name*)(*server-name,server-node-name,subprogram,logon-indicator,transport-protocol-name*)...(*server-name,server-node-name,subprogram,logon-indicator,transport-protocol-name*))

Where:

Syntax Element	Value	Explanation
<i>server-name</i>	1 - 8 characters	The server name. There is no default, the value must be specified.
<i>server-node-name</i>	1 - 8 characters	The server node name. There is no default, the value must be specified.
<i>subprogram</i>	1 - 8 characters	The name of the subprogram titled CALLNAT, which is to be used as an interface. The default name is RDSSCDIR.
<i>logon-indicator</i>	L	The client initiates a Natural logon to the server with the library name of the current library on the client. On Windows platforms: Instead of specifying L, check the selection box.
	(blank)	Blank means that no server logon will be executed. If nothing is specified, this is the default.
<i>transport-protocol-name</i>	ACI	The name of the transport protocol to be used. ACI is the only possible value and the default.

155

RECAT - Dynamic Recataloging

This Natural profile parameter specifies the action to be taken if Natural detects an inconsistency in the global data area definition as defined in the program currently being executed; that is, the global data area in the program does not correspond to the definition of the global data area currently in use.



Important: This profile parameter only applies to Natural objects of Version 2.3 and above.

Possible settings	ON	Natural issues an error message and disables the system commands CATALOG, PURGE and SAVE. Note: 1. If the RECAT parameter has been set to ON, and an object exists in both source and cataloged form, then the source and the cataloged object cannot be processed independently. In order to ensure consistency between the source and the cataloged object, Natural disables the system command CATALOG (also when invoked via CATALL). In addition, the system commands PURGE and SAVE are disabled for a source for which a corresponding cataloged object exists. 2. Only objects satisfying the criteria for a particular command (such as PURGE) will be displayed in the corresponding selection box.
	OFF	Natural issues an error message.
Default setting	OFF	
Dynamic specification	yes	
Specification within session	no	
Application programming interface	USR1005N	See SYSEXT - <i>Natural Application Programming Interfaces</i> in the <i>Utilities</i> documentation.

156

REINP - Issue Internal REINPUT Statement for Invalid

Data

This Natural profile and session parameter can be used to prevent an internal REINPUT for invalid data.

Possible settings	ON	An internal REINPUT statement is issued when invalid data have been entered.
	OFF	An internal REINPUT statement is not issued when invalid data have been entered.
Default setting	ON	
Dynamic specification	yes	
Specification within session	yes	
Applicable statements	SET GLOBALS	
Applicable command	GLOBALS	
Application programming interface	USR1005N	See <i>SYSEXT - Natural Application Programming Interfaces</i> in the <i>Utilities</i> documentation.



Notes:

1. By default, Natural automatically issues an internal REINPUT statement if invalid data have been entered in response to an INPUT statement. With this parameter, you can switch this mechanism off. This will allow you to handle such input errors yourself in your application.
2. Within a Natural session, the profile parameter REINP can be overridden by the session parameter REINP.

157

ROSY - Read-Only Access to System Files

This Natural profile parameter disables modifications on the Natural system files [FDDM](#), [FNAT](#), [FUSER](#), [FDIC*](#) and [FSEC*](#).

* Not supported on this platform.

Possible settings	ON	No data can be written to, modified on or deleted from the system files. Natural issues an error message instead of performing any action that would modify any of these system files.
	OFF	Data can be written to, modified on and deleted from the system files.
Default setting	OFF	
Dynamic specification	yes	
Specification within session	no	

158

RPCSDIR - Library for Service Directory

This Natural profile parameter specifies the name of the Natural library (or one of its steplibs) used by the RPC client at runtime.

Possible settings	1 - 8 characters	Valid Natural library name.
Default setting	none	
Dynamic specification	yes	
Specification within session	no	



Notes:

1. The parameter `RPCSDIR` is specified on the client side only.
2. It is evaluated by the `SYSRPC` utility functions Service Directory Maintenance and Server Command Execution.
3. For information on Natural RPC, see the *Natural Remote Procedure Call (RPC)* documentation.

159

RTINT - Allow Runtime Interrupt

This Natural profile parameter determines whether it should be allowed to interrupt a running Natural application that does not respond anymore by using the interrupt key combination of the operating system (typically CTRL+C).

Possible settings	ON	Interrupts are allowed.
	OFF	Interrupts are not allowed.
Default setting	OFF	
Dynamic specification	yes	
Specification within session	no	



Note: For further information, see *Interrupting a Running Natural Application* in the *Programming Guide*.

160

RQTOUT – REQUEST DOCUMENT Timeout

This Natural profile and session parameter specifies the timeouts used for HTTP requests issued internally by the `REQUEST DOCUMENT` statement. If this time is exceeded, the request (connect, data send or data receive) will be terminated with a corresponding error message.

Possible settings	0 or 1 - 65535	Seconds. A value of zero implies no timeout.
Default setting	0	
Dynamic specification	yes	
Specification within session	yes	The setting of this parameter can be changed using the <code>GLOBALS</code> system command.



Note: This parameter is not available on mainframe platforms.

161

SA - Sound Terminal Alarm

This Natural profile and session parameter specifies whether the terminal alarm feature is to be used.

Possible settings	ON	The terminal alarm sound is output each time the user is prompted for input by Natural.
	OFF	No terminal alarm is used for input prompting, however, the alarm may still be activated with the <i>ALARM Option</i> of the REINPUT statement.
Default setting	OFF	
Dynamic specification	yes	
Specification within session	yes	
Applicable statements	SET GLOBALS	
Applicable command	GLOBALS	
Application programming interface	USR1005N	See SYSEXT - <i>Natural Application Programming Interfaces</i> in the <i>Utilities</i> documentation.



Note: Within a Natural session, the profile parameter SA can be overridden by the session parameter SA.

162

SB - Selection Box

- Syntactical Considerations 364
- Runtime Considerations 365

Selection boxes in an `INPUT` statement are available on mainframe computers only. For other platforms, selection boxes may be defined in the map editor only.

Selection boxes can be attached to input fields. They are a comfortable alternative to help routines attached to fields, since you can code a selection box direct in your program. You do not need an extra program as with help routines.

You may define a selection box clause for every `INPUT` variable of type alpha, regardless if this field is an input or output field, or both.

The syntax is:

```
SB=operand1 [,operand1]...
```

where *operand1* represents a value operand which is used to fill up the selection box with items.

Operand	Possible Structure	Possible Formats	Referencing Permitted	Dynamic Definition
<i>operand1</i>	C S A	A	yes	no

With `SB`, you specify the values to be displayed within the selection box.

To assign a selection box to a field, specify the attribute `SB` for an alpha `INPUT` field in your Natural program using the following example syntax:

```
INPUT #FLD (SB='value1', #ITEM1, #ITEM2(1:3), #ITEM3(*))
```

The following topics are covered below:

Syntactical Considerations

It is possible to assign both a selection box and a help routine to a field.

Selection boxes can be defined for every variable field in an `INPUT` statement. Exceptions are the following:

System Variables	For example: <code>*PROGRAM</code> , <code>*COM</code>
Named Constants (mainframe only)	defined with a <code>CONST</code> clause of <code>DEFINE DATA</code> statement.

In addition to the `SB` attribute, other attributes can be defined as well, for example: `AD` or `CD`.

The selection box field does not have to be modifiable, as is the case with `AD=A` or `AD=M`. In other words, it is possible to provide a selection box (and select values) even for a write-protected output

field, such as `AD=0`. If you use `AD=0`, the user is forced to choose from a set of predefined values, which themselves appear in a selection box.

Runtime Considerations

Selection Box Position

When a program containing a selection box is executed, the selection box is positioned on the screen according to the same positioning algorithm used for help windows; that is, the size and position of the selection box are determined automatically, “near” the field.

Selection Box Attributes

The color and intensified attributes assigned to the field are also applied to the values displayed in the corresponding selection box.

Edit Masks in Selection Boxes

If an edit mask has been defined for the field, the edit mask is applied to all selection box values.

To define an edit mask for a field:

Using the `INPUT` statement, you can define an edit mask for a field. This is demonstrated in following code example.

```
DEFINE DATA  
LOCAL  
1 A(A4)  
END-DEFINE  
MOVE 'ABCD' TO A  
*  
SET KEY PF1 = HELP  
FORMAT KD=ON  
*  
INPUT A (AD=M EM=X.X.X.X SB='1234','WXYZ')  
WRITE A  
END
```

Selection Box Line Sizes

The line size of the selection box matches the field length to which the box corresponds.

If a value intended for the selection box exceeds the line size of the selection box, the value is truncated.

Sequence of Selection Box Values

Selection box values are displayed in the order they appear in the SB attribute.

163

SD - Time Delay between Two Screens

This Natural profile parameter can be used to delay the time related to screen output display. This is the time delay between two screens during a non-conversational write operation (see the Natural terminal command %N).

Possible settings	1 - 100	The unit for the specified setting is a tenth of a second, which means that SD=10 leads to a delay of one second.
	0	
Default setting	0	
Dynamic specification	no	
Specification within session	no	

164

SERVER - Start Natural Session as an RPC Server

Session

This Natural profile parameter specifies whether or not the Natural session will be started as an RPC server session.

Possible settings	ON	The Natural session will be started as an RPC server session.
	OFF	The Natural session will not be started as an RPC server session.
Default setting	OFF	
Dynamic specification	yes	
Specification within session	no	



Notes:

1. SERVER can be specified on both the client and the server side.
2. For information on Natural RPC, see the *Natural Remote Procedure Call (RPC)* documentation.

165 SF - Spacing Factor

This Natural profile and session parameter specifies the default number of spaces to be inserted between field settings of columns on Natural reports created using a `DISPLAY` statement.

Possible settings	1 - 30	Number of spaces. Note: The SF parameter cannot be set to 0; that is, at least one blank character must be placed between report columns.
Default setting	1	
Dynamic specification	yes	
Specification within session	yes	
Applicable statements	SET GLOBALS	
Applicable command	GLOBALS	
Application programming interface	USR1005N	See <i>SYSEXT - Natural Application Programming Interfaces</i> in the <i>Utilities</i> documentation.



Notes:

1. Within a Natural session, the profile parameter SF can be overridden by the session parameter SF.
2. Under Natural Security, the setting of this parameter can be overridden by the *Session Parameters* option of the Library Profile.
3. See also *Column Spacing - SF Parameter and nX Notation* in the *Programming Guide*.

166

SG - Sign Position

This session parameter determines whether or not a sign position is to be allocated for a numeric field.

Possible settings	ON	A sign position will be allocated.
	OFF	No sign position will be allocated. Note: 1. SG=OFF causes numeric fields with negative values to be output without a minus (-) sign. 2. SG=OFF does not prevent you from entering negative values in input fields.
Default setting	ON	
Specification within session	yes	
Applicable statements	DISPLAY FORMAT INPUT PRINT WRITE	
Applicable command	none	



Notes:

1. If the **EM** (edit mode) parameter is specified, it overrides the **SG** parameter.
2. See also *Parameters to Influence the Output of Fields* in the *Programming Guide*.

Example:

```
FORMAT SG=OFF
```


167

SHELL - Grant Shell Access to Natural User

This Natural profile parameter can only be set by Natural administrators. This parameter allows or disallows the shell exit from the Natural Main Menu for specific users.



Caution: Be careful when granting shell access to a Natural user. This might introduce security problems, because the user would then be able to use the underlying features of the operating system.

Possible settings	YES	Shell exit is allowed. If the shell exit is allowed for a user, the name of the shell that will be started for this user can be specified by the administrator. Note: This shell name must be the name of an executable DCL program, for example: <i>SPAWN</i> .
	NO	Shell exit is not allowed.
Default setting	NO	
Dynamic specification	no	
Specification within session	no	

168

SSLPRX - Specify URL of SSL Proxy Server

This Natural profile parameter specifies the Uniform Resource Locator (URL) of the (intranet) SSL proxy server through which all requests have to be routed (optional).

Possible settings	<i>url</i>	URL of SSL proxy server
Default setting	none	
Dynamic specification	no	
Specification within session	no	

169

SSLPRXPT - Specify Port Number of SSL Proxy

This Natural profile parameter specifies the port number of the proxy, if any is set.

Possible settings	<i>nnnn</i>	Port number of proxy, 4 characters at maximum.
Default setting	443	
Dynamic specification	no	
Specification within session	no	

170

SM - Programming in Structured Mode

This Natural profile and session parameter specifies whether or not structured mode must be used.

Possible settings	ON	Forces the use of structured mode syntax.
	OFF	Programming can be done in either structured mode or reporting mode.
Default setting	OFF	
Dynamic specification	yes	
Specification within session	yes	
Applicable statements	none	
Applicable command	GLOBALS	
Application programming interface	USR1005N	See <i>SYSEXT - Natural Application Programming Interfaces</i> in the <i>Utilities</i> documentation.



Notes:

1. If structured mode (SM=ON) is specified by profile parameter SM, an attempt to change this setting with system command GLOBALS and session parameter SM will be rejected (Reporting mode not permitted).
2. Within a Natural session, the profile parameter setting SM=OFF can be overridden by the session parameter SM=ON.
3. Under Natural Security, the setting of the mode option in the library's security profile determines whether the SM profile parameter can be used; see also *Programming mode* in the *Natural Security* documentation.
4. Under Natural Security, this parameter may be disabled by Natural Security to the effect that structured mode is invariably in effect for a given library.

171

SNAT - Sound a Bell at Syntax Error

This Natural profile parameter is used to sound a bell when the compiler detects a syntax error in a Natural program.

Possible settings	ON	A bell will sound when a syntax error is encountered.
	OFF	No bell will sound in the case of syntax errors.
Default setting	OFF	
Dynamic specification	no	
Specification within session	no	

172

SORTSIZE - Size of Sort Buffer

This Natural profile parameter specifies the amount of storage to be reserved for use by the SORT program.

Possible settings	500 - 2048	Buffer size in KB.
Default setting	500	
Dynamic specification	yes	
Specification within session	no	



Notes:

1. This sort buffer is only allocated when executing a Natural program which contains a SORT statement.
2. Increasing the buffer size setting leads to faster SORT processing, in particular when all data to be sorted fit into the sort buffer.

173

SRETAIN - Retain Source Format

This Natural profile parameter specifies that all existing sources have to be saved in their original encoding format.

Possible settings	ON	The original code page of an existing Natural source is retained. If the profile parameter <code>SUTF8</code> is defined as well, new sources will be saved in UTF-8 format.
	OFF	For existing Natural sources with format UTF-8 the encoding will not be changed. Existing sources with other encodings will be saved using the current code page.
Default setting	ON	
Dynamic specification	yes	
Specification within session	no	



Notes:

1. This parameter only takes effect if sources are edited in a Natural Single Point of Development environment, because otherwise sources which have an encoding that is different from the current code page cannot be opened anyway.
2. When new sources are created, they will be saved either in the current code page format or in UTF-8 format, depending on the setting of profile parameter `SUTF8`. This is independent of the setting of `SRETAIN`.
3. If a source can not be saved in the target code page format, because this code page does not define all characters contained in the source, a message is displayed which allows the user to choose whether he/she wants to remove the problematic characters or cancel the save process.
4. See also *Profile Parameters in the Unicode and Code Page Support* documentation.

174

SRVCMIT - Server Commit Time

This Natural profile parameter specifies the time at which a Natural RPC server automatically commits an RPC conversation or a non-conversational RPC request.

Possible settings	B	The Natural RPC server automatically commits a database transaction before the reply is sent to the client. Note: If the reply fails, the database transaction is already committed.
	A	The Natural RPC server automatically commits a database transaction after the reply has been successfully sent to the client. Note: If the reply fails, the database transaction is rolled back.
Default setting	B	
Dynamic specification	yes	
Specification within session	no	



Notes:

1. SRVCMIT is specified on the server side only.
2. This parameter is only evaluated if the profile parameter `ETEOP` is set to ON.
3. For information on Natural RPC, see the *Natural Remote Procedure Call (RPC)* documentation.

175

SRVNAME - Name of RPC Server

This Natural profile parameter specifies the name of the RPC server, with which it registers on the node specified with the profile parameter [SRVNODE](#).

Possible settings	1 - 192 characters	<p>Valid server name.</p> <p>You may either specify a physical server name of up to 32 characters or a logical service name of up to 192 characters. In case of a logical service name, an asterisk (*) must be specified with the SRVNODE parameter (intentionally left empty).</p> <p>In case of an EntireX Broker node, the value of SRVNAME corresponds to the value of the SERVER attribute of a service entry in the broker attribute file, as shown below:</p> <pre>CLASS=RPC, SERVICE=CALLNAT, SERVER=<i>srvname</i></pre> <p>Example:</p> <pre>SRVNAME='PRODUCTION_SERVER' /* physical ↵ server name */ SRVNAME='MY_LOGICAL_SERVICE,MY_SET' /* logical ↵ server name */</pre>
Default setting	none	
Dynamic specification	yes	
Specification within session	no	



Notes:

1. SRVNAME is specified on the server side only.

2. For information on Location Transparency and logical service names, refer to the EntireX documentation.
3. For information on Natural RPC, see the *Natural Remote Procedure Call (RPC)* documentation.

176

SRVNODE - Name of Node

This Natural profile parameter specifies the name of the node upon which an RPC server registers.

Possible settings	1 - 192 characters	<p>Node name.</p> <p>You may either specify a physical node name of up to 32 characters, a logical node name of up to 192 characters or an asterisk (*) (intentionally left empty) to indicate that the parameter <code>SRVNAME</code> contains a logical service name.</p> <p>In case of an EntireX Broker node, a physical node name may refer to an Entire Net-Work node or to an TCP/IP address. Note that the broker stub in use must support the naming notation. For details about the structure of node names and their support by the broker stubs, refer to the EntireX documentation.</p> <p>See <i>Examples</i>.</p>
Default setting	none	
Dynamic specification	yes	
Specification within session	no	



Notes:

1. SRVNODE is specified on the server side only.
2. For information on Location Transparency and logical node names, refer to the EntireX documentation.
3. For information on Natural RPC, see the *Natural Remote Procedure Call (RPC)* documentation.

Examples

The examples below are based on the EntireX notation.

```
SRVNODE=ETB001 /* Entire Net-Work node */
SRVNODE=PCBROKER /* host name for a TCP/IP address */
SRVNODE='157.189.160.95:1958:TCP' /* TCP/IP address with port number */
SRVNODE='tcpip://host.com:1958' /* host name for a TCP/IP address ↵
with port number */
SRVNODE='LOGBROKER=MY_LOGICAL_NODE,MY_SET' /* logical node name */
SRVNODE='*' /* logical service name in SRVNAME */
```



Notes:

1. If a host name is used for the TCP/IP address, the name must either be known to your DNS server or it must be defined in the hosts file of your TCP/IP configuration.
2. If the port number is omitted, either a default port number is used by the EntireX broker stub or a host name must be used, and the host name must be known to your DNS server or must be defined in the services file of your TCP/IP configuration.

177

SRVTRTY - Number of Connect/Reconnect Attempts

This Natural profile parameter specifies the number of attempts for an RPC server to connect/reconnect (REGISTER) to an EntireX Broker that is not active, and the wait time between two successive attempts.

Possible settings	See <i>SRVTRTY Parameter Syntax</i> .	
Default setting	0,60	No attempts.
Dynamic specification	yes	
Specification within session	no	



Note: SRVTRTY is specified on the server side only.

SRVTRTY Parameter Syntax

The SRVTRTY parameter syntax is as follows:

```
SRVTRTY=(attempts,wait-time)
```

Or:

```
SRVTRTY=attempts
```



Note: If only a value for *attempts* is specified, the parentheses may be omitted.

Where:

Syntax Element	Value	Explanation
<i>attempts</i>	0 or 1 - 2147483647	<p>Number of attempts to connect/reconnect to an EntireX Broker that is not active (EntireX Broker message 02150148).</p> <p>Note:</p> <ol style="list-style-type: none"> 1. The specification of <i>attempts</i> enables you to start a Natural RPC server before the required EntireX Broker has been started and to shutdown an EntireX Broker temporarily without implicitly terminating all Natural RPC servers. 2. If the EntireX Broker is still not active after the number of attempts specified in <i>attempts</i> or if <i>attempts</i> is zero, the RPC server terminates.
<i>wait-time</i>	0 or 1 - 3600	Wait time in seconds between two successive attempts.

Examples

1. `RPC=(SRVRTRY=(20,10))`

Or:

`NTRPC SRVRTRY=(20,10)`

20 attempts with a wait time of 10 seconds between two successive attempts.

2. `RPC=(SRVRTRY=500)`

Or:

`NTRPC SRVRTRY=500`

500 attempts with a wait time of 60 seconds between two successive attempts.



Note: For further information, see the *Natural Remote Procedure Call (RPC)* documentation, and especially *Considerations for Mainframe Natural RPC Servers with Replicas*.

178

SRVTERM - Server Termination Event

This Natural profile parameter specifies the event at which a Natural RPC server is automatically terminated.

Possible settings	NEVER	A Natural RPC server is never automatically terminated. Note: To terminate a Natural RPC server, refer to <i>Terminating a Natural RPC Server</i> and <i>Terminating an EntireX Broker Service</i> in the <i>Natural Remote Procedure Call (RPC)</i> documentation.
	TIMEOUT	A Natural RPC server is automatically terminated if the wait time for the next client request outside of an RPC conversation is exceeded. Note: TIMEOUT should only be set if you use an Attach Manager to dynamically start Natural RPC servers on request.
Default setting	NEVER	
Dynamic specification	yes	
Specification within session	no	



Notes:

1. SRVTERM is specified on the server side only.
2. For information on Natural RPC, see the *Natural Remote Procedure Call (RPC)* documentation.

179

SRVUSER - User ID for RPC Server Registry

This Natural profile parameter specifies the user ID needed to register a Natural RPC server on the node specified with the profile parameter [SVRNODE](#).



Note: In case of an EntireX Broker node, SRVUSER is also used to logon to the EntireX Broker. A password is either taken from Natural Security (see *NSC below) or specified via the application programming interface USR2072N.

Possible settings	<i>user-ID</i>	Valid user ID. 1 to16 characters.
	*USER	If SRVUSER is set to *USER, the Natural server uses the current Natural user ID (see system variable *USER) to logon to the node.
	*NSC	If SRVUSER is set to *NSC and Natural Security is installed, the Natural server uses the current Natural user ID (see system variable *USER) and the password defined for this user ID in Natural Security to logon to the node.
Default setting	<i>timestamp</i>	If the user ID is omitted, the timestamp will be used.
Dynamic specification	yes	
Specification within session	no	



Notes:

1. SRVUSER is specified on the server side only.
2. For information on Natural RPC, see the *Natural Remote Procedure Call (RPC)* documentation.

180

SRVWAIT - Wait Time of RPC Server

This Natural profile parameter specifies the number of seconds the server is to wait for a Natural RPC client request.

Possible settings	0 or 1 - 32767	Wait time in seconds. Note: <ol style="list-style-type: none">1. If this time is exceeded, the RPC server is informed by the node to which the RPC server has registered. The RPC server writes a corresponding message to the Natural RPC server trace file, and continues to wait for an RPC client request.2. If TCP/IP is used to communicate with the node, a non-zero value will also avoid an indefinite wait in TCP/IP if the node cannot respond for any reason.
Default setting	0	Unlimited wait time. Note: In case of an EntireX Broker node, the wait time is set to the SERVER-NONACT value of the corresponding Entirex Broker attribute file.
Dynamic specification	yes	
Specification within session	no	

181

SSIZE - Size of Source Area Allocated by the Editors

This Natural profile parameter determines the maximum size of the Natural source area, which will be dynamically allocated by the Natural editors.

Possible settings	1 - 100	Maximum size of the Natural source area in MB.
Default setting	1	
Dynamic specification	no	
Specification within session	no	



Note: The maximum size for one Natural source member is 1 MB (independent of SSIZE).

182

STACK - Place Data/Commands on the Stack

This Natural profile parameter is used to place data/commands on the Natural stack.



Note:

The profile parameter `STACK` is used to place data/commands on the Natural command stack.

Possible settings	any character string
Default setting	none
Dynamic specification	yes
Specification within session	no



Notes:

1. The amount of data to be passed with this parameter is limited to 512 bytes. If this limit is exceeded, a corresponding error message is returned.
2. The stack can contain a sequence of Natural commands and/or user-specified commands, together with their data, for execution at the beginning of the Natural session. The command stack is processed before the user is prompted for input on the screen.
3. If an `INPUT` statement is encountered during stack processing, the corresponding input screen is generated only if the required input data were not supplied with the command when the stack was created. Any reports generated during stack processing are displayed as usual.
4. Each system or user-defined command can be optionally followed by data which are used to satisfy requests for information required during the processing of the command. If the command is a user command (that is the name of a user program), any data provided resolve the data requirements of `INPUT` statements within the user program.

Conventions:

- Multiple settings for one `INPUT` statement are separated by a comma.

- Data for multiple INPUT statements are separated by a colon (:).
- A semicolon (;) is used to delimit multiple commands.

Examples:

```
LOGON:USER1;UCMD1 A,B;UCMD2 C,D:E;FIN
```

Logs on to the library USER1, executes the commands UCMD1 and UCMD2 providing the corresponding input data, and ends the Natural session.

```
CMD DATA:DATA;CMD
```

Places commands and data on stack. Since some commands (for example, GLOBALS) do not read parameters by INPUT, a blank character should be used rather than a colon to delimit a command from the first parameter data element.

If specified dynamically, the character string provided as data for the STACK parameter must be enclosed in apostrophes; if the character string contains multiple commands, it must also be enclosed in parentheses, for example:

```
STACK="(LOGON SYSTEM;UCMND)"
```

Logs on to the library SYSTEM and executes the command UCMND.

183

STARTUP - Program Name for System Variable

*STARTUP

This Natural profile parameter specifies a program name for the Natural system variable *STARTUP.

Possible settings	1 - 8 characters	Valid program name.
Default setting	none	
Dynamic specification	no	
Specification within session	no	



Notes:

1. The program whose name is contained in *STARTUP is executed each time the Natural command line is invoked. In a Natural program, you can assign another program name to *STARTUP.
2. If you have Natural Security installed, STARTUP is not evaluated; the startup program to be used is read from the library profile defined in Natural Security.

184

STEPLIB - Initial Setting for *STEPLIB System Variable

This Natural profile parameter specifies the initial setting for the system variable *STEPLIB.

Possible settings	1 - 8 characters	Any valid library name.
Default setting	SYSTEM	
Dynamic specification	yes	
Specification within session	no	
Application programming interface	USR1005N	See SYSEXT - <i>Natural Application Programming Interfaces</i> in the <i>Utilities</i> documentation.



Notes:

1. The content of the system variable *STEPLIB influences the order in which objects are searched in the system file.
2. Using the Configuration Utility, you can define additional steplibs that can be searched for objects which cannot be found in the current library. See *Steplibs* in the *Configuration Utility* documentation.
3. See also *Steplibs* and *Search Sequence for Object Execution* in the *Using Natural* documentation.

185

SUBCHAR - Substitution Character for Default Code

Page

This Natural profile parameter allows you to specify the substitution character for the default code page. The substitution character is automatically inserted whenever the conversion of a Unicode character into the current default code page (see profile parameter [CP](#)) fails and the profile parameter [CPCVERR](#) is set to `OFF`.

Possible settings	<i>n</i>	Substitution character.
	<code>OFF</code>	If <code>OFF</code> is specified, the ICU default substitution character is used. Note: For further information, see also <i>Profile Parameters in the Unicode and Code Page Support</i> documentation.
Default setting	<code>OFF</code>	
Dynamic specification	<code>no</code>	
Specification within session	<code>no</code>	

186

SUTF8 - UTF-8 Format for Sources

This Natural profile parameter specifies the default format to be used when Natural sources are saved.



Note: This profile parameter is valid only for Natural Development Server sessions; it will be ignored in a native Natural for OpenVMS session.

Possible settings	ON	The default format for saving Natural sources is UTF-8. Note: 1. All sources will be saved in UTF-8 format, which assures that the source content does not depend on the installed system code page. 2. If the profile parameter SRETAIN is also set to ON, only newly created sources will be saved in UTF-8 format. Existing sources will then be saved in the original encoding, if possible.
	OFF	The default format for saving Natural sources is "code page".
Default setting	OFF	
Dynamic specification	no	
Specification within session	no	



Note: See also *Profile Parameters in the Unicode and Code Page Support* documentation.

187

SYMGEN - Generate Symbol Table

This Natural profile and session parameter specifies whether a symbol table is to be generated or not.

Possible settings	ON	A symbol table will be generated.
	OFF	No symbol table will be generated.
Default setting	OFF	
Dynamic specification	yes	
Specification within session	yes	
Applicable statements	none	
Applicable command	GLOBALS	



Notes:

1. The symbol table contains all symbols used within a Natural program (for example, variable names). It is part of the generated program and is required, for example, for the Natural Debugger and the dialog editor.
2. Within a session, the profile parameter SYMGEN can be overridden by the session parameter SYMGEN.

188

SYNERR - Control of Syntax Errors

This Natural profile parameter specifies whether or not syntax errors will be passed to the error transaction program.

Possible settings	ON	Syntax errors are passed to the error transaction program.
	OFF	Syntax errors are not passed to the error transaction program.
Default setting	OFF	
Dynamic specification	yes	
Specification within session	no	
Application programming interface	USR4007N	See <i>SYSEXT - Natural Application Programming Interfaces</i> in the <i>Utilities</i> documentation.



Notes:

1. The error transaction program is defined either with the profile parameter [ETA](#) or by a user program by way of assignment to the system variable *ERROR-TA or, if Natural Security is installed, within the Natural Security library profile; see *Components of a Library Profile* in the *Natural Security* documentation.
2. For further information, see *Using an Error Transaction Program* in the *Programming Guide*.

189 TC - Trailing Characters

With this session parameter, you can specify trailing characters that are to be displayed immediately to the right of a field output with a `DISPLAY` statement. The width of the output column is enlarged accordingly.

Possible settings	any character	Up to 10 characters may be specified.
Default setting	none	
Specification within session	yes	
Applicable statements	FORMAT	Parameter may be specified dynamically with the <code>FORMAT</code> statement.
	DISPLAY	Parameter may be specified at statement level and/or at element level.
Applicable command	none	



Notes:

1. Trailing characters may optionally be specified enclosed within apostrophes, in which case any characters can be specified. Any character string specified which contains a closing parenthesis or a quotation mark must be enclosed within apostrophes.
2. The parameter `TC` can also be used with `U` format fields. For information on Unicode format, see also *Unicode and Code Page Support in the Natural Programming Language, Session Parameters, EMU, ICU, LCU, TCU versus EM, IC, LC, TC*.
3. See also *Parameters to Influence the Output of Fields in the Programming Guide*.

Examples:

```
FORMAT TC=*  
DISPLAY (TC='*B*')
```

190

TCU - Unicode Trailing Characters

With this session parameter, you can specify trailing characters that are to be displayed immediately to the right of a field output with a `DISPLAY` statement. The width of the output column is enlarged accordingly.

Possible settings	any character	Up to 10 characters may be specified.
Default setting	none	
Specification within session	yes	
Applicable statements	<code>FORMAT</code>	Parameter may be specified dynamically with the <code>FORMAT</code> statement.
	<code>DISPLAY</code>	Parameter may be specified at statement level and/or at element level.
Applicable command	none	



Notes:

1. Trailing characters may optionally be specified enclosed within apostrophes, in which case any characters can be specified. Any character string specified which contains a closing parenthesis or a quotation mark must be enclosed within apostrophes.
2. The session parameter `TCU` is identical to the session parameter `TC`. The difference is that the trailing characters are always stored in Unicode format. This allows you to specify trailing characters with mixed characters from different code pages, and assures that always the correct character is displayed independent of the installed system code page.

See also:

- *Parameters to Influence the Output of Fields in the Programming Guide*
- *Unicode and Code Page Support in the Natural Programming Language, Session Parameters, EMU, ICU, LCU, TCU versus EM, IC, LC, TC*

191 TD - Time Differential

This Natural profile parameter specifies a time differential to be applied to the Natural time/date setting to ensure that the current local time/date is used, rather than the computer center time/date.

Possible settings	-23,59 to 23,59	The notation <i>hours,minutes</i> is used to add/subtract the specified time to/from the physical machine time to set the time/date to be used by Natural; <i>minutes</i> (if specified) must be 00-59.
Default setting	0,0	
Dynamic specification	yes	
Specification within session	no	



Note: This parameter is applicable in an environment in which remote nodes are being used in a computer network.

Examples:

```
TD=6           (6 hours ahead)
TD=-11        (11 hours behind)
TD=(5,30)     (5 hours and 30 minutes ahead)
TD=(-6,30)    (6 hours and 30 minutes behind)
```


192

TF - Translation of Database ID/File Number

This Natural profile parameter is used to translate the database ID/file number of a production database into the database ID/file number of a test database.



Caution: This parameter applies to user files only. It does not apply to system files.

Possible settings	<i>production-DBID</i>	0 - 65535, except 255, or can be an asterisk (*) which stands for all DBIDs. Note: DBID 255 is reserved for logical system files for Software AG products, see profile parameter LFILE .
	<i>production-FNR</i>	1 - 5000, or an asterisk (*) which stands for all FNRs.
	<i>test-DBID</i>	0 - 65535, except 255.
	<i>test-FNR</i>	1 - 5000
Default setting	none	
Dynamic specification	yes	This parameter can be specified dynamically and in the Natural parameter file NATPARM.
Specification within session	no	



Notes:

1. The translation of file number is relevant when developing an application in a production environment; it enables you to develop an application in a test database and then transfer the finished application to the production database without having to change or re-compile the application.
2. The transfer is done by a translation of the application's database identification (DBID) and file number (FNR): with the `TF` parameter, you specify the production DBID/FNR and the test DBID/FNR. The Natural objects are then cataloged with the production DBID/FNR, but whenever a database access is executed, the production DBID/FNR is translated into the test

DBID/FNR; that is, the test database is used. This means that testing can take place in the actual production environment, but not with production data.

3. The asterisk (*) notation for *production-DBID* and *production-FNR* is mutually exclusive.

TF Parameter Syntax

The parameter is specified as follows:

```
TF=(production-DBID,production-FNR,test-DBID,test-FNR)
```

The TF parameter can be specified several times. Existing specifications are displayed in a corresponding list box.



Notes:

1. Production and test databases must be of the same type (Adabas/Adabas, for example).
2. If the database type is not specified in NATPARM, the Adabas is used as default type; that is, SQL and XML databases must be specified explicitly.
3. For SQL and XML databases, the file number must always be set to 1. The DBID must be in the range of 0-254.
4. The profile parameter UDB (User Database ID) is evaluated before the TF parameter is evaluated.

This Natural profile parameter is used to enable or disable the use of dynamic thousands separators in edit masks at compilation time.

Possible settings	ON	Dynamic thousands separators are used. Note: Every dynamic thousands separator that is not part of a string literal is replaced at runtime with the thousands separator character defined with THSEPCH .
	OFF	Dynamic thousands separators are not used. Note: Thousands separators in the edit mask are treated as literal and displayed unchanged at runtime. This is the compatibility setting.
Default setting	OFF	
Dynamic specification	yes	
Specification within session	yes	
Applicable statements	OPTIONS	
Applicable command	THSEP	Option of system command <code>COMPOPT</code> .



Notes:

1. At runtime the dynamic thousands separators are replaced by the value (thousands separator character) of the profile and session parameter [THSEPCH](#).
2. In the Natural source, the dynamic thousands separator is either a comma (,) or a period (.), depending on the current setting of the profile and session parameter [DC](#) (decimal character). If a comma is specified, then the dynamic thousands separator is a period, otherwise it is a comma.
3. Fields in Unicode format should not be redefined as alphanumeric (A) or numeric (N) fields.

See also:

- Profile parameter [THSEPCH](#) in the *Parameter Reference*.
- *Customizing Separator Character Displays* in the *Programming Guide*.

194

THSEPCH - Thousands Separator Character

This Natural profile and session parameter is used to specify the character to be used as thousands separator at runtime. Then the thousands separator character replaces the dynamic thousands separators in edit masks.

Possible settings	any character	At runtime, the dynamic thousands separator is replaced with this character. Note: <ol style="list-style-type: none">1. If the thousands separator character is to be a comma, it must be enclosed in quotes, that is, THSEPCH=' , ' when using the dynamic parameter facility, because a comma is used to separate individual parameters.2. If the thousands separator character is to be a quote, it must be specified as two quotes enclosed in quotes, that is, THSEPCH=' ' ' ' .
Default setting	, (comma)	Note: By default, a comma is used as thousands separator.
Dynamic specification	yes	
Specification within session	yes	
Applicable statements	none	
Applicable command	GLOBALS	



Note: In the Natural source, the dynamic thousands separator is always represented by a comma (,) or a period (.).

See also:

- Profile parameter [THSEP](#) in the *Parameter Reference* documentation.
- Option THSEP of system command COMPOPT in the *System Commands* documentation.

- *Customizing Separator Character Displays in the Programming Guide.*

195

TIMEOUT - Wait Time for RPC Server Response

This Natural profile parameter specifies the number of seconds the client is to wait for an RPC server response.

Possible settings	0 -32767	Timeout in seconds. Note: If this time is exceeded, the remote procedure call will be terminated with a corresponding error message.
Default setting	55	
Dynamic specification	yes	
Specification within session	yes	At runtime, this value can be overwritten using the Parameter Maintenance function of the SYSRPC utility.



Notes:

1. TIMEOUT is specified on the client side only.
2. For information on Natural RPC, see the *Natural Remote Procedure Call (RPC)* documentation.

196

TMPSORTUNIQ - Alternate Algorithm for Generating

Sort Work File Names

If this profile parameter is specified on the Natural startup command, Natural will use a different algorithm from normal when generating work file names for sort operations. It forces Natural to generate a unique file name for any required work files without embedding the values of the `ETID` parameter and user ID into the file name.

Possible settings	specified or not specified	If this profile parameter is specified, Natural will use an algorithm different from normal when generating work file names for sort operations.
Default setting	not specified	
Dynamic specification	yes	
Specification within session	no	



Note: The normal, default algorithm creates work file names with the values of the `ETID` setting and the user ID embedded. Whereas this algorithm usually results in file names which are unique to a particular Natural session, this may cause problems in environments where the `ETID` contains characters which are invalid within a file name, or where multiple Natural sessions are running which use the same user ID and no `ETID` specification (thus possibly resulting in work file names for sort operations being created which are not unique).

197

TQ - Translate Quotation Marks

This parameter has been replaced by the Natural profile parameter [TQMARK](#).

198

TQMARK - Translate Quotation Marks

This Natural profile parameter controls the translation of a quotation mark (") within a Natural text constant. It takes effect at compilation time only.

Possible settings	ON	Each quotation mark within a text constant is output as a single apostrophe.
	OFF	Quotation marks within text constants are not translated, they are output as quotation marks.
Default setting	ON	
Dynamic specification	yes	
Specification within session	yes	
Applicable statements	OPTIONS	
Applicable command	TQMARK	Option of system command COMPOPT



Note: Do not confuse quotation mark (") with double apostrophes (' '). Double apostrophes within a text constant are always output as a single apostrophe ('), regardless of the setting of the TQMARK parameter.

Example 1 (TQMARK=ON):

```
WRITE 'THERE"S A QUOTATION MARK'
```

is displayed as: THERE'S A QUOTATION MARK

Example 2 (TQMARK=OFF):

```
WRITE 'THERE"S A QUOTATION MARK'
```

is displayed as: THERE"S A QUOTATION MARK

Example 3 (TQMARK=ON or OFF):

```
WRITE 'DOUBLE APOSTROPHES'' OUTPUT IS A SINGLE APOSTROPHE'
```

is displayed as: DOUBLE APOSTROPHES' OUTPUT IS A SINGLE APOSTROPHE

199

TRACE - Define Trace Level for Natural RPC Servers

This Natural profile parameter activates the Natural RPC trace facility and determines the trace level to be used.

Possible settings	0	Nothing is traced.
	1	Only messages (inclusive Natural errors) are traced.
	(1 , E)	Messages are traced in the event of an error only.
	2	All messages and data from/to client are traced.
	(2 , E)	Messages and data from/to client are traced in the event of an error only.
	3 - 9	The values 3 - 9 are also accepted. These values are for future use and behave like TRACE=2.
Default setting	0	
Dynamic specification	yes	
Specification within session	no	



Notes:

1. TRACE is specified on the server side only.
2. For further information, see *Using the Server Trace Facility* p.p. in the *Natural Remote Procedure Call (RPC)* documentation.
3. For information on Natural RPC, see the *Natural Remote Procedure Call (RPC)* documentation.

200

TRANSP - Server Transport Protocol

This Natural profile parameter specifies which server transport protocol is used. If ACI is used, you can additionally specify the transport method.



Note: The use of TRANSP is no longer required as you may now specify the full node name with [SRVNODE](#). It is still supported for compatibility reasons.

Possible settings	ACI	ACI is used. The transport method is defined by the EntireX Broker.
	(ACI , TCP)	ACI is used with TCP/IP.
	(ACI , NET)	ACI is used with Entire Net-work, i.e. using the Adabas protocol.
	(ACI , TCP - NET)	Trying to use ACI with TCP. If not available, ACI is used with NET.
	(ACI , NET - TCP)	Trying to use ACI with NET. If not available, ACI is used with TCP.
Default setting	ACI	
Dynamic specification	yes	
Specification within session	no	



Notes:

1. TRANSP is specified on the server side only.
2. For information on Natural RPC, see the *Natural Remote Procedure Call (RPC)* documentation.

201

TRYALT - Try Alternative Server Address

This Natural profile parameter specifies whether an RPC client should try to execute an RPC request on an alternative server or not.

Possible settings	ON	If a request could not be executed on the node you specified, the RPC client tries to find an alternative server address to send that request to.
	OFF	No such attempt will be made.
Default setting	OFF	
Dynamic specification	yes	
Specification within session	yes	At runtime, this value can be overwritten using the Parameter Maintenance function of the SYSRPC utility.



Notes:

1. TRYALT is specified on the client side only.
2. For further information, see *Specifying RPC Server Addresses* in the *Natural Remote Procedure Call (RPC)* documentation.
3. For information on Natural RPC, see the *Natural Remote Procedure Call (RPC)* documentation.

202

UC - Underlining Character

This session parameter determines the character that is used as underlining character for the following:

- column headings generated by `DISPLAY` statements;
- page titles/trailers produced by `WRITE TITLE`/`WRITE TRAILER` statements with `UNDERLINED` option.

Possible settings	any character	See also Note.
	OFF	
Default setting	-	Hyphen (-).
Specification within session	yes	
Applicable statements	DISPLAY FORMAT WRITE TITLE WRITE TRAILER	
Applicable command	none	



Note: If you do not wish column headers to be underlined, you have the following options:

UC=	A blank line will be output instead of underlining.
UC=OFF	The field values will be output immediately below the heading line, without any blank line in between. You can specify UC=OFF only at the statement level of a DISPLAY statement; in this case, you cannot make any other UC specifications for individual fields in that statement.

Examples:

```
FORMAT UC=*  
DISPLAY (UC= ) NAME AGE (UC=+)
```



Note: See also *Underlining Character for Titles and Headers - UC Parameter* in the *Programming Guide*.

203

UDB - User Database ID

This Natural profile parameter specifies the DBID to be used for a database access at runtime. This database ID specified with the `UDB` parameter replaces DBID 0 when Natural objects are executed.

Possible settings	0 or 1 - 65535, except 255	Valid database ID. Note: Database ID 255 is reserved for logical system files for Software AG products, see profile parameter <code>LFILE</code> .
Default setting	1	
Dynamic specification	yes	
Specification within session	no	
Application programming interface	USR1005N	See <i>SYSEXT - Natural Application Programming Interfaces</i> in the <i>Utilities</i> documentation. * Recommended.
	USR1040N *	



Notes:

1. The database type of DBID 0, which is specified in the DBMS assignments table of the Configuration Utility, and the database types of the DBID specified with the `UDB` parameter must be the same: ADA/ADA, ADA2/ADA2, SQL/SQL or XML/XML. As an exception, the combination ADA/ADA2 is possible. The first type is the database type of DBID 0 and the second type is the database type of the DBID specified with the `UDB` parameter.
2. If the DBID in the DDM used is 0, then the database type is taken from the DBMS assignments table entry `DBID=0` at compilation time, whereas the database type of the DBID specified with the `UDB` parameter is used only at runtime.
3. If no DBID 0 is specified in the DBMS assignments table, then the default database type is set to ADA.

4. If no DBID is specified in the DDM used, the DBID specified with the UDB profile parameter determines which database is accessed. If so, the UDB profile parameter must be set to a valid DB number.
5. UDB is also used to specify the DBID for storing transaction data if the profile parameter ETDB is not specified.

204 ULANG - User Language

This Natural profile parameter specifies the language to be used for date edit masks, system messages, user messages, helptexts, help routines, and multi-lingual maps. The setting is used to set the Natural system variable *LANGUAGE.

Possible settings	1 - 60	Natural language code. Note: 1. For example, 1 is assigned to English, 2 is assigned to German, 3 is assigned to French. 2. For a detailed list of language codes, see the table in the documentation of the *LANGUAGE variable.
Default setting	1	
Dynamic specification	yes	
Specification within session	no	
Application programming interface	USR1005N	See SYSEXT - <i>Natural Application Programming Interfaces</i> in the <i>Utilities</i> documentation.



Notes:

1. Within the session, the language code can be specified using the terminal command %L=.
2. *Screen Design, Skill-Sensitive User Interfaces* in the *Programming Guide*.

205

USEDIC - Common Logical Name for Dictionary Servers

This Natural profile parameter is used to specify a common logical name for dictionary servers defined with Natural RPC to enable remote dictionary access on a mainframe or UNIX host.

Possible settings	any valid server name	Remote dictionary access will be possible.
Default setting	blank	Remote dictionary access will not be possible.
Dynamic specification	no	
Specification within session	no	

See also *Dictionary Server Assignments* in the *Configuration Utility* documentation.

206

USER - User ID

This Natural profile parameter is used to enter a user ID.

Possible settings	Any valid user ID
Default setting	blank
Dynamic specification	no
Specification within session	no



Notes:

1. If the default setting is used, the login user ID from the operating system applies.
2. Under Natural Security, this profile parameter is ignored.

207

USEREP - Repository Usage

This Natural profile parameter enables you to use the repository.

Possible settings	ON	Repository usage enabled.
	OFF	Repository usage disabled.
Default setting	ON	
Dynamic specification	yes	
Specification within session	no	

208

USIZE - Size of User Buffer

This Natural profile parameter specifies the size of the user buffer in virtual memory. The user buffer contains all data dynamically allocated by Natural.

Possible settings	10 - 1024	Buffer size in MB.
	0	With USIZE=0, the memory capacity will be unrestricted.
Default setting	20	
Dynamic specification	no	
Specification within session	no	

209

WEBIO - Use Natural Web I/O Interface

This Natural profile parameter defines whether the Natural input and output (I/O) remains unchanged (that is, terminal emulation in case of SPoD, and emulation from where Natural is started when calling Natural directly on OpenVMS) or whether the Natural Web I/O Interface is used.

Possible settings	ON	I/O via Natural Web I/O Interface.
	OFF	I/O remains unchanged (terminal emulation).
Default setting	OFF	
Dynamic specification	yes	
Specification within session	no	



Notes:

1. The Natural Web I/O Interface displays the input and output data in a web browser. On platforms other than Windows, the Natural Web I/O Interface can only be used to display and enter U format fields with characters which are not contained in the current code page.
2. The parameter WEBIO can only be used when Natural is running as a server, not in an interactive Natural session.
3. The parameter WEBIO is not compatible with the parameter BATCHMODE. If the parameter BATCHMODE is set, WEBIO=OFF is assumed.
4. See also *Profile Parameters in the Unicode and Code Page Support* documentation.

210

WFOPFA - Opening of Work Files

This Natural profile parameter specifies when work files are to be opened by Natural.

Possible settings	ON	A work file is opened at the time when it is first accessed by a given READ WORK FILE or WRITE WORK FILE statement. This means that only those work files which are actually accessed are opened, while the contents of unopened work files are not deleted.
	OFF	All work files referenced in a Natural object are opened when the execution of this object starts. (This may delete the content of a work file when closing if the work file was referenced by a WRITE WORK FILE statement that was never executed.)
Default setting	ON	
Dynamic specification	yes	
Specification within session	no	



Note: WFOPFA=OFF only affects main programs; for routines, WFOPFA=ON always applies.

211

WH - Wait for Record in Hold Status

This Natural profile and session parameter specifies the action to be taken if a required record is not available for processing, because it has been placed in hold status by another user.

Possible settings	ON	The user is placed in wait status until either the requested record becomes available, or an error message is issued due to Adabas exceeding a time limit or other limit while attempting to place the record in hold status.
	OFF	An error message is returned if any of these records cannot be placed in hold status.
Default setting	OFF	
Dynamic specification	yes	
Specification within session	yes	
Applicable statements	SET GLOBALS	
Applicable command	GLOBALS	
Application programming interface	USR1005N	See <i>SYSEXT - Natural Application Programming Interfaces</i> in the <i>Utilities</i> documentation.



Notes:

1. This Natural profile and session parameter applies to Adabas databases only.
2. Within a Natural session, the profile parameter WH can be overridden by the session parameter WH.
3. When a Natural statement is executed which results in Adabas records being read and an update/delete operation could follow, Natural requests that Adabas places these records in hold status. See the *Adabas Command Reference* documentation for further information on hold processing.
4. Under Natural Security, the setting of this parameter can be overridden by the Session Parameters option of the *Library Profile*.

212

WORK - Work-File Assignments

This Natural profile parameter defines the number of work files to be used during the session.

Possible settings	0 or 1 - 32	Number of work files.
Default setting	32	
Dynamic specification	no	
Specification within session	no	

WORK=*nn*

If WORK is set to *nn* (in the range 1 - 32), this setting defines the highest work file number which is available for the Natural session.

See also *Work Files* in the *Operations* documentation.

213 XADB - Database for Coordination of Transaction

Processing

This Natural profile parameter specifies the databases, where transaction processing is to be coordinated by a TP-monitor system. Mark all such databases in the parameter's database list box.

Possible settings	ON / OFF	Use the check boxes to specify the relevant databases.
Default setting	none	
Dynamic specification	no	
Specification within session	no	



Note: This Natural profile parameter is reserved for future use.

214

XREF - Creation of XRef Data for Natural

■ Possibilities of Setting the XREF Parameter	470
■ XRef Data Generation	471
■ Extended XRef Data Generation (For Internal Use Only)	471

This Natural profile parameter is used to enable/disable the creation of XRef data for Natural. This parameter also determines how XRef data are treated when Natural members are processed with the Natural utilities `SYSMAIN` or `INPL` or with the Object Handler.

Possible settings	ON	XRef data are generated in the cases described above. Documentation premise is not checked.
	OFF	XRef data are not generated. Documentation premise is not checked.
	FORCE	A Natural object can only be cataloged if a documentation object already exists for this implementation object. XRef data are generated in the cases described above.
	DOC	A Natural object can only be cataloged if a documentation object already exists for this object. XRef data are not generated.
Default setting	OFF	
Dynamic specification	yes	
Specification within session	yes	
Applicable statements	none	
Applicable commands	XREF	

The following topics are covered below:

Possibilities of Setting the XREF Parameter

There are different ways to set the Natural `XREF` parameter:

- In the Natural parameter file.
- As a dynamic parameter when starting a Natural session.
- In Natural Security. If Natural Security has been used to set the `XREF` parameter, the `XREF` command may only be used to enforce this setting (by changing from `ON` to `FORCE`, from `OFF` to `ON` or `FORCE`).
- With the Natural `XREF` command. If Natural Security is not installed, the `XREF` parameter is usually set with the Natural `XREF` command. The Natural command `XREF ?` displays the current setting of the `XREF` parameter.

XRef Data Generation

XRef data is generated in two cases:

- The Natural compiler writes XRef data for Natural programs and data areas when these are cataloged (provided that the XREF parameter has been set to either ON or FORCE, see below).
- Natural Security writes XRef data for programs that are used as Startup, Restart or Error-Transaction in an application or as a special link if the XREF parameter is set to ON or FORCE in the application's Natural Security definition and a user system file is defined for the application.

The XREF parameter controls the compilation in two aspects:

- generation of XRef data in the cases described above and
- fulfilment of promise to document implementation objects. The adherence to this promise can be ensured by allowing the completion of the catalog operation only for objects that are documented in the Predict FDIC system file or in the development server file used in Natural Single Point of Development (SPoD).

Extended XRef Data Generation (For Internal Use Only)



Important: The extended XREF parameter is reserved for internal use by Natural.

The extended XREF parameter has the following syntax:

```
XREF=(normal-xref-setting,extended-xref-setting)
```


215

YSLW - Year Sliding or Fixed Window

This Natural profile parameter specifies the range of years covered by the “year sliding window” or “year fixed window”.



Note: The sliding-window or “year fixed window” mechanism assumes a date with a 2-digit year to be within a “window” of 100 years. Within these 100 years, every 2-digit year setting is uniquely related to a specific century, so that there is no confusion about which century is meant.

Possible settings	Normal Setting	0	When you set the parameter to 0, the current century is assumed. No sliding or fixed-window mechanism is used.
	Sliding Window	1 - 99	By setting the parameter to a value between 1 - 99, you determine when the 100-year range begins in the past. The YSLW setting is subtracted from the current year to determine the first year of the window range. Example: If the current year is 2002 and you specify YSLW=40, the sliding window will cover the years 1962 to 2061. A 2-digit year setting <i>nn</i> from 62 to 99 is then interpreted accordingly as 19 <i>nn</i> , while a 2-digit year setting <i>nn</i> from 00 to 61 is interpreted as 20 <i>nn</i> .
	Fixed Window	1582 - 2600	By setting the parameter to a value between 1582 - 2600, you determine the first year of a 100-year range. The upper boundary of the 100-year range is evaluated by adding 99 to the value specified. Example: If you specify YSLW=1985, the fixed window will cover the years 1985 to 2084. A 2-digit year setting <i>nn</i> from 85 to 99 is then interpreted accordingly as 19 <i>nn</i> , while a 2-digit year setting <i>nn</i> from 00 to 84 is interpreted as 20 <i>nn</i> .

Default setting	0	No sliding or fixed-window mechanism is used.
Dynamic specification	yes	
Specification within session	no	

The YSLW parameter is evaluated at runtime when an alphanumeric date setting with a 2-digit year component is moved into a date variable. This applies to data settings which are:

- used with the mathematical function VAL;
- used with the IS(D) option in a logical condition;
- read from the stack as input data;
- or entered in a map as input data.

See also the section *Processing of Date Information* in the *Programming Guide*.

216

ZD - Zero-Division Check

This Natural profile and session parameter specifies the action to be taken when an attempt is made to perform a division operation in which the divisor is 0.

Possible settings	ON	Natural issues an error message if a division by 0 is attempted.
	OFF	Natural returns a result of 0 for any division operation in which the divisor is 0.
Default setting	ON	
Dynamic specification	yes	
Specification within session	yes	
Applicable statements	SET GLOBALS	
Applicable command	GLOBALS	
Application programming interface	USR1005N	See <i>SYSEXT - Natural Application Programming Interfaces</i> in the <i>Utilities</i> documentation.



Notes:

1. Within a Natural session, the profile parameter ZD can be overridden by the session parameter ZD.
2. Under Natural Security, the setting of this parameter can be overridden by the *Session Parameters* option of the Library Profile.

217 ZP - Zero Printing

This Natural profile and session parameter specifies how a field which contains a setting of all zeros is to be output.

Possible settings	ON	Each field value which consists of all zeros is output as one zero, right justified (for numeric fields) or all zeros (for time fields).
	OFF	Each field value which consists of all zeros is suppressed.
Default setting	ON	
Dynamic specification	yes	
Specification within session	yes	
Applicable statements	DISPLAY FORMAT INPUT PRINT REINPUT SET GLOBALS WRITE	
Applicable command	GLOBALS	
Application programming interface	USR1005N	See <i>SYSEXT - Natural Application Programming Interfaces</i> in the <i>Utilities</i> documentation.



Notes:

1. This Natural profile and session parameter is used to suppress the display of a numeric field (format N, I, P or F) or time field (format T) which contains a value of all zeros.
2. Within a Natural session, the profile parameter ZP can be overridden by the session parameter ZP.
3. See also *Parameters to Influence the Output of Fields* in the *Programming Guide*.

