

Class Builder

The Class Builder is a tool which can be used to display a Natural class in a structured hierarchical order, and also to manage the class and its components efficiently.

A Natural class can be composed of various components: "real" Natural objects (for example, an object data area) or objects which exist only in the class source (for example, interface components).

The Class Builder represents each component of the class in the form of a node. By selecting these nodes, the class and its components can be managed in a context-sensitive manner.

The *Class Builder* documentation explains how to create and modify a Natural class with the Class Builder. Please refer to *Defining Classes* in *Introduction to NaturalX (Programming Guide)* to become acquainted with the general usage of Natural classes.

- What is the Class Builder?
 - Class Builder Interface
 - Class Builder Nodes
 - Node Properties
 - Adding Class Components
 - Renaming Class Components
 - Removing Class Components
 - Editing Class Components
 - Using Interfaces from Several Classes
 - Locking Concept
 - Tutorial
 - Glossary
-

What is the Class Builder?

The Class Builder provides the following features:

- It is fully integrated in the general Natural user interface.
- The components of a class are displayed as nodes in the same way as Natural modules. Every type of node has a special icon assigned which provides detailed information for that component.
- Natural objects which are used by a class (for example, ODA), can be managed (edit, stow, ...) by the Class Builder.

- Class and interface GUIDs (Global Unique IDs) are generated and hidden.
- Class comments (one comment for every class component) can be created and changed by the Class Builder.
- The class source is generated automatically.

Which Classes can be handled by the Class Builder?

The Class Builder can manage any syntactically correct class. Even if it is possible to change the class source with the program editor as well, the Class Builder is the recommended editor for changing classes. Please note that a class, which has been changed with the program editor and saved with syntax errors, can no longer be opened using the Class Builder.

The class syntax is highly "flexible", i.e., it is possible to obtain the same runtime behavior with different syntax constructs. This was important for earlier Natural versions, because the user had to type all class code himself. With the Class Builder, this is no longer necessary; the Class Builder will generate the class code and create Natural objects, which are used by the class. The Class Builder will generate only the most reasonable code.

For this reason, the following features are not supported by the Class Builder:

- **create a new GUID LDA:**
The Class Builder generates a GUID for the class and the interfaces of the class. If you wish to define the GUID yourself, you must create a LDA outside of the Class Builder and then link it to the class.
- **create new inline data definitions:**
The Class Builder only provides for the creation of new data areas. This is because data definitions are usually used in several places (for example, method parameter in class and method subprogram) and it is fault-prone if the same inline data definitions have to be used more than once.
- **use data from inline data definitions for assignments in the Class Builder:**
If data definitions have to be assigned to class components in the case of unique IDs and property implementations, the Class Builder offers a list of all data definitions from the corresponding data areas. Data from inline data definitions will not be included in these lists. This means, for example, that the object data variable which is defined inline cannot be used as property implementation.

Although the Class Builder does not permit the creation of all class syntax constructs, it can nonetheless read existing classes with these constructs and can be used to modify these constructs.

If the Class Builder cannot read a class because it is syntactically incorrect, it displays an error message and activates the program editor. The syntax error must be corrected in the program editor. After the class has been saved, it can be opened with the Class Builder.

Note:

If you save a class with the Class Builder, the class source will be generated. This means that any special source formats, such as indentation, will be lost.

When is a Class saved?

When a class is opened in the Class Builder, the contents are read from the class source and stored in an internal structure. If you then change the class, these changes are performed only on the internal structures. The changes are visible in all views of Natural. So, for example, when a new interface is added in the library workspace, a node for this interface will also be created in the "Interfaces" list view of the class. If you want to save your changes, you must execute **Save**, **Save As** or **Stow** for the class.

If you create a new class, this does not automatically create a new class module. This is only done when **Save**, **Save As** or **Stow** is executed for the class. For this reason, a "new" class will not be visible in the File View of the library workspace until it is saved the first time.

If you want to remove the changes which you applied to a class, you can use the **Restore** command. This command will restore the class as it is contained in the class module, i.e., the last saved state.

If Natural is ended and unsaved classes exists, the user will be asked if the classes should be saved.

Class Comments

The Class Builder tries to assign every comment found in the class source to one component of the class. A comment is usually assigned to the following class component. For example a comment which is found before the definition of an interface is taken as comment for this interface.

The comments can be changed and created via the **Properties** menu item, which is available for all class component nodes. For more information, see *Node Properties*.

Note:


If a class is read by the Class Builder for the first time, it is possible that the Class Builder assigns the comments to a component other than the one the user expects. No comment will be lost when the class is saved, but the user should check if the comments are assigned to the correct components.

When a class is saved by the Class Builder for the first time, all comments will be marked with a special tag. This ensures that the comment assignment is correct when this class is read later by the Class Builder.

Class Builder Interface

The Class Builder is available in the logical and flat view of Natural. It is fully integrated in the general Natural user interface which shows the Natural objects as nodes of a tree or list view.

In a tree view of the Library Workspace or Application Workspace, a class can be "opened" by expanding the class node. The class nodes are grouped hierarchically. For example, the interface is a child of the class node and the method is a child of the interface node. Every class node provides the same features as all other nodes, for example, a context menu which allows node-specific actions. Most of the class nodes that have child nodes can be opened as a list view which displays all children of this node. The List View shows more information about the nodes (for example, the library in which an object data area is located). The list view nodes offer the same context menu as the corresponding tree view nodes.



The following topics are covered below:

- Logical View
- Flat View

Logical View

The class nodes of the logical view are inscribed with the class name, i.e., the name that is used when an object of this class is created with the `CREATE OBJECT` statement.

In the logical view the nodes are, as a basic principle, grouped by their type. This is also valid for the class nodes. Class nodes of the same type are collected under a group node which describes the type with its contents. Therefore, all object data nodes are children of the object data group node named "Object Data".

The following topics are covered below:

- Tree Views
- List Views
- Class List View
- Object Data Group List View
- Local Data Group List View
- Interface Modules Group List View
- Interface ModuleList View
- Interfaces Group List View
- Interface List View
- Properties Group List View
- Methods Group List View
- Method Parameter Data Group List View

Tree Views

You can expand and collapse nodes of a class. Expand displays all child nodes and Collapse hides all child nodes of the selected class node.

The logical view provides you with a structured view of the class. You can then expand those class nodes on which you wish to work. For more information, refer to the section *Library Workspace*.

List Views

Most of the parent nodes of a class have an assigned list view which can be opened with the **Open** command from the context menu. This section describes the information which is shown in the list views of the logical view. For more information, refer to the section *List View*.

Class List View

The class list view consists of group nodes. The list view for a group node can be opened with the **Open** command.

The following group nodes exist:

- **"Object Data" group:**
is displayed if the class uses a ODA
- **"Local Data" group:**
is displayed if the class uses a LDA for class or interface GUIDs
- **"Interface Modules" group:**
is displayed if the class uses an Interface Module (see *Using Interfaces from several Classes*).
- **"Interfaces" group:**
is displayed if the class has defined interfaces (internal or external)

The class list view has the following columns:

- **Type:**
type of the node (e.g. Object Data)

- **Count:**
number of components of the specified type

Object Data Group List View

The "Object Data" group list view consists of object data nodes. Choosing the **Open** command for a node will open the data area editor for data areas and a special Class Builder dialog for inline definitions.

The "Object Data" group list view has the following columns:

- **Name:**
name of the object data module or "Inline" in the case of an inline data definition
- **Library:**
library where the object data module is located (is empty for inline data definitions or if the data area has not yet been created)
- **Type:**
Natural type of the object data module ("Local Data Area", "Parameter Data Area" or "Inline Definition")

Local Data Group List View

The "Local Data" group list view consists of local data nodes. Choosing the **Open** command for a node will open the data area editor for data areas and a special Class Builder dialog for inline definitions.

The "Local Data" group list view has the following columns:

- **Name:**
name of the local data module or "Inline" for an inline data definition.
- **Library:**
library where the local data module is located (empty for inline data definitions or if the data area has not yet been created).
- **Type:**
Natural type of the local data module ("Local Data Area", "Parameter Data Area" or "Inline Definition").

Interface Modules Group List View

The "Interface Modules" group list view consists of interface module nodes (see *Interface Module List View*). Choosing the **Open** command for a node will open the list view (see *Using Interfaces from several Classes*) for this particular interface module.

The "Interface Modules" group list view has the following columns:

- **Name:**
name of the interface module (copycode name)
- **Library:**
library where interface module is located.

Interface ModuleList View

The interface module list view consists of interface nodes. Choosing the **Open** command for a node will open the list view (see *Interface List View*) for this particular interface.

The interface module list view has the following columns:

- **Name:**
name of the interface.

Interfaces Group List View

The "Interfaces" group list view consists of interface nodes. Choosing the **Open** command for a node will open the list view (see *Interface List View*) for this particular interface.

The "Interfaces" group list view has the following columns:

- **Name:**
name of the interface.
- **Component Type:**
"Internal Interface" for interfaces which are defined in the class and "External Interface" for interfaces which are defined in an interface module included in this class.
- **Defined In:**
interface module name for externally defined interfaces (empty for internal interfaces).

Interface List View

The interface list view consists of group nodes. Choosing the **Open** command for a node will open a list view for this particular group.

The following group nodes exist:

- **"Properties" group:**
is displayed if the interface contains property definitions
- **"Methods" group:**
is displayed if the interface contains method definitions.

The interface list view has the following columns:

- **Type:**
type of the node (e.g. Properties).
- **Count:**
number of components of the specified type.

Properties Group List View

The "Properties" group list view consists of property nodes. The "Property" group list view has the following columns:

- **Name:**
name of the property.
- **Format:**
format of property.
- **Length:**
length of property.
- **Dimension:**
dimension of property.
- **Read-only:**
shows whether property is read-only or not.
- **ODA Variable:**
name of assigned ODA variable


Methods Group List View

The "Methods" group list view consists of method implementation and parameter data nodes. For every method of the interface, it contains one method implementation (subprogram) node and one node for every parameter data definition of the method.

Choosing the **Open** command for a node of this list view will open the editor for the particular node type (for example, program editor for method implementation node).

The "Methods" group list view has the following columns:

- **Name:**
name of the method. The parameter data nodes are numbered from 1 to n (for example, INIT (2) for the second parameter data node of method INIT).
- **Implementation:**
only for method implementation node: the name of the subprogram which implements the method
- **Parameter Data:**
only for method parameter data node: the name of the parameter data module or "Inline" for an inline data definition
- **Library:**
depending on the node type, library where implementation or parameter data module is located (empty for inline data definitions or if the Natural module has not yet been created).



Method Parameter Data Group List View

The "Parameter Data" group list view consists of parameter data nodes. Choosing the **Open** command for a node will open the data area editor for data areas and a special Class Builder dialog for inline definitions.

The "Parameter Data" group list view has the following columns:

- **Name:**
name of the parameter data module or "Inline" for an inline data definition.
- **Library:**
library where parameter data module is located (empty for inline data definitions or if the data area has not yet been created)
- **Type:**
Natural type of parameter data module ("Parameter Data Area" or "Inline Definition")

Flat View

The class nodes of the flat view show the class module name.

Unlike the logical view, the flat view does not contain any group nodes. The flat view has the advantage that the level where a specific class component is displayed is lower compared to the logical view, and thereby provides you with a better class overview.

The following topics are covered below:

- Tree Views
- List Views
- Class List View
- Interface Module List View
- InterfaceList View

Tree Views

You can expand and collapse nodes of a class. Expand displays all child nodes and Collapse hides all child nodes of the selected class node. The flat view provides you with a general overview of the class. It lists all sub-components of a class component on the same level. For example, if an interface node is expanded, all properties and methods of the interface will be displayed as child nodes of the interface node. For more information, see *Library Workspace*.

List Views

The flat view supports only a few list views because of the low node nesting level. The list views can be opened with the **Open** command from the context menu. This section describes the information which is shown in the list views of the flat view. For more information, refer to the section *List View*.

Class List View

The class list view contains a node for every child component.


The following nodes exist:

- **Object Data node**
for every ODA of the class. Choosing the **Open** command of the node opens the data area editor for data areas and a special Class Builder dialog for inline definitions
- **Local Data node**
for every GUID LDA of the class. Choosing the **Open** command of the node opens the data area editor for data areas and a special Class Builder dialog for inline definitions.
- **Interface Module node**
for every interface module which is used by the class. Choosing the **Open** command of the node will open the interface module list view.
- **Interface node**
for every interface of the class (external and internal). Choosing the **Open** command of the node will open the interface list view.

The class list view has the following columns:

- **Name:**
name of the component.
- **Component Type:**
indicates the type of the component ("Object Data", "Local Data", "Interface Module", "External Interface" or "Internal Interface").

- **Type:**
only for component type "Object Data" and "Local Data": Natural type of data module ("Local Data Area", "Parameter Data Area" or "Inline Definition")



Interface Module List View

The interface module list view consists of interface nodes. Choosing the **Open** command of a node will open the list view (see *List Views*) for this particular interface.

The interface module list view has the following columns:

- **Name:**
name of the interface.

InterfaceList View

The interface list view contains all nodes for the properties and methods of the interface.

The following nodes exist:

- **Property node**
for every property of the interface.

- **Method implementation node**
for every method of the interface. Choosing the **Open** command for the node will open the program editor with the specified implementation (subprogram).
- **Method parameter data node**
for every parameter data component of every method of the interface. Choosing the **Open** command for the node will open the data area editor for data areas and a special Class Builder dialog for inline definitions.

The interface list view has the following columns:



















- **Name:**
name of the property or method; the parameter data nodes for methods are numbered from 1 to n (for example, INIT (2) for the second parameter data node of method INIT).
- **Implementation:**
only for properties and method implementation node: the name of the assigned ODA variable for properties and the name of the subprogram which implements the method for methods.
- **Parameter Data:**
only for method parameter data node: the name of the parameter data module or "Inline" for an inline data definition.
- **Library:**
only for methods: depending on the node type, library where implementation or parameter data module is located (empty for inline data definitions or if the Natural module has not yet been created).
- **Format:**
only for properties: format of property.
- **Length:**
only for properties: length of property.
- **Dimension:**
only for properties: dimension of property.
- **Read-only:**
only for properties: shows whether property is read-only or not.

Class Builder Nodes

Related to the user interface, every component of a class is represented by a node. Nodes are displayed both in tree views and in list views.

Every node has an icon and textual information about the component which can be the name of the component (in the library workspace) or the name of the component and additional information (in the list views).

The following table lists all available Class Builder nodes with their icons and a short description:

Type	Icon	Description
new class		new class which has not yet been saved
class (src)		class which is only available as source
class (gp)		class which is only available as generated program
class (src & gp)		class which is available as source and generated program
ODA		object data defined in a data area module
inline ODA		object data defined with an inline data definition
LDA		local data (for GUIDs) defined in a data area module
inline LDA		local data (for GUIDs) defined with an inline data definition
Interface Module		interface module, i.e., copycode which defines interfaces
internal interface		interface which is defined in the class
external interface		interface which is defined in an interface module that is used by the class
internal property		property which is defined in an internal interface
external property		property which is defined in an external interface
internal method		method which is defined in an internal interface
external method		method which is defined in an external interface
method implementation		subprogram which implements a method
method PDA		method parameter data defined in a data area module
inline method PDA		method parameter data defined with an inline data definition

In the following section, the Class Builder nodes are described in more detail. The commands of a specific node can be invoked from the context menu of the node or the "Classes" toolbar.

The following topics are covered below:

- Class Nodes
- Object Data Nodes
- GUID Local Data Nodes
- Interface Nodes
- Property Nodes
- Method Nodes
- Method Implementation Nodes

- Method Parameter Data Nodes

Class Nodes

The class node represents the class itself. The name displayed in the class node is either the class name (logical view) or the class module name (flat view).

Types

New Class

If a new class is created, it is displayed with the new class icon until it is saved the first time. Therefore, new class means that the class is only "transient" in the current Natural session and is not available in source format. For this reason, the new class will not be shown in the File View which shows the source and gp files of the Natural objects. In addition, it is not possible to execute all class node commands on a new class.

Source-Only

The source-only class icon is displayed if the class is only available in source format but has not yet been cataloged.

GP-only

The GP-only class icon is displayed if the class is only available in GP format. Classes of this type cannot be handled with the Class Builder and the context menu of these classes is the same as for all other Natural objects which are only available in GP format.

Source-and-GP

The Source-and-GP class icon is displayed if the class is available in source and GP format.

Commands

Command	available for	Description
Open	new source-only source-and-GP	Opens the class list view. For more information, see <i>List Views</i>
List	new source-only source-and-GP	Opens the program editor in read-only state with the internal source format of the current class structure.
Cat	source-only source-and-GP	Catalogs the current class.
Save	new source-only source-and-GP	Saves the current class structure in the given class module.
Save As	new source-only source-and-GP	Saves the current class structure in a new Natural module or with a different encoding.

Command	available for	Description
Stow	new source-only source-and-GP	Stows the current class structure in the given class module.
New ODA	new source-only source-and-GP	Creates a new object data area for the class.
New Interface	new source-only source-and-GP	Creates a new interface for the class.
New Interface Module	new source-only source-and-GP	Creates a new interface module. This interface module is linked to the class.
Link LDA	new source-only source-and-GP	Uses an existing data area as GUID LDA for the class. See <i>Link</i> .
Link ODA	new source-only source-and-GP	Uses an existing data area as ODA for the class. See <i>Link</i> .
Link Interface Module	new source-only source-and-GP	Uses an existing copycode as interface module for the class. All interfaces defined in the Interface Module will be included in the class. See <i>Link</i> .
Register	source-and-GP	Registers the class in the system registry. For more information, see <i>NaturalX</i> in the <i>Programming Guide</i> .
Unregister	source-and-GP	Unregisters the class from the system registry. For more information, see <i>NaturalX</i> in the <i>Programming Guide</i> .
Rename	new source-only source-and-GP	Changes either the class name or the class module name depending on the current view of the library workspace. For more information, see <i>Renaming Class Members</i> .
Delete	new source-only source-and-GP	Deletes the Natural module of the class (for source-only and source-and-GP) or only the internal structure of the class (new).
Restore	source-only source-and-GP	Removes all changes of the class which have not yet been saved. This command will close all list views of the class and collapse the class node in the library workspace.
Cut	source-only source-and-GP	Cuts the class module.
Copy	source-only source-and-GP	Copies the class module.
Paste	source-only source-and-GP	Pastes the class module.

Command	available for	Description
Print	new source-only source-and-GP	Prints the source format of the current class structure.
Properties	new source-only source-and-GP	Opens the Properties dialog which shows class-specific information. For more information, see <i>Node Properties</i> .

Object Data Nodes

An object data node represents an object data area module or an inline object data definition. A class can have several object data nodes. If more than one object data node exists, you must take care to follow the correct object data sequence when you use these nodes in method implementations.

Types

Data Area

This type indicates that the object data is defined in a separate Natural module of type local data area or parameter data area. The name which is displayed in the node is the name of the Natural data area module.

Inline Data Definition

This type indicates that the object data is defined direct in the class source with a `DEFINE DATA OBJECT` statement. In this case, the object data has to be defined again in every method implementation which uses the object data. A node of this type is always named "Inline".

Commands

Command	available for	Description
Open	data area	Opens the data area module with the data area editor.
Edit	inline data definition	Opens a dialog which shows the contents of the inline data definition for editing.
List	data area	Lists the data area module.
Cat	data area	Catalogs the data area module.
Stow	data area	Stows the data area module.
Unlink	data area	Unlinks the data area module from the class, i.e. it is no longer used as Object Data Area for the class.
Rename	data area	Renames the Object Data Area link, i.e. uses another data area module as Object Data Area for the class. For more information, see <i>Renaming Class Members</i> .
Delete	inline data definition	Deletes the inline data definition from the class.
Print	data area	Prints the data area module.
Properties	data area inline data definition	Opens the Properties dialog which shows object data-specific information. For more information, see <i>Node Properties</i> .

GUID Local Data Nodes

An GUID Local Data node represents a local data area module or an inline local data definition which contains GUID definitions. A class can have several local data nodes.

Types

Data Area

This type indicates that the GUID local data is defined in a separate Natural module of type local data area or parameter data area. The name which is displayed in the node is the name of the Natural data area module.

Inline Data Definition

This type indicates that the GUID local data is defined direct in the class source with a `DEFINE DATA LOCAL` statement. A node of this type is always named "Inline".

Commands

Command	available for	Description
Open	data area	Opens the data area module with the data area editor.
Edit	inline data definition	Opens a dialog which shows the contents of the inline data definition for editing.
List	data area	Lists the data area module.
Cat	data area	Catalogs the data area module.
Stow	data area	Stows the data area module.
Unlink	data area	Unlinks the data area module from the class, i.e. the data area module is no longer used as GUID Local Data Area for the class.
Rename	data area	Renames the GUID Local Data Area link, i.e. uses another data area module as GUID Local Data Area for the class. For more information, see <i>Renaming Class Members</i> .
Delete	inline data definition	Deletes the inline data definition from the class.
Print	data area	Prints the data area module.
Properties	data area inline data definition	Opens the Properties dialog which shows local data-specific information. For more information, see <i>Node Properties</i> .

Interface Module Nodes

An Interface Module node represents an interface module. The interface module is a Natural module of type copycode which defines interfaces that can be included in several classes. For more information about interface modules and their usage, see *Using Interfaces from several Classes*.

Commands

Command	Description
Open	Opens the interface module list view. For more information, see <i>List Views</i> .
List	Opens the program editor in read-only state with the source format of the current Interface Module structure.
Save	Saves the current Interface Module structure in the given Natural copycode module.
New Interface	Creates a new interface in the Interface Module.
Unlink	Unlinks the Interface Module from the class, i.e. the interfaces defined in the Interface Module are no longer available in the class.
Print	Prints the source format of the current Interface Module structure.
Properties	Opens the Properties dialog which shows Interface Module-specific information. For more information, see <i>Node Properties</i> .

Interface Nodes

An interface node represents an interface of an interface module or a class. For more information about internal and external interfaces, see *Using Interfaces from several Classes*.

Types

Internal

The parent of an internal interface is either an interface module or a class. If its parent is an interface module, this means that the interface is defined in the interface module which is used by the class. In this case, the interface will be displayed a second time as an external interface of the class (For more information, see *Using Interfaces from several Classes*). If the internal interface is a child of the class itself, this means that the interface is defined direct in the class.

External

An external interface can appear only as subnode of a class, which uses an interface module which defines this interface. The commands which can be executed on an external interface node are only a subset of the commands available for an internal interface. Basically you can only change the implementation of such an interface. For more information, see *Using Interfaces from several Classes*.

Commands

Command	available for	Description
Open	internal external	Opens the interface list view. For more information, see <i>List Views</i> .
New Method	internal	Creates a new method for the interface.
New Property	internal	Creates a new property for the interface.
Rename	internal	Renames the interface. For more information, see <i>Renaming Class Members</i> .
Delete	internal	Deletes the interface and all its dependent components.
Properties	internal external	Opens the Properties dialog which shows interface-specific information. For more information, see <i>Node Properties</i> .

Property Nodes

A property node represents a property of an internal or external interface.

Types

Internal

If a property appears as subnode of an internal interface, it will be displayed as internal property. An internal property node always has a dedicated external property node.

External

If a property appears as subnode of an external interface, it will be displayed as external property. The commands which can be executed on an external property are only a subset of the commands which are available for internal properties.

Commands

Command	available for	Description
Rename	internal	Renames the property. For more information, see <i>Renaming Class Members</i> .
Delete	internal	Deletes the property.
Properties	internal external	Opens the Properties dialog which shows property-specific information. For more information, see <i>Node Properties</i> .

Method Nodes

A method node represents a method of an internal or external interface.

Types

Internal

If a method appears as subnode of an internal interface, it will be displayed as an internal method. An internal method node always has a dedicated external method node.

External

If a method appears as subnode of an external interface, it will be displayed as external method. The commands which can be executed on an external method are only a subset of the commands which are available for internal methods.

Commands

Command	available for	Description
New PDA	internal	Creates a new method parameter data area for the method.
Link PDA	internal	Uses an existing parameter data area as method PDA. See <i>Link</i> .
Link implementation	internal external	Uses an existing subprogram as method implementation. See <i>Link</i> .
Rename	internal	Renames the method. For more information, see <i>Renaming Class Members</i> .
Delete	internal	Deletes the method and all its dependent components.
Properties	internal external	Opens the Properties dialog which shows method-specific information. For more information, see <i>Node Properties</i> .

Method Implementation Nodes

A method implementation node represents the Natural subprogram which is executed when the method is called.

Commands

Command	Description
Open	Opens the subprogram of the method implementation in the program editor.
List	Lists the subprogram of the method implementation in read-only mode in the program editor.
Cat	Catalogs the subprogram of the method implementation.
Stow	Stows the subprogram of the method implementation.
Rename	Renames the method implementation, i.e. uses another subprogram for the method implementation. For more information, see <i>Renaming Class Members</i> .
Print	Prints the subprogram of the method implementation.
Properties	Opens the Properties dialog which shows method implementation-specific information. For more information, see <i>Node Properties</i> .

Method Parameter Data Nodes

A method parameter data node represents a parameter data area module or an inline parameter data definition. A method can have several method parameter data nodes, which define the parameter used by the method implementation. If more than one method parameter data node exists, you must ensure that the correct parameter data sequence is used in method implementations.

Types

Data Area

This type indicates that the method parameter data is defined in a separate Natural module of type parameter data area. The name which is displayed in the node is the name of the Natural parameter data area module.

Inline Data Definition

This type indicates that the method parameter data is defined direct in the class source (or interface module source) with a `DEFINE DATA PARAMETER` statement. In this case, the parameter data must be defined again in every method subprogram. A node of this type is always named "Inline".

Commands

Command	available for	Description
Open	data area	Opens the data area module with the data area editor.
Edit	inline data definition	Opens a dialog which shows the contents of the inline data definition for editing..
List	data area	Shows the listing of the data area module.
Cat	data area	Catalogs the data area module.
Stow	data area	Stows the data area module.
Unlink	data area	Unlinks the data area module from the method, i.e. the data area module is no longer used as parameter data area for the method.
Rename	data area	Renames the method parameter data area link, i.e. uses another data area module as parameter data area for the method. For more information, see <i>Renaming Class Members</i> .
Delete	inline data definition	Deletes the inline data definition.
Print	data area	Prints the data area module.
Properties	data area inline data definition	Opens the Properties dialog which shows method parameter data-specific information. For more information, see <i>Node Properties</i> .

Node Properties

The Class Builder provides node-specific information on Natural classes and their elements if context-menu entry **Properties** is chosen. This context-menu entry is available if an object is selected in the library workspace or in a list view. The property sheet provides no information on group nodes.

The information itself is presented in a property sheet. The actual number of property pages shown depends on the type of the selected object.

- **OK**: Accept modifications.

- **Cancel:** Skip modifications.

For all class elements, property pages General and Comment are available. The other property pages depend on the selected node type.

The following topics are covered below:

- General
- Comments
- Identification
- Settings
- Definition

General

The screenshot shows a 'Properties' dialog box with a blue title bar and a close button (X) in the top right corner. Below the title bar are four tabs: 'General', 'Comment', 'Identification', and 'Settings'. The 'General' tab is selected and active. Inside the dialog, there are three text input fields: 'Name' containing 'DEPARTMENTLIST', 'Defined in' containing 'DEPLST', and 'Library' containing 'SYSEXCOM'. At the bottom of the dialog are two buttons: 'OK' and 'Cancel'.

This property page shows general information on the selected object. Its contents vary with the corresponding type of node and are described in the following sections.

Class

Name	Class Name
Defined in	Class Module
Library	Library

Object and Local Data Area

Name	Name of Object or Local Data Area
Used in	Class Name
Library	Library

Inline Data Definition

Name	"Inline Definition"
Defined in	Class Name

Interface Module

Name	Name of Interface Module
Used in	Class Name
Library	Library

Interface

Name	Name of Interface
Defined in	Class Name
Interface Module	If the interface is defined in an interface module this field shows the corresponding name.

Method

Name	Name of Method
Defined in	Name of the interface that offers this method.
Interface Module	If the method is defined in an interface module this field shows the corresponding name.

Implementation

Name	Name of Subprogram
Used in	Name of the method that is implemented by this subprogram.
Library	Library


Parameter Data Area

Name	Name of Parameter Area
Used in	Name of Method
Library	Library

Property

Name	Name of Property
Defined in	Name of the interface that offers this property.
Interface Module	If the property is defined in an interface module this field shows the corresponding name.

Comments




Each component has its own comment.

This property page shows the comment and allows adding new or modifying existing comments. They are entered and listed without any special syntactic notation.

The comment is changed if the property sheet is left by pressing **OK**. Pressing **Cancel** leaves the comment unchanged.

Identification




This property page is available for class and interface nodes. For interfaces, the list box below is only enabled if the interface is defined direct as part of the class. The list box is not visible if the interface is defined in an interface module.

The upper control **Unique ID** shows the current **Global Unique ID** of a class or an interface as read-only information.

This list box offers all data variables contained in local data areas that are linked to the class. These variables can be used as unique identifiers. Inline definitions of variables are not supported.

To exchange the current **Global Unique ID** that is displayed in the upper control with another value, select a variable from the list. The name control is then updated with the newly selected variable name. The **Global Unique ID** is exchanged if a variable has been selected and the property sheet is left by pressing **OK**. Pressing **Cancel** leaves the identification unchanged. There is no check whether a selected variable represents a valid **Global Unique ID**.

Settings



This property page is available for class nodes only. It allows setting the class's activation policy within the Class Builder.

An activation policy for a class can be:

- External Single
- Internal Multiple
- External Multiple


Or it is set to default.

More information on the meaning of these values can be found in *NaturalX* in the *Programming Guide*.

To change the current activation policy select the required value.

The value is changed if the property sheet is left by pressing **OK**. Pressing **Cancel** leaves the identification unchanged.

Definition



This property page is available for properties of interfaces only. It allows modifying the definition of an existing property.

The property's name cannot be changed. The following changes are possible:

- An Object Data Variable can be assigned to the property.

The available Object Data Variables are listed in the page's list box together with their format definition and dimension.

They are taken from the Object Data Areas that are linked to the current class. Inline definitions of variables are not supported.

- Existing assignments of Object Data Variables to properties can be changed. The corresponding control is then updated with the newly selected variable's name.
- The property's format definition can be added or changed if it is different from the Object Data Variable's definition.

Otherwise format and length definition are taken from the assigned Object Data Variable.

- It can be defined whether this property is used read only.

The definition of the property is changed if the property sheet is left by pressing **OK**. Pressing **Cancel** leaves the definition unchanged.

Adding Class Components

To make the development of a class more comfortable the Class Builder offers two ways to add components to a class.

The following topics are covered below:


- Link
- New
- New Class
- New Object Data Area
- New Interface Module
- New Interface
- New Method
- New Property

Link

Existing Natural objects can be linked to a class component.

If context menu item **Link** is activated for an object node a dialog is opened. It lists all objects of the required type that can be found in the current library or its steplibs.

If an object has been selected and the dialog is left by pressing **OK**, a reference to the selected object is added to the class structure. **Cancel** leaves the class structure unchanged.



Link to Class

A GUID Local Data Area, an Object Data Area or an Interface Module can be linked to a class. The dialog shows object name and library.

Link to Method

Each method requires a method implementation. The existing implementation can be exchanged by linking another subprogram to a selected method. Moreover, one or more Parameter Data Areas can be linked to a method. The dialog shows object name and library.

New

New class components are created with context menu item **New**.

In the library workspace, class components are created using in-place editing. List views use dialogs to query the necessary data and create new objects. This applies to all nodes apart from class properties: They are always created using a dialog.

The following sections describe how the different class components are created.

New Class

A new class is first created as an internal class structure. At this time the class name is defined. The class module name, i.e. the name of the actual Natural object, is assigned when the class is saved the first time.

Library Workspace

A new class name, for example NEWCLS, is generated. The corresponding tree node is selected and made available for in-place editing. The name can be changed to any valid class name.

List View

A dialog is opened that asks for the name of the new class.

New Object Data Area

Creating a new object data area adds a reference to a new component to the class structure. The corresponding Natural object is not yet created. It is created if you confirm such when you open it.

Library Workspace

A new object data area, for example NEWODA, is generated. The corresponding node is selected and is made available for *in-place editing*. The name can be changed to any valid data area name.

List View

A dialog is opened that asks for the name of the new object data area.

New Interface Module

Creating a new interface module adds a reference to a new component to the class structure. The corresponding Natural object is not yet created. It is created if it contains interfaces at the time the class is saved.

Library Workspace

A new interface module, for example NEWEIF, is generated. The corresponding node is selected and is made available for in-place editing. The name can be changed to any valid copycode name.

List View

A dialog is opened that asks for the name of the interface module.

New Interface

Library Workspace

A new interface, for example NEWIIF, is generated. The corresponding node is selected and is made available for in-place editing. The name can be changed to any valid interface name.

List View

A dialog is opened that asks for the name of the interface.

New Method

Library Workspace


A new method, for example NEWMET, is generated. The corresponding node is selected and is made available for in-place editing. The name can be changed to any valid method name. The new method name is also taken as the name of the method implementation. Both are added to the class structure. If the method name is longer than a valid Natural subprogram name, only the first characters are used to guarantee a valid implementation name.

List View

A dialog is opened that asks for the name of the method. The new method name is also taken as the name of the method implementation. Both are added to the class structure. If the method name is longer than a valid Natural subprogram name the first characters are used to guarantee a valid implementation name.

New Property

New properties are always created using a dialog.



This dialog retrieves the following information:

Property name:	A valid property name. This is either a new name or the name of the selected ODA variable. For fully qualified ODA variable names the dot is replaced by an underscore.
ODA variable:	The list box lists all variables that are defined in the linked ODAs. If property name, format and length are not changed, these values are taken from the selected ODA variable.
Format:	Format and length can be changed if they must be different from the ODA variable's definitions.
Read-Only:	The property can be marked as read-only.

Renaming Class Components

Like any other Natural object that can be modified in the Natural Studio, the components of a class are renamed by editing their identifier in place. This is done using the mouse or by pressing F2 or by choosing context menu entry **Rename** which is enabled for every class component.

During the edit process the new name is checked for syntactical correctness. If it is not a valid Natural name the edit mode cannot be left. Pressing ESC cancels the edit mode and resets the old identifier.

If class components refer to Natural objects such as Object Data Areas, Parameter Data Areas or Interface Modules, only the references within the class are changed. The corresponding Natural objects are not renamed. They have to be changed explicitly if required.

Removing Class Components

Unlink

Context menu entry **Unlink** is available for class components that refer to Natural objects like Data Areas or Interface Modules. If these modules have been linked to a class previously they can be removed using **Unlink**.

This action only removes the reference to selected components from the class. It does not delete an existing Natural object.

Delete

Context menu entry **Delete** is available for classes and those of their components that do not refer to Natural objects.

If this context menu item is selected, the Class Builder's Delete dialog will be displayed.

You are asked whether you want to delete the selected component(s). A list of references that shows the dependent Natural objects is displayed for each component (if you do not choose **Yes to All**). These Natural objects are identified by name, library and Natural object type if required. The list serves for information purposes only. The dependent Natural sources are not affected.

If the selected component is the class itself, the internal structure is deleted and the corresponding Natural source and cataloged modules are removed from the library.

Yes	Deletes the selected component. If several components are selected, the list of references is shown for the next component.
Yes to All	Closes the dialog and deletes all selected components.
No	Does not delete the selected component. If other components are selected, the delete procedure continues by displaying the delete dialog for the next component.
Cancel	Closes the dialog without deleting anything.

Editing Class Components

Classes

At the time a new class is created, the corresponding new class module is not yet created. This occurs only if **Save**, **Save As** or **Stow** is called for the class.

Save

Save called for an existing class writes the class source to the class module.

If **Save** is called for a new class that does not yet have a corresponding class module, then **Save** is treated like **Save As**. The encoding is initialized with the default code page currently used. If such a class module does not yet exist in the current library, the class module is created and the source is written to this object.

Save As

If **Save As** is called, a dialog is opened that prompts for the class module and the encoding of the class. The input length is restricted to guarantee a valid Natural class module name and the input is checked for validity. If such a class module does already exist or if the name is invalid, an error message is issued.

Cat

If the command **Cat** is called, the class source is cataloged and a corresponding class GP is generated. This does not apply to new classes.

Stow

As for other Natural objects **Stow** internally saves and catalogs a class. If a new class is to be stowed, you are prompted for the class module as described for **Save As**.

Natural Objects

Natural objects that can act as class components can also be modified in the context of the class structure. References to Object Data Areas, Parameter Data Areas and Interface Modules can be created by **New**. Existing objects can be edited, saved and stowed.

Local Data Areas and method implementations cannot be created in the class's context. Here only existing objects can be linked to the class. But they can be edited, saved and stowed.

Other Class Components

Other class components such as interfaces, methods and properties cannot be saved, cataloged or stowed independently. They can only be modified in the context of a class.

Using Interfaces from Several Classes

For some applications, it is useful to implement the same interface in several classes. For this purpose, it is possible to define the interface in a Natural copycode module and include this copycode module in the class which wants to implement the interface. The implementation-specific settings, like method implementations, can be defined in the copycode as a default setting, and they can be overwritten in the class, to use class specific implementations.

Natural copycode modules which define interfaces are called Interface Modules in the Class Builder environment. Interface Modules are fully integrated in the Class Builder, so that interfaces defined in an Interface Module can be handled in the same way as interfaces of a class. However, an Interface Module can only be changed with the Class Builder when it is included from a class.

Interfaces which are defined in an Interface Module are always visible in two places of a class: they are shown as an internal interface under the Interface Module node and they are shown as an external interface under the class node. The commands available for an external interface can be used to change the implementation of the interface.

You can save a changed Interface Module without saving the whole class. If an Interface Module is changed and the class which is the parent of the Interface Module node is saved, the Class Builder asks the user if he wants to save the Interface Module as well.

The locking principles for Interface Modules are described in *Locking Concept*.

Note:

If you change an Interface Module, you should always be aware that this Interface Module can also be used by other classes. After saving the changes other classes can possibly no longer be stowed without errors. The Class Builder cannot check if your Interface Module is used by other classes!

Creating a new Interface Module

The class command **New Interface Module** (see *Class Builder Nodes*) creates a new Interface Module.

An Interface Module node is added in the tree and list views and you can then create new interfaces for the Interface Module, methods and properties for the interfaces and so on. If a new component is created for the Interface Module, the corresponding external node will be added for the class. For example, if a new interface INT1 as added to the Interface Module, an external interface node named INT1 will be created as subnode of the class. The new Interface Module is saved just as an existing Interface Module. As soon as the Interface Module exists as Natural module, it can be linked from other classes.

Linking an existing Interface Module

The class command **Link Interface Module** (see *Class Builder Nodes*) uses an existing Interface Module for the class. A dialog is shown which lists all Natural copycode modules of the current step libraries.

Note:

The dialog will list all copycode modules and not only the Interface Modules.

If you select a copycode module from this list which defines class interfaces, these interfaces are added to the current class interfaces. An error will be generated if you select a copycode module which does not define interfaces or if the selected copycode module contains an interface which is already defined in the class. In this case, the Interface Module is not linked to the class.

If the Interface Module was linked successfully to the class, a node for it will be added to the class tree. Opening the Interface Module node will show the interfaces of the Interface Module. Furthermore all interfaces of the Interface Module are added as external interface nodes to the class itself.

Unlinking an Interface Module

If the **Unlink** command (see *Interface Module Nodes*) is executed for an Interface Module, the interfaces of this Interface Module are no longer used by the class.

This has the effect that the Interface Module node itself and all external interface nodes from this Interface Module are removed from the class.

Note:

If you unlink an Interface Module from a class, all class-specific settings contained in the class source module, such as method implementations for the interfaces of this Interface Module, will be deleted as well.

Interface Nodes

If an Interface Module is used by a class, every interface defined in the Interface Module is represented by two nodes: an internal interface node which is a subnode of the Interface Module and an external interface node which is a subnode of the class. These two interface node types can be distinguished by their icon (see *Interface Nodes*). The same is of course valid for the property and method nodes: if they are children of an internal interface, they are represented by an internal node and if they are children of an external interface, they are represented by an external node (see *Property Nodes* and *Method Nodes*).

Furthermore the commands which can be executed on external interfaces, properties and methods are only a subset of the commands available on internal interfaces, properties and methods. For example, the name of an interface can only be changed for an internal interface. External interfaces allow only the redefinition of the implementation of the interface, i.e. changing the method implementation and the ODA variable which is assigned to a property.

Locking Concept

Natural must ensure that a Natural module cannot be changed at the same time from different places. Therefore, related to the Class Builder, this means that a Natural user must be prevented from changing a Natural module with the program editor which has already been changed with the Class Builder and vice versa.

The Class Builder can be used to change Natural classes and Interface Modules which are special copycode modules (see *Using Interfaces from several Classes*).

Because of the different requirements, the locking concept for classes differs from the Interface Module locking concept. In the following sections both concepts are described.

Locking of Classes

The locking of classes is done very flexibly. The Class Builder does not lock a class until it is changed. This means that a class which is opened with the Class Builder can be opened in the program editor as well.

If a class is opened in the program editor, the class nodes can be viewed in the Class Builder, but it is not possible to apply any changes. Before changing the class, the program editor session has to be closed first.

If a class is visible in the Class Builder and the user changed the class in the program editor, the changes will also be shown in the Class Builder when the class is saved. If a class has been changed with the Class Builder it is no longer possible to open this class with the program editor.

Locking of Interface Modules

The locking of Interface Modules is a bit more restrictive than the locking of classes. A two stage locking exists for the Interface Modules. For the first time the Class Builder must ensure that the Interface Module cannot be changed with the Class Builder and the program editor at the same time: if a class which uses an Interface Module is opened in the Class Builder, the Interface Module is locked. This means on the one hand, that an Interface Module can no longer be opened with the program editor, when a class which uses it is opened in the Class Builder. On the other hand, a class cannot be opened with the Class Builder when it uses an Interface Module which is already open in the program editor.

Moreover, an Interface Module can be opened several times in the Class Builder if it is included from several classes. The Class Builder must ensure that an Interface Module is opened only once, when the user wants to change it, because the other Interface Module instances are then no longer up-to-date: it will try to close all other instances, to make sure that only the current instance of the Interface Module remains visible. The Class Builder will display a confirmation dialog for this purpose which allows the user to stop the process.

If one of the classes was already changed, the user will be asked, if the changes are to be saved . After saving a changed Interface Module, it is again possible to open other classes which use the Interface Module.

Tutorial

This section provides a short introduction on the usage of the Class Builder.

The example shows how class EMPLOYEE in library SYSEXCOM can be built using the Class Builder.

The following topics are covered:

- New class
- Linking Object Data
- Creating an Interface

- Creating Methods
- Creating Properties
- Using an Interface Module
- Linking a GUID Local Data Area
- Activation Policy
- Save and Stow Class
- Register

New class

Activate the logical view in the library workspace and create a new library MYEXCOM that contains the local data areas EMPGUIDS and EMPLOY-O. These are just copies of the objects in SYSEXCOM.

EMPGUIDS contains GUID definitions and EMPLOY-O contains object data definitions. To create a new class MYEMPLOYEE select the library node and then select context menu item **New Source > Class**. A new tree node labeled "NEWCLS" is presented for in-place editing. Just change its name to "MYEMPLOYEE".

Linking Object Data

The object data for MYEMPLOYEE have to be defined in an object data area. This object data area can either be created by selecting context menu item **New** of node "MYEMPLOYEE" or by linking an existing object data area via context menu item **Link > Object Data Area**.

A dialog pops up and shows a list of all local and parameter data areas in MYEXCOM and its steplib. These objects can be used as object data areas. Select EMPLOY-O.

Creating an Interface

To create the first interface select context menu item **New > Interface** of node "MYEMPLOYEE". A new tree node labeled "NEWIIF" is presented for in-place editing. Just change its name to "EMPLOY-I". Further interfaces can be created accordingly or by selecting **New** in the context menu for "Interfaces" (group node).

Creating Methods

To create the first method select context menu item **New > Method** of interface node "EMPLOY-I". A new tree node labeled "NEWMET" is presented for in-place editing. Rename this node to "INIT". A method implementation node with the same name is created automatically.

To use subprogram ELOAD-N (copied from SYSEXCOM) to implement this method, select the method's context-menu item **Link > Implementation** and change the method implementation.

Parameter Data Area ELOAD-A (copied from SYSEXCOM) can be linked using **Link > Parameter Data Area** and then selecting the appropriate module. Further methods can be created accordingly or by selecting **New** in the "Methods" (group node) context menu.

Creating Properties

To create the first property, select context-menu item **New > Property** of interface node "EMPLOY-I". The dialog lists all object data variables that are defined in linked object data areas and can be assigned to a property. They are shown together with their format and length definition and dimension. If one of these variables is selected without entering any information in the other control, this variable name is taken as property name and format and length definition are generated accordingly.

But the Class Builder allows assigning the property another name and format and length can be adapted as long as the new format is data-transfer compatible (see *NaturalX* in the *Programming Guide*). The new property can be marked as read only.

Using an Interface Module

So far class MYEMPLOYEE only defines interfaces internally. But there might be interfaces defined in modules that were adequate to incorporate.

For this purpose an interface module can be linked using the Class's context-menu item **Link > Interface Module**. The interfaces that are defined in this module are then inserted under the corresponding interface module in group "Interface Modules" and at the same time under the group node "Interfaces". To implement their methods, select the corresponding node that can be found under "Interfaces".

Linking a GUID Local Data Area

The Class Builder generates Global Unique IDs for classes and interfaces automatically. But if variables are to be used instead of the generated identifiers, a local data area with the corresponding definition can be linked to MYEMPLOYEE.

The existing Global Unique ID of MYEMPLOYEE can then be changed. Select context menu item **Properties** and activate page Identifiers. This page is available for classes and interfaces.

The generated GUID is displayed in the upper control. Local variables that are defined in EMPGUIDS are listed in the lower box. Select EMPGUID and leave the property sheet with **OK**.

Activation Policy

The Class Builder allows setting a class's activation policy explicitly. The current activation policy of MYEMPLOYEE can be viewed under Settings if context menu item **Properties** is selected. This option is available for classes only. Select **External Multiple** and leave the property sheet with **OK**.

Save and Stow Class

Up to now the new class MYEMPLOYEE has only existed as an internal class structure. To save all changes the class can be saved and stowed in the class module. This change of state is indicated by the changed icon.

Register

And finally register MYEMPLOYEE by selecting context menu item **Register** on the class node.

Glossary

External Interface

An external interface is an interface which is defined in an interface module, that is included by the class.

Interface Module

An Interface Module is a Natural copycode module which defines interfaces. The Interface Module can be used in a class to define the contained interfaces. The class can overwrite the method and property implementations, but all other settings of the interface are used as defined in the Interface Module.

Internal Interface

An internal interface is an interface which is defined direct in the class, or an interface of an Interface Module, which is defined in the Interface Module.

Method Implementation

A method implementation is a Natural subprogram which is assigned to the method and executed when this method is called for a class object.

Property Implementation

A property implementation is the object data variable that is assigned to a property.