

Natural

Terminal Commands

Version 9.1.3

October 2021

This document applies to Natural Version 9.1.3 and all subsequent releases.

Specifications contained herein are subject to change and these changes will be reported in subsequent release notes or new editions.

Copyright © 1992-2021 Software AG, Darmstadt, Germany and/or Software AG USA, Inc., Reston, VA, USA, and/or its subsidiaries and/or its affiliates and/or their licensors.

The name Software AG and all Software AG product names are either trademarks or registered trademarks of Software AG and/or Software AG USA, Inc. and/or its subsidiaries and/or its affiliates and/or their licensors. Other company and product names mentioned herein may be trademarks of their respective owners.

Detailed information on trademarks and patents owned by Software AG and/or its subsidiaries is located at <http://softwareag.com/licenses>.

Use of this software is subject to adherence to Software AG's licensing conditions and terms. These terms are part of the product documentation, located at <http://softwareag.com/licenses/> and/or in the root installation directory of the licensed product(s).

This software may include portions of third-party products. For third-party copyright notices, license terms, additional rights or restrictions, please refer to "License Texts, Copyright Notices and Disclaimers of Third-Party Products". For certain specific third-party license restrictions, please refer to section E of the Legal Notices available under "License Terms and Conditions for Use of Software AG Products / Copyright and Trademark Notices of Software AG Products". These documents are part of the product documentation, located at <http://softwareag.com/licenses> and/or in the root installation directory of the licensed product(s).

Use, reproduction, transfer, publication or disclosure is prohibited except as specifically provided for in your License Agreement with Software AG.

Document ID: NATUX-NNATTCOM-913-20210930

Table of Contents

Preface	v
1 About this Documentation	1
Document Conventions	2
Online Information and Support	2
Data Protection	3
2 Introduction to Terminal Commands	5
Purpose of Terminal Commands	6
Changing the Terminal Command Control Character	6
Issuing Terminal Commands	6
Using Terminal Commands in Programs	6
Terms Used in the Terminal Command Descriptions	7
3 Terminal Commands Grouped by Function	9
Case Translation	10
Copy/Clear	10
Language, Messages, Error Processing	10
Screen and Window Processing	10
Colors	11
INPUT Statement	11
Screen Capturing	11
Statistics	12
Miscellaneous	12
Key Assignments	12
4 Terminal Command Key Assignments	13
Assigning Terminal Commands to Function Keys	14
CLEAR Key - Interrupt Current Operation	14
5 %% and %. - Interrupt Current Operation	15
%% in Online Mode	16
%% in Batch Mode	16
%. in Online Mode	17
%. in Batch Mode	17
6 %* - Inhibit Character Display	19
7 %+ and %- - Enable/Disable Use of Natural Connection	21
8 %<TECH - Display Technical Information	23
9 %= - Assigning Colors to Fields	25
10 %C - Copying Contents of Page Buffer	27
11 %CS and %CC - Copying Data to Stack or *COM	29
12 %E - Display Screen Captures	31
13 %E= - Activate/Deactivate Error Processing	33
14 %F= - Frame Characters for Window	35
15 %FM - Numeric Edit Mask Free Mode	37
16 %H - Hardcopy Output	39
17 %I - Capture Current Screen	41
18 %J - Invoke Helproutine	43

19 %K and %KP - Simulate PF- and PA-Key	45
20 %L - Disable Lower- to Upper-Case Translation	47
21 %L= - Set Language Code	49
22 %M - Control of Message Line	51
Message Line Positioning	52
Message Line Color	53
23 %N - Activate Non-Conversational Mode	55
24 %O - Deactivate Screen Capturing	57
25 %P - Capture Screen Sequence	59
26 %Q - Suppress Next Input	61
27 %QS - Simultaneous Output of Multiple Screens	63
28 %R - Repeat INPUT Statement	65
29 %RN - Suppress Compression of Screen Data	67
30 %S - Resume Screen Capturing	69
31 %T - Position Cursor to Top of Active Window	71
32 %Tl/cc - Position Cursor to Line ll, Column cc	73
33 %T+ and %T- - Position Cursor on Protected Fields	75
34 %T* - Position Cursor Outside Window	77
35 %U - Translate Lower to Upper Case	79
36 %V - Control of Print Mode	81
37 %W - Window Processing	83
Window Size and Position on the Physical Screen	84
Window Position on a Logical Page	86
%WA and %WZ - Save Screen Image before Window	89
38 %X - Control of Infoline	91
Infoline	92
39 %Y - Control of PF-Key Lines	93
Display Format of Function-Key Lines	94
Single- and Double-Line Display	95
Positioning of Function-Key Lines	95
Range of Displayed Function Keys	95
Intensified or Reverse Video Display of Function-Key Lines	96
Coloring of Function-Key Lines	96
40 %Z - Clear Source Area	97

Preface

This documentation describes the Natural terminal commands. It is organized under the following headings:

Introduction to Terminal Commands	What are terminal commands? How to issue terminal commands and how to use them in a program.
Terminal Commands Grouped by Function	Provides an overview of the terminal commands ordered by functional groups.
Terminal Command Key Assignments	How to assign a frequently used terminal command to a function key. Information on CLEAR key.
Terminal Commands in Alphabetical Order	Descriptions of the terminal commands in alphabetical order.

1 About this Documentation

▪ Document Conventions	2
▪ Online Information and Support	2
▪ Data Protection	3

Document Conventions

Convention	Description
Bold	Identifies elements on a screen.
Monospace font	Identifies service names and locations in the format <i>folder.subfolder.service</i> , APIs, Java classes, methods, properties.
<i>Italic</i>	Identifies: Variables for which you must supply values specific to your own situation or environment. New terms the first time they occur in the text. References to other documentation sources.
Monospace font	Identifies: Text you must type in. Messages displayed by the system. Program code.
{ }	Indicates a set of choices from which you must choose one. Type only the information inside the curly braces. Do not type the { } symbols.
	Separates two mutually exclusive choices in a syntax line. Type one of these choices. Do not type the symbol.
[]	Indicates one or more options. Type only the information inside the square brackets. Do not type the [] symbols.
...	Indicates that you can type multiple options of the same type. Type only the information. Do not type the ellipsis (...).

Online Information and Support

Software AG Documentation Website

You can find documentation on the Software AG Documentation website at <https://documentation.softwareag.com>.

Software AG Empower Product Support Website

If you do not yet have an account for Empower, send an email to empower@softwareag.com with your name, company, and company email address and request an account.

Once you have an account, you can open Support Incidents online via the eService section of Empower at <https://empower.softwareag.com/>.

You can find product information on the Software AG Empower Product Support website at <https://empower.softwareag.com>.

To submit feature/enhancement requests, get information about product availability, and download products, go to [Products](#).

To get information about fixes and to read early warnings, technical papers, and knowledge base articles, go to the [Knowledge Center](#).

If you have any questions, you can find a local or toll-free number for your country in our Global Support Contact Directory at https://empower.softwareag.com/public_directory.aspx and give us a call.

Software AG Tech Community

You can find documentation and other technical information on the Software AG Tech Community website at <https://techcommunity.softwareag.com>. You can:

- Access product documentation, if you have Tech Community credentials. If you do not, you will need to register and specify "Documentation" as an area of interest.
- Access articles, code samples, demos, and tutorials.
- Use the online discussion forums, moderated by Software AG professionals, to ask questions, discuss best practices, and learn how other customers are using Software AG technology.
- Link to external websites that discuss open standards and web technology.

Data Protection

Software AG products provide functionality with respect to processing of personal data according to the EU General Data Protection Regulation (GDPR). Where applicable, appropriate steps are documented in the respective administration documentation.

2 Introduction to Terminal Commands

- Purpose of Terminal Commands 6
- Changing the Terminal Command Control Character 6
- Issuing Terminal Commands 6
- Using Terminal Commands in Programs 6
- Terms Used in the Terminal Command Descriptions 7

Purpose of Terminal Commands

A complete functional overview of Natural terminal commands is given in the section *Terminal Commands Grouped by Function*.

Changing the Terminal Command Control Character

You can define another special character as control character; this is done with the session parameter CF.

When the control character is changed, all terminal commands which have been assigned to function keys will be adjusted accordingly.

Issuing Terminal Commands

Terminal commands can be used in a Natural runtime environment. The following rules apply:

- You can enter the control character as first character in any unprotected field or in any position, if the screen contains only protected fields.
- As soon as you enter the control character, a window is displayed in which you can enter a terminal command.
- Terminal commands which have been entered incorrectly are ignored, but you will not receive a corresponding error message.
- If you have entered data in unprotected fields before the terminal command window is displayed, the data will not be processed.

Using Terminal Commands in Programs

Terminal commands may also be issued from within a program by using the `SET CONTROL` statement. When a terminal command is specified with a `SET CONTROL` statement, the control character is omitted.

Terms Used in the Terminal Command Descriptions

In the descriptions of several terminal commands, the terms “screen” and “window” are used with the following meanings:

Term	Meaning
Screen	Depending on the operating system under which Natural is running, “screen” refers either to the entire terminal screen as such, or to the operating-system window in which the Natural session is running, or to the Natural main output window. However, for the sake of convenience, the term “screen” is used in all these instances.
Window	Always refers to the Natural window (as explained with the terminal command <code>%W</code>).

3 Terminal Commands Grouped by Function

- Case Translation 10
- Copy/Clear 10
- Language, Messages, Error Processing 10
- Screen and Window Processing 10
- Colors 11
- INPUT Statement 11
- Screen Capturing 11
- Statistics 12
- Miscellaneous 12
- Key Assignments 12

The following tables provide an overview of the terminal commands grouped by functions.

Case Translation

Terminal Command	Function
%L	Disable lower- to upper-case translation.
%U	Enable lower- to upper-case translation.

Copy/Clear

Terminal Command	Function
%C	Copy current screen into Natural source area.
%CC	Copy data into system variable *COM.
%CS	Copy data to the stack.
%Z	Clear source area.

Language, Messages, Error Processing

Terminal Command	Function
%E=	Activate/deactivate error processing.
%L=	Set language code.
%M	Control of message line.

Screen and Window Processing

Terminal Command	Function
%F=	Frame characters for window.
%K	Simulate PF- and PA-keys.
%Knn, %KPn	Simulate PF- and PA-keys.
%N	Activate non-conversational mode.
%QS	Simultaneous output of multiple screens.
%T and %T11/cc	Set cursor position.

Terminal Command	Function
%T*	Position cursor outside window.
%T+ and %T-	Position cursor on protected field.
%W	Natural window handling.
%Y	Control of PF-key lines.
%*	Disable display of input characters. In batch mode, suppress printing of next input record read.

Colors

Terminal Command	Function
%=	Assign colors to fields.

INPUT Statement

Terminal Command	Function
%FM	Activate/deactivate edit mask free mode.
%R	Repeat INPUT statement.

Screen Capturing

Terminal Command	Function
%E	Display screen captures.
%I	Capture current screen.
%O	Deactivate screen capturing.
%P	Capture screen sequence.
%S	Resume screen capturing.

Statistics

Terminal Command	Function
<code>%X</code>	Control of statistics line/infoline.
<code>%<TECH</code>	Display technical information.

Miscellaneous

Terminal Command	Function
<code>%H</code>	Produce hardcopy output.
<code>%J</code>	Invoke help routine.
<code>%Q</code>	Suppress next input.
<code>%V</code>	Control of print mode.
<code>%% and %.</code>	Interrupt current Natural operation.

Key Assignments

Key(s)	Function
<code>CLEAR</code>	Interrupt current Natural operation.

4 Terminal Command Key Assignments

- Assigning Terminal Commands to Function Keys 14
- CLEAR Key - Interrupt Current Operation 14

Assigning Terminal Commands to Function Keys

For enhanced operating convenience, you can assign a frequently used terminal command to a function key. The following methods exist:

- Within a program, you can assign terminal commands to function keys by using the statement `SET KEY`.
- Function-key assignments can also be made by the Natural administrator via the profile parameter `KEY`.


CLEAR Key - Interrupt Current Operation

Pressing the `CLEAR` key has the same effect as the terminal command `%%`.

You can use the `ESC` key instead of the `CLEAR` key - unless another function is assigned to `ESC` in the terminal database `SAGtermcap`.

5 %% and %. - Interrupt Current Operation

- %% in Online Mode 16
- %% in Batch Mode 16
- %. in Online Mode 17
- %. in Batch Mode 17



These terminal commands can be used to interrupt the current operation.



Note: The terminal commands %% and %. will be ignored if the profile parameter `ESCAPE` is set to `OFF`.

%% in Online Mode

If you enter %% in any field on the screen, the currently active Natural program will be terminated immediately and Natural will return to command input mode. If you enter %% in command input mode, the Natural session will be terminated.

%% has the following effects:

- The contents of the Natural stack will be deleted.
- Any logical database transaction currently being processed is backed out.
- The source program currently in the work area of the editor will not be affected.

%% in Batch Mode

In batch mode, %% may be used to set restart points in the input files and thus ensure the synchronization of the input files in the case of an error.

Influence of Profile Parameter `CC`

Command	Function
<code>CC=ON</code>	If the Natural profile parameter <code>CC</code> is set and an error occurs during the compilation/execution of a Natural program in batch mode, the input data stream for the <code>SYNIN</code> and <code>OBJIN</code> input files will be flushed until a line containing %% in the first two positions is encountered (if no %% is encountered, it will be flushed until the end-of-file is reached). In addition, the contents of the Natural stack will be deleted. If more data are available in the input stream, Natural resumes processing with the line after %.
<code>CC=OFF</code>	Any %% in the input data will be ignored.

%. in Online Mode

Online, %. is the same as %, except that the Natural stack is not deleted.

%. in Batch Mode

In batch mode, %. causes reading of input values for the current INPUT statement to be terminated.

6 %* - Inhibit Character Display

`%*`

This command may be used when entering sensitive data (for example, passwords). %* causes all fields on the current screen to be non-displayable.

When used with the SET CONTROL statement, %* causes all fields on the next screen to be non-displayable.

7 %+ and %- - Enable/Disable Use of Natural Connection

These commands only apply if Natural Connection is installed.

%	{	+ [N]	}
		-	

These terminal commands are used to activate/deactivate Natural Connection.

Command	Function
%+	This command causes the Natural system variable *DEVICE to be set to PC. This permits usage of the Natural Connection system.
%+N	Same as %+. In addition, this command causes no field names to be sent when uploading/downloading data.
%-	This command causes the Natural system variable *DEVICE to be set to the setting in effect prior to execution of a %+ command.


See the *Natural Connection* documentation for further information.

8

%<TECH - Display Technical Information

%<TECH

9 %= - Assigning Colors to Fields



With this command, you can assign colors to field attributes for programs that were originally not written for color support. The command causes all fields/text defined with the specified attributes to be displayed in the specified color.

If predefined color assignments are not suitable for your terminal type, you can use this command to override the original assignments with new ones.

You can also use this command within Natural editors, for example, to define color assignments dynamically during map creation.

Command	Function
General settings:	
<i>blank</i>	Clear color translate table.
F	Newly defined colors are to override colors assigned by program.
N	Color attributes assigned by program are not to be modified.
Field types:	

Command	Function
O	Output fields (AD=O). For detailed information on the session parameter AD, see <i>Field Input/Output Characteristics</i> in the <i>Parameter Reference</i> documentation.
M	Input fields; that is, input-only fields (AD=A) and modifiable fields (AD=M).
T	Text constants.
Possible field attributes:	
B	Blinking
C	Italic
D	Default
I	Intensified
U	Underlined
V	Reverse video
A color can also be assigned to the following parts of a screen:	
BG	Background
WN	Foreground (that is, fields for which no color is defined)
PT	Default page title
FR	Frame of a window
Possible colors:	
BL	Blue
GR	Green
NE	Neutral
PI	Pink
RE	Red
TU	Turquoise
YE	Yellow

Example:

```
%=TI=RE,OB=YE
```

This example assigns color red to intensified text fields and color yellow to all blinking output fields.

10 %C - Copying Contents of Page Buffer

`%C`

This terminal command is used to copy the contents of the page buffer to the next available lines in the Natural source work area.

The page currently displayed by Natural will be copied into the Natural source work area. The page content will be written to the next free location in the source work area, where it can be modified using the Naturalsource editor.

To clear the source work area before copying the page, the `%Z` terminal command may be used.




Notes:

1. `%C` should not be used in an editor session. Modifications made to the source area outside of editor content are not recognized by the editor.
2. The page buffer (the logical output from Natural) is not necessarily the same as the screen buffer which is displayed on the screen.

Example:

```
DEFINE DATA LOCAL
1 I (I2)
END-DEFINE
FOR I = 1 TO 10
  WRITE I
  SET CONTROL 'C'
END-FOR
END
```


11 %CS and %CC - Copying Data to Stack or *COM



1 and W cannot be specified with *Lnn*.

With this terminal command, you can copy parts of a screen into the Natural stack (%CS) or into the system variable *COM (%CC). The protected data from a specific screen line are copied field by field (except with option A; see below).

The second letter in the command determines where the data are copied to:

- %CC...
Copies the data into the system variable *COM.
- %CS...
Copies the data into the Natural stack. The data are placed on top of the stack as input data (as with a `STACK TOP DATA` statement).

The third letter in the command determines the line from which the data are copied:

- %CCC **and** %CSC
Copies all protected data from the line in which the cursor is positioned, beginning from the field in which the cursor is positioned.

- **%CCLnnand %CSLnn**
Copies all protected data from line number *nn*.

Moreover, you have the following options:

- **%C...A**
Copies all of a line, that is, not only the protected data, but also the modifiable fields; the line is not copied field by field, but as a whole (including field attributes).
- **%C...I**
Copies only the intensified fields from a line.
- **%C...color**
Copies only the fields of that color from a line.
- **%C...C1**
Copies only one field, namely the field in which the cursor is positioned (regardless of its attributes). (%C...L *nn1* is not possible.)
- **%C...CW**
Copies only the word (as delimited by blanks or special characters within a field) over which the cursor is positioned. (%C...L *nnW* is not possible.)
- **%C...S**
Causes Natural to “stay” on the screen from which the data are copied, when the command is executed. This allows you to copy several different data from a screen, before you process the data.

When you enter the command directly as **%C...** (or assign it to a PF-key), it applies to the *physical screen* within the active window.

12

%E - Display Screen Captures

`%E`

With this command, you can display any screens that have been captured with the Page Data Set function;

This command suspends normal processing and enters the display mode of the Page Data Set function: A list of all screens captured with this function (by using the terminal commands `%I` and `%P`) is displayed; including screen number, time of capturing, and map name (if the screen is a map). From the list you can then select the screens you wish to have displayed. You cannot enter any data on the displayed screens.

When a screen is captured with `%I` or `%P`, two items of information are superimposed on the screen: the time when the screen was captured, and a screen number (the screens are numbered sequentially in the order in which they are captured).

A window will be displayed in which you can scroll through the list of screens captured. With `ENTER`, you can select a screen for display. With `ESC`, you leave the function.

See also the terminal commands `%P`, `%O`, `%S`, and `%I`.

13 %E= - Activate/Deactivate Error Processing

%E=	{	ON	}
		OFF	

With the terminal command `%E=OFF` any error transaction and `ON ERROR` processing is switched off, with `%E=ON` error transaction and `ON ERROR` processing is switched on again.

Command	Function
<code>%E=OFF</code>	Switches any error transaction (as identified by the system variable <code>*ERROR-TA</code> or defined in Natural Security) and <code>ON ERROR</code> processing off; any error that occurs will then be handled by normal Natural error processing. This may be used to locate an error in your applications' error processing if the structure of the application with various error-handling procedures on different levels makes it impossible for you to find out where exactly an error originally occurred.
<code>%E=ON</code>	Switches error transaction and <code>ON ERROR</code> processing on again.

For further information, see *Using an Error Transaction Program* in the *Programming Guide*

14 %F= - Frame Characters for Window

```
%F=chv
```

With this terminal command, you can define the characters to be used in the frame of a window.

<i>c</i>	The first character will be used for the four corners of the window frame.
<i>h</i>	The second character will be used for the horizontal frame lines (top and bottom frame lines).
<i>v</i>	The third character will be used for the vertical frame lines (left and right frame lines).

Example: The command `%F=+-!` would cause the window frame to look like this:

```
+-----+
!               !
!               !
!               !
!               !
+-----+
```

For further information on window processing, see the `DEFINE WINDOW` statement (in the *Statements* documentation).

15 %FM - Numeric Edit Mask Free Mode

`%FM { + }`

This command is used to activate/deactivate edit mask free mode, a special capability to allow literals to be omitted during input into a field with a numeric edit mask.

Command	Function
%FM-	With this command, you switch edit mask free mode off.
%FM+	With this command, you switch edit mask free mode on.

The default setting at session startup is provided with profile parameter `EMFM`.

See the `INPUT` statement (in the *Statements* documentation) for additional information on the edit mask free mode.

16 %H - Hardcopy Output

%H	<i>destination</i> # <i>destination</i> =[<i>destination</i>] -
----	--

These terminal commands are used to produce hardcopy output from Natural reports on a printer or special destination, such as the source area.

By default, a %H command is effective for the current logical output (that is, the current window without message line, function-key lines and statistics line/infoline).

You have the following options:

Command	Function
%H	<p>This command activates the hardcopy output. The hardcopy output is deactivated when either an INPUT statement with modifiable fields is executed, or the end of the program is reached. All pages, which are processed when the hardcopy output is active, will be forwarded to the printing destination. These pages are not displayed on the screen.</p> <p>If %H is entered in an input field, only the current page will be printed.</p> <p>For the definition of the output destination, a window is displayed listing all available printers and special destinations (e.g. SOURCE). From this list, you select the destination on which the hardcopy is to be printed.</p>
%H <i>destination</i>	Same as %H, but the printing destination is specified with <i>destination</i> . The <i>destination</i> can be 1 to 8 characters long.

Command	Function
%H!	<p>With <code>SET CONTROL 'H!'</code>, the current page (that is, the page which was output before the <code>SET CONTROL</code> statement was executed) is printed. With <code>%H!</code>, the page which is currently displayed on the screen, is printed.</p> <p>For the definition of the output destination, a window is displayed listing all available printers and special destinations (e.g. <code>SOURCE</code>). From this list, you select the destination on which the hardcopy is to be printed.</p>
%H! <i>destination</i>	Same as <code>%H!</code> , but the printing destination is specified with <i>destination</i> . The destination can be 1 to 8 characters long.
%H=	<p>This command activates/deactivates (toggle switch) the logging of all following pages. Logging means that all pages, which are displayed on the screen are forwarded to the printing destination as well. This feature may be used, for example, to log a sequence of output for administrative, debugging or educational purposes.</p> <p>For the definition of the output destination, a window is displayed listing all available printers and special destinations (e.g. <code>SOURCE</code>). From this list you select the destination on which the hardcopy is to be printed.</p>
%H= <i>destination</i>	Same as <code>%H=</code> , but the printing destination is specified with <i>destination</i> . The destination can be 1 to 8 characters long.
%H# <i>destination</i>	Same as <code>%Hdestination</code> .
%H-	<p>Deactivates the hardcopy output immediately.</p> <p>Note: When a <code>SET CONTROL 'H-'</code> statement is executed, data which were already written to the page buffer but have not been output yet, will not be routed to the printer. To also print these data, you have to code an <code>EJECT</code> statement before the <code>SET CONTROL 'H-'</code> statement.</p>



Note: The `EJECT` statement does not affect the `%H` command. The `%H` command always causes Natural to advance pages.

17

%I - Capture Current Screen

`%I`

When you enter this command on a screen, the screen will be captured by the Page Data Set function.

The maximum number of screens that can be captured is determined by the session parameter `PD`. If this number is exceeded, each additional screen will overwrite one that has already been captured, beginning with the one captured first.

To display screens that have been captured with the Page Data Set function, use the terminal command `%E`.

See also the terminal commands `%P`, `%O`, `%S`, and `%E`.

18

%J - Invoke Helproutine

`%Jhelproutine`

This terminal command can be used to invoke an interactive helproutine.

19 %K and %KP - Simulate PF- and PA-Key

%K	{ <i>nn</i> <i>Pn</i> }
----	----------------------------------

These terminal commands can be used to simulate the terminal function (PF, ENTER) and program attention (PA) keys.

Command	Function
<i>%Knn</i>	Simulates the terminal function key numbered <i>nn</i> (PF1 to PF99). This permits PF-keys 13-24 to be assigned to PF-keys 1-12, or the activation of PF-keys not available on the keyboard used. This terminal command also makes function keys available in batch mode.
<i>%K0</i>	Simulates the ENTER key.
<i>%KPn</i>	Simulates the program attention key numbered <i>n</i> (PA1 to PA3) (see <i>%Knn</i>).

20 %L - Disable Lower- to Upper-Case Translation

`%L`

This command prevents that lower-case characters are translated to upper-case by Natural.

`%L` influences the interactive input which is entered, for example, with a Natural `INPUT` statement. It does not, however, influence the input from the stack.

See also the terminal command [%U](#).

21

%L= - Set Language Code

`%L=nn`

With the terminal command `%L=nn`, you can set the language code `nn` to be used by Natural.


For a list of possible language codes, see the system variable `*LANGUAGE`.

To set the language code already at session start, specify the profile parameter `ULANG`.

22

%M - Control of Message Line

- Message Line Positioning 52
- Message Line Color 53



With this terminal command, you can control the position, the protection mode and the color of the Natural message line.

This terminal command is ignored in batch mode.

Message Line Positioning

Command	Function
%MT	Causes the message line to be the top line of the screen.
%MB	Causes the message line to be the bottom line of the screen.
%M	Causes the current message line position to be switched from the top line to the bottom line of the screen (or vice versa), or from line <i>nn</i> to the bottom line.
%M <i>nn</i>	Causes the message line to be placed on line <i>nn</i> of the screen.
%M- <i>nn</i>	Causes the message line to be placed on the <i>nn</i> th line from the bottom of the screen. If the line number <i>nn</i> or <i>-nn</i> is not within the current screen, the message line will not be displayed.

Message Line Color

Command	Function
<code>%M=color-code</code>	When a color screen is used, this terminal command causes the message line to be displayed in the specified color (for an explanation of color codes, see the session parameter CD).

See also *Control of the Message Line - Terminal Command %M* in the *Programming Guide*.

23 %N - Activate Non-Conversational Mode

`%N`

This terminal command is used with a `SET CONTROL` statement and causes the next logical output screen to be displayed without requiring any user response for processing to continue; that is, after the screen has been displayed, processing will continue immediately without waiting for any user input.

This command may be used to send messages about the progress of program execution to the user.

24 %O - Deactivate Screen Capturing

`%O`

With this command, you deactivate the capturing of screens by the Page Data Set function as activated by the terminal command `%P`.

The current screen is captured. All screens captured since the last `%P` command are retained.

See also the terminal commands `%E`, `%I`, `%P` and `%S`.

25

%P - Capture Screen Sequence

`%P`

With this command, you activate the Page Data Set function to capture the current screen and all subsequent screens.

The maximum number of screens that can be captured is determined by the session parameter `PD`. If this number is exceeded, each additional screen will overwrite one that has already been captured, beginning with the one captured first.

All screens that have been captured with previous `%P` and `%I` commands will be deleted when you issue a `%P` command.

To display screens that have been captured, you use the terminal command `%E`.

See also the terminal commands `%E`, `%I`, `%O` and `%S`.

26 %Q - Suppress Next Input

%Q

In interactive processing, the %Q command is ignored.

SET CONTROL 'Q' causes the next INPUT statement *not* to be processed. This may be used, for example, if at the end of a help routine the processing is to continue without the user having to press ENTER upon return from the help to the map.

27

%QS - Simultaneous Output of Multiple Screens

%QS

With this command, you can display multiple screens simultaneously.

%QS causes the next screen I/O not to be executed. The corresponding output screen is kept internally until the following I/O, when it is displayed together with the next screen. Therefore %QS only makes sense if the second output screen is a window, that is, if it does not entirely overlay the first screen that was suppressed with %QS.

Example: You can suppress the output of a screen A with %QS; the next screen B is a window which partially overlays screen A (perhaps a help window for one of the fields on screen A); with the next screen I/O, the window B and the “underlying” screen A are displayed simultaneously.

A %QS command only applies to the subsequent screen.



Note: As %QS reduces the number of screen I/O operations, it also improves performance.

28

%R - Repeat INPUT Statement

%R

This command causes `INPUT` statement repetition and the output screen to be rebuilt. All output data generated from the beginning of the `INPUT` statement will be reproduced.

29

%RN - Suppress Compression of Screen Data

%RN

For the next screen I/O, this command suppresses Natural's automatic compression of screen data and causes the entire screen to be sent instead.

At a screen I/O, Natural usually does not send the entire screen, but only the changed screen data. When a non-Natural program is invoked which causes a screen I/O, Natural in most TP environments recognizes the non-Natural I/O and sends the entire screen upon the next screen I/O. However, in some TP environments, the non-Natural I/O is not recognized by Natural; in such a case, %RN should be used.

%RN only applies to the next screen I/O.

30

%S - Resume Screen Capturing

%S

This command is used to resume the capturing of screens by the Page Data Set function.

The capturing of screens (which is activated with the terminal command %P) can be interrupted with the terminal command %0. After it has been interrupted, you can use the terminal command %S to resume the capturing of screens.

See also the terminal commands %E, %I, %0 and %P.

31

%T - Position Cursor to Top of Active Window

`%T`

This command positions the cursor at the top left-hand corner of the active window on the next screen output.

This command only works if there is an input field (session parameter `AD=A` or `AD=M`) at the top left-hand corner.

32

%Tll/cc - Position Cursor to Line ll, Column cc

`%Tll/cc`

This command positions the cursor at line *ll*, column *cc* on the next screen output.

The line and column positions are counted beginning with 1 within the current logical page. For this reason, the message line, the function-key lines, and the statistics line/info line (if active) are not taken into account for the cursor position; that is, %T1/1 always positions to the beginning of the topmost data line of the page (if visible).

You have to execute the terminal command %T+ before you can place the cursor at any desired position on the screen.

%Tll/cc only works if there is an input field (session parameter AD=A or AD=M) at the specified position.

33

%T+ and %T- - Position Cursor on Protected Fields

%T { + } { - }

The following command options are available:

Command	Function
%T+	After you issue this command, you can position the cursor anywhere on the screen, including protected fields (however, the protected fields remain write-protected).
%T-	With this command, you cancel the effect of the command %T+.

34 %T* - Position Cursor Outside Window

%T*

Normally, when a window is active and the window contains no input fields (AD=A or AD=M), the cursor is placed in the top left corner of the window.

This terminal command causes the cursor to be placed in a *COM system variable outside the window when the active window contains no input fields.

Command	Function
%T*	Switches between cursor placement in system variable *COM outside the window and standard cursor placement within the window.

%T* only applies to the next INPUT statement, and it must be issued *before* the INPUT statement.

35

%U - Translate Lower to Upper Case

`%U`

This command causes Natural to translate lower-case characters to upper-case for alphanumeric input data.

Upper-case translation is in effect by default.

`%U` influences the interactive input, which is entered, for example, with a Natural `INPUT` statement. It does not, however, influence the input from the stack.

Upper-case translation is not performed if `AD=W` has been specified for the input field (see the section *Field Upper/Lower Case Characteristics* in the description of the session parameter `AD`).

See also the terminal command [%L](#).

36 %V - Control of Print Mode

%V	[ON] [OFF]
----	-------------------

Syntax Description:

Command	Function
%VON	Sets screen direction to right-to-left.
%VOFF	Sets screen direction to left-to-right.
%V	Toggles between left-to-right to right-to-left screen direction. For detailed information on how to use the terminal command %V, see <i>Bidirectional Language Support</i> in the <i>Unicode and Code Page Support</i> documentation.

For further information on print modes, see the session parameter PM.

37

%W - Window Processing

- Window Size and Position on the Physical Screen 84
- Window Position on a Logical Page 86
- %WA and %WZ - Save Screen Image before Window 89



Note: You are strongly recommended to use the `DEFINE WINDOW` statement instead of the `%W` command.

A Natural window is that segment of a logical page, built by a Natural program, which is displayed on the terminal screen.

The `%W` command controls the processing of this window.

The command must always be specified with parameters for the various functions as described hereafter. Multiple parameters may be specified with one `%W` command; they must be specified consecutively without any delimiter characters.

There is always a window present, although you may not be aware of its existence: unless specified differently (with a `%W` command or `DEFINE WINDOW` statement), the size of the window is identical to the physical size of your terminal screen.

See also the `DEFINE WINDOW` statement in the *Statements* documentation for information on window processing.


There are two types of window commands:

- commands to control the size and position of the window on the physical screen;
- commands to control the position of the window on the logical page created by the program.

Window Size and Position on the Physical Screen

The following window commands control the size and position of the window on the physical screen.

When you change the position of the window on the physical screen, the position of the window on the logical page will remain unchanged:



For information on possible window sizes, see the `DEFINE WINDOW` statement.

Command	Function
<code>%WB</code>	The window size (excluding frame) will be set to physical screen size. If a frame is defined, it will not be visible.
<code>%WBlll/ccc</code>	The top left corner of the window will be positioned to line number <i>lll</i> , column number <i>ccc</i> (lines and columns are counted on the physical screen). The window size will remain unchanged. If the window is too large to be placed at the specified position, it will be placed as close as possible to that position.
<code>%WB0</code>	The window will be positioned to the top left corner of the screen. The window size will remain unchanged.
<code>%W#</code>	The top left corner of the window will be positioned to the cursor position. The window size will remain unchanged. If the window is too large to be placed at the specified position, it will be placed as close as possible to that position.
<code>%W?</code>	The bottom right corner of the window will be set to the cursor position. The top left corner of the window will remain unchanged, and the size of the window will be adjusted accordingly.
<code>%WLn</code>	The line size (horizontal extension) of the window (including frame, if specified) will be set to <i>nn</i> . If <i>nn</i> is omitted or specified larger than would fit on the screen, the line size will be set to the maximum possible (that is, to the right edge of the screen).

Command	Function
%WCnn	The column size (vertical extension) of the window (including frame, if specified) will be set to <i>nn</i> . If <i>nn</i> is omitted or specified larger than would fit on the screen, the column size will be set to the maximum possible (that is, to the bottom of the screen).

Column size and line size specifications refer to the overall physical size of the window (including frame, if specified), not to the size of what is logically visible inside the window.


Any incorrect/impossible size or positioning commands will either be ignored or adjusted to the physical possibilities.

Command	Function
%WF	Switch on framing. The boundaries of the window will be indicated by a frame. If the window size is smaller than 4 lines by 12 columns, the frame will not be visible.
%WM	Switch off framing. The boundaries of the window will not be indicated by a frame. Switching off the frame does not change the size of the window (only the size of the page segment visible inside the window).
%WO	Suppress display of PF-key lines, message line and statistics line. This command only applies if the screen is a "real" window (that is, smaller than the physical screen). To cancel the effect of %WO, you issue %WO again (or %WD).
%WP	By default, the PF-key lines, the message line and the statistics line are displayed within a window. To display them on the screen outside the window, use %WP. To cancel the effect of %WP, you use %WD.
%WD	Cancels the effects of %WF, %WO and %WP (and of the TITLE option of the DEFINE WINDOW statement).
%WX	If there is a *COM field outside the window, this field is normally not write-protected. With %WX you can make it write-protected.
%WY	Cancels the effect of %WX.

Window Position on a Logical Page

The following window commands control the positioning of the window on the current logical page, that is, the current report/map produced by the Natural program for display. This logical page may be larger in size than the physical screen.

When you change the position of the window on the logical page, the size and position of the window on the physical screen will remain unchanged. In other words, the window is not moved over the page, but the page is moved "underneath" the window:



Unless specified differently by one of the following commands, the window will be placed at the top left corner of the logical page.

Command	Function
<code>%W*</code>	The position marked on the page by the cursor will be shifted to the top left corner of the window.
<code>%Wlll,ccc</code>	The position of the logical page determined by line number <i>lll</i> , column number <i>ccc</i> will be shifted to the top left corner of the window. Lines and columns are counted on the logical page.
<code>%W<</code>	Shift window left. The number of positions shifted is equal to the line size (horizontal extension) of the window.
<code>%W<<</code>	Shift window to leftmost position of page.
<code>%W<n</code>	Shift window left <i>n</i> positions ($0 \leq n \leq$ logical line size).
<code>%W></code>	Shift window right. The number of positions shifted is equal to the line size (horizontal extension) of the window.
<code>%W>></code>	Shift window to rightmost position of page.
<code>%W>n</code>	Shift window right <i>n</i> positions ($0 \leq n \leq$ logical line size).
<code>%W+</code>	Shift window down. The number of lines shifted is equal to the number of lines in the window. (*)
<code>%W++</code>	Shift window to bottom of page. (*)
<code>%W+n</code>	Shift window down <i>n</i> lines ($0 \leq n \leq$ logical page size). (*)
<code>%W-</code>	Shift window up. The number of lines shifted is equal to the number of lines in the window.

Command	Function
%W -	Shift window to top of page.
%W - n	Shift window up <i>n</i> lines (0 =< <i>n</i> =< logical page size).
%WH	By default, the position of the window on the logical page is reset to <i>top left corner</i> after a screen I/O. %WH prevents the window position from being reset by the next I/O, that is, the set window position will be retained. %WH only applies to the next I/O.
%WS	Switch on the STAY option; that is, control will “stay” on the current page until the end of the page. If a page is not yet completely shown in vertical direction, a string of VVVV will appear in the message line. The window will be scrolled downward with every ENTER until the end of the logical page is reached. The next ENTER will cause control to be returned to the program. (This does not apply to pages created by an INPUT statement with input fields (session parameter AD=A or AD=M).)
%WN	Switch off the STAY option. When you press ENTER, control is returned to the program.

* The window can be shifted to the last non-blank line of the page at most.



Notes:

1. If you wish to use one of the above commands within a program to shift the window, assign the command to a function key (with a SET KEY statement).
2. If you wish to specify it with a SET CONTROL statement, this statement must be followed by a REINPUT statement (that is, it must be placed between the REINPUT statement and corresponding INPUT statement); otherwise Natural will not be able to uniquely identify the window to which the command is to be applied (and will ignore it).
3. As a rule, however, no SET CONTROL 'W' statement should be placed between an INPUT statement with WINDOW='window-name' option and the corresponding REINPUT statement.

Examples of Command Combinations

The various parameters to be specified with the %W command may also be combined with one another; for example:

%W<<-	Position window to top left corner of page.
%W>>+	Position window to bottom right corner of page.
%W+-	Display the next to last window segment of the page.
%W+3>6	Position window 3 lines down and 6 positions right on the page.
%W10+>	Position window to line 10 of the page, then 1 window down and 1 window right.

%WL40C10+-3	Define the window with a line size of 40 positions and a page size of 10 lines, move that window to the bottom of the page, then move it up 3 lines on the page.
%WL30C10B3/15--<<	Define the window with a line size of 30 positions, page size of 10 lines, position the window at line 3 column 15 on the physical screen and move this window to the top left corner of the page.
%WFS	Generate a frame around the window and set the STAY option on.


The parameters are evaluated in the sequence in which they are specified, so that different sequences of the same parameters may lead to different results.

%WA and %WZ - Save Screen Image before Window

Command	Function
%WA	<p>With %WA, you activate a “save screen image before window” feature. When this feature is activated and a window is to be opened, all active screen data that will be overlaid by the window are saved. When the same window is moved, the saved screen image is reconstructed before the window is built up at the new location on the screen. In addition, it is possible to rebuild the saved images of multiple dependent windows whenever the calling window becomes active again.</p> <p>When the current INPUT statement uses a window, the screen image is stored before the window is output. Whenever the same INPUT statement is repeated, the current or all subsequent stored screen images are recovered and are written back to the screen.</p> <p>This feature makes it possible, for example, to use windows in a PC-like manner. For a given window, any number of dependent windows can be written to the screen. All these windows will disappear from the screen when the main input window is re-executed.</p> <p>The buffer contents (screen images) are deleted whenever Natural performs a full-screen I/O, when Natural returns to command mode (NEXT), after a LOGON command, or after the CLEAR key has been pressed.</p>
%WZ	With %WZ, you deactivate a previously entered %WA command.

38 %X - Control of Infoline

- Infoline 92



This terminal command controls the display of the Natural **infoline**.

Command	Function
%X+	Switches the display of the infoline on.
%X-	Switches the display of the infoline off.
%X	Switches the display of the infoline on and off (toggle switch).
%XB	Displays the infoline in the bottom line of the screen.
%XT	Displays the infoline in the top line of the screen.
%Xnn	Displays the infoline on line <i>nn</i> of the screen. If the line number <i>nn</i> is not within the current screen, the infoline will not be displayed.
%X - nn	Displays the infoline on the <i>nn</i> th line from the bottom of the screen. If the line number <i>-nn</i> is not within the current screen, the infoline will not be displayed.


Infoline

Data can be written to the infoline by specifying the output destination `INFOLINE` with the `DEFINE PRINTER` statement. Only a single line can be written to the infoline. The infoline can be used to have status information displayed, for example, for debugging purposes; it can also be used as separator line (as defined by SAA standards).

39

%Y - Control of PF-Key Lines

- Display Format of Function-Key Lines 94
- Single- and Double-Line Display 95
- Positioning of Function-Key Lines 95
- Range of Displayed Function Keys 95
- Intensified or Reverse Video Display of Function-Key Lines 96
- Coloring of Function-Key Lines 96



Alternatively, you may specify:

```
%Y=color-code [color-code] [color-code]
```

The terminal command %Y is used to control the display of the Natural PF-key lines.

 **Note:** On graphical user interfaces, this command is ignored.

Display Format of Function-Key Lines

Command	Function
%YN	Displays the function-key lines in normal tabular Software AG format.
%YS	Displays the function-key lines in sequential format, and only showing those keys to which names have been assigned (PF1= <i>value</i> , PF2= <i>value</i> , etc.).
%YP	Displays the function-key lines in PC-like sequential format; corresponds to %YS, except that F <i>n</i> = instead of PF <i>n</i> = is displayed before the names.

Single- and Double-Line Display

Command	Function
%YA	All-line display. Displays both function-key lines.
%YH	Half display. Displays only one function-key line; for normal tabular display mode (%YN), this is the line with the function-key names; for the other two display modes (%YS and %YP), this is the upper line to be displayed.

Positioning of Function-Key Lines

Command	Function
%YB	Displays the function-key lines at the bottom of the screen.
%YT	Displays the function-key lines at the top of the screen.
%Ynn	Displays the function-key lines on line <i>nn</i> on the screen.
%Y - nn	Displays the function-key lines on the <i>nn</i> th line from the bottom of the screen. If the line number <i>nn</i> or <i>-nn</i> is not within the current screen, the function-key lines will not be displayed.

Range of Displayed Function Keys

Command	Function
%YF	Displays the first range of function keys (that is, usually 1 to 12).
%YL	Displays the last range of function keys (that is, usually 13 to 24).
%YX	Is used to toggle-switch between the two displays.

Intensified or Reverse Video Display of Function-Key Lines

Command	Function
%YI	Displays the function-key lines intensified. Enter %YI again to switch back from intensified to non-intensified display.
%YV	Displays the function-key lines in reverse video. Enter %YV again to switch back from reverse video display to normal display.

Coloring of Function-Key Lines

Command	Function
%Y= <i>color-code(s)</i>	<p>Displays the function-key lines in the specified colors. The <i>color-codes</i> you can specify are the same as with the session parameter CD).</p> <p>You can specify up to three <i>color-codes</i>: the first <i>color-code</i> refers to the first function-key line (the one displaying the function-key numbers), the second <i>color-code</i> refers to the second function-key line (the one displaying the function-key names), and the third <i>color-code</i> refers to the background of both lines.</p> <p>For example, %Y=GRPIYE would cause the characters in the first line to be displayed in green, the characters in the second line in pink, and the background of both lines in yellow.</p>

40

%Z - Clear Source Area

`%Z`

This command clears the contents of the Natural source area.

It can only be used with the `SET CONTROL` statement.

