

Natural

Natural Web I/O Interface

Version 9.3.3

October 2025

This document applies to Natural Version 9.3.3 and all subsequent releases.

Specifications contained herein are subject to change and these changes will be reported in subsequent release notes or new editions.

Copyright © 1992-2025 Software GmbH, Darmstadt, Germany and/or its subsidiaries and/or its affiliates and/or their licensors.

The name Software AG and all Software GmbH product names are either trademarks or registered trademarks of Software GmbH and/or its subsidiaries and/or its affiliates and/or their licensors. Other company and product names mentioned herein may be trademarks of their respective owners.

Detailed information on trademarks and patents owned by Software GmbH and/or its subsidiaries is located at <https://softwareag.com/licenses>.

Use of this software is subject to adherence to Software GmbH's licensing conditions and terms. These terms are part of the product documentation, located at <https://softwareag.com/licenses> and/or in the root installation directory of the licensed product(s).

This software may include portions of third-party products. For third-party copyright notices, license terms, additional rights or restrictions, please refer to "License Texts, Copyright Notices and Disclaimers of Third-Party Products". For certain specific third-party license restrictions, please refer to section E of the Legal Notices available under "License Terms and Conditions for Use of Software GmbH Products / Copyright and Trademark Notices of Software GmbH Products". These documents are part of the product documentation, located at <https://softwareag.com/licenses> and/or in the root installation directory of the licensed product(s).

Use, reproduction, transfer, publication or disclosure is prohibited except as specifically provided for in your License Agreement with Software GmbH.

Document ID: NATUX-NNATWEBIO-933-20251030

Table of Contents

Preface	vii
1 About this Documentation	1
Document Conventions	2
Online Information and Support	2
Data Protection	3
I About the Natural Web I/O Interface	5
2 About the Natural Web I/O Interface	7
What is the Natural Web I/O Interface?	8
Components of the Natural Web I/O Interface	8
Executing a Natural Application in a Web Browser	9
Client-Server Compatibility	10
Terminology	10
Differences in a SPoD Development Environment	11
Restrictions When Using the Natural Web I/O Interface with Natural Applications	11
Differences between the Natural Web I/O Interface Client and Terminal Emulation	13
II Installing and Configuring the Natural Web I/O Interface Server	15
3 Installing and Configuring the Natural Web I/O Interface Server	17
Installing the Natural Web I/O Interface Daemon	18
Setting Up the Natural Web I/O Interface Components	18
Directories	20
Configuring the Natural Web I/O Interface Daemon on Linux	21
PAM Module for OIDC	26
Logging Information	32
SSL Support	34
Working with the Linux Components of the Natural Web I/O Interface	35
III Installing the Natural Web I/O Interface Client	39
4 Prerequisites	41
Servlet Container	42
Natural for z/OS	42
Natural for Linux	42
Natural for Windows	43
Browser Prerequisites	43
5 Installing the Natural Web I/O Interface Client on Apache Tomcat	45
Installation Steps	46
Installation Verification	47
6 Migrating the Natural Web I/O Interface Client from IIS to Apache Tomcat	49
Before You Install the Natural Web I/O Interface Client	50
Installing the Natural Web I/O Interface Client on Apache Tomcat	51
Configuring the Natural Web I/O Interface Client on Apache Tomcat	51
IV Configuring the Client	55
7 About the Logon Page	57

Starting a Natural Application from the Logon Page	58
Examples of Logon Pages	58
Dynamically Changing the CICS Transaction Name, Host Name, and Port Number when Starting a Session	59
Specifying a Password in the Logon Page	60
Changing the Password in the Logon Page	60
Browser Restrictions	61
8 Natural Client Configuration Tool	63
Invoking the Configuration Tool	64
Session Configuration	65
Logging Configuration	73
Logon Page	73
Logout	73
9 Natural Web I/O Style Sheets	75
Name and Location of the Style Sheets	76
Editing the Style Sheets	76
Modifying the Position of the Main Output and of the PF Keys	76
Modifying the Font Size	77
Modifying the Font Type	78
Defining Underlined and Blinking Text	79
Defining Italic Text	80
Defining Bold Text	80
Defining Different Styles for Output Fields	81
Modifying the Natural Windows	81
Modifying the Message Line	82
Modifying the Background Color	82
Modifying the Color Attributes	83
Modifying the Style of the PF Key Buttons	84
JavaScript and XSLT Files	85
10 Starting a Natural Application with a URL	87
11 Configuring Container-Managed Security	89
About Container-Managed Security	90
Name and Location of the Configuration File for Security	90
Activating Security	90
Defining Security Constraints	91
Defining Roles	91
Selecting the Authentication Method	92
Configuring the UserDatabaseRealm	92
12 Configuring SSL	93
About Configuring SSL	94
Creating Your Own Trust File	94
Defining SSL Usage in the Configuration File	95
13 Logging	97
About Logging	98
Name and Location of the Configuration File for Logging	98

Invoking the Logging Configuration Page 98
Overview of Options for the Output File 100

Preface

This documentation is organized under the following headings:

Introduction	What is the Natural Web I/O Interface?
Installing and Configuring the Natural Web I/O Interface Server	How to install and configure the Natural Web I/O Interface server in a Linux environment.
Installing the Natural Web I/O Interface Client	How to install the Natural Web I/O Interface client on an application server or in a servlet container so that it can be used with the Natural Web I/O Interface server.
Configuring the Client	How to define the information that is to appear in the logon page.



Note: This documentation only explains how to install the Natural Web I/O Interface server in a Linux environment. For information on how to install it in a z/OS or Windows environment, see the Natural documentation for the appropriate platform.

1 About this Documentation

▪ Document Conventions	2
▪ Online Information and Support	2
▪ Data Protection	3

Document Conventions

Convention	Description
Bold	Identifies elements on a screen.
Monospace font	Identifies service names and locations in the format <code>folder.subfolder.service</code> , APIs, Java classes, methods, properties.
<i>Italic</i>	Identifies: Variables for which you must supply values specific to your own situation or environment. New terms the first time they occur in the text. References to other documentation sources.
Monospace font	Identifies: Text you must type in. Messages displayed by the system. Program code.
{ }	Indicates a set of choices from which you must choose one. Type only the information inside the curly braces. Do not type the { } symbols.
	Separates two mutually exclusive choices in a syntax line. Type one of these choices. Do not type the symbol.
[]	Indicates one or more options. Type only the information inside the square brackets. Do not type the [] symbols.
...	Indicates that you can type multiple options of the same type. Type only the information. Do not type the ellipsis (...).

Online Information and Support

Product Documentation

You can find the product documentation on our documentation website at <https://documentation.softwareag.com>.

Product Training

You can find helpful product training material on our Learning Portal at <https://learn.software-ag.com>.

Tech Community

You can collaborate with Software GmbH experts on our Tech Community website at <https://tech-community.softwareag.com>. From here you can, for example:

- Browse through our vast knowledge base.
- Ask questions and find answers in our discussion forums.
- Get the latest Software GmbH news and announcements.
- Explore our communities.
- Go to our public GitHub and Docker repositories at <https://github.com/softwareag> and <https://hub.docker.com/publishers/softwareag> and discover additional Software GmbH resources.

Product Support

Support for Software GmbH products is provided to licensed customers via our Empower Portal at <https://empower.softwareag.com>. Many services on this portal require that you have an account. If you do not yet have one, you can request it at <https://empower.softwareag.com/register>. Once you have an account, you can, for example:

- Download products, updates and fixes.
- Search the Knowledge Center for technical information and tips.
- Subscribe to early warnings and critical alerts.
- Open and update support incidents.
- Add product feature requests.

Data Protection

Software AG products provide functionality with respect to processing of personal data according to the EU General Data Protection Regulation (GDPR). Where applicable, appropriate steps are documented in the respective administration documentation.

I About the Natural Web I/O Interface

2 About the Natural Web I/O Interface

▪ What is the Natural Web I/O Interface?	8
▪ Components of the Natural Web I/O Interface	8
▪ Executing a Natural Application in a Web Browser	9
▪ Client-Server Compatibility	10
▪ Terminology	10
▪ Differences in a SPoD Development Environment	11
▪ Restrictions When Using the Natural Web I/O Interface with Natural Applications	11
▪ Differences between the Natural Web I/O Interface Client and Terminal Emulation	13

This chapter describes the purpose and the functions of the Natural Web I/O Interface.



Note: This introduction mainly describes how the Natural Web I/O Interface works in a runtime (production) environment. The section *Differences in a SPoD Development Environment* briefly explains the special version that is used in a SPoD development environment.

What is the Natural Web I/O Interface?

The Natural Web I/O Interface is used to execute Natural applications in a web browser. It fully supports the following:

- The display and input of Unicode characters. See *Unicode Input/Output Handling in Natural Applications* in the *Unicode and Code Page Support* documentation.
- Rich internet applications developed with Natural for Ajax.

Components of the Natural Web I/O Interface

The Natural Web I/O Interface consists of a server and a client.

Server

The Natural Web I/O Interface server enables you to use a browser as the I/O device for Natural applications. The server does the user authentication, creates the Natural session and handles the I/O between Natural and the client. The Natural Web I/O Interface server is installed on the same machine as the Natural application.

Client

The client handles the communication between the user's web browser and the Natural Web I/O Interface server. It converts the output from the Natural application to web pages, and returns the user input to Natural.


Two types of client are supported:

- Natural Web I/O Interface client for displaying character-based applications in the web browser. Maps with GUI controls are not supported in this case.
- Natural for Ajax for displaying rich internet applications in the web browser. For further information on this type of client, see the Natural for Ajax documentation.

The client is installed on a web/application server. This can be done on any machine in the network.

Executing a Natural Application in a Web Browser

The Natural Web I/O Interface receives data from a Natural application and delivers web pages to the user's web browser. This is illustrated in the following graphic:



The communication steps for executing a Natural application in the web browser are:

1. The user enters the address (URL) of a logon page in the web browser. The client then displays the logon page in the web browser.



Note: For information on how to invoke and configure the logon page, see *Configuring the Client*.

2. The user enters all required information for starting a Natural application into the logon page. This information is sent to the client.
3. The client asks the Natural Web I/O Interface server to start the requested Natural application for this user.
4. The Natural Web I/O Interface server checks the supplied user ID and password, creates a Natural session for the user and starts the Natural application.

5. The Natural application returns the first application screen which is then transferred via the Natural Web I/O Interface server to the client and finally as a web page to the web browser.

Different web browsers are supported. Note that cookies and JavaScript must be enabled in the web browser. For a list of the currently supported web browsers, see the browser prerequisites for the type of client that you are using.

Client-Server Compatibility

The following rules apply:

- The Natural Web I/O Interface server can work with any client that has the same or a higher protocol version.

If the server detects that the client is using a version that is lower than the server version, the server replies that the client is too old and the connection is closed.

- The client can work with any server that has the same or a lower protocol version.

If the client detects that the server is using a version that is lower than the client version, the client switches to the server version. However, new client functionality is not supported in this case.

- The Natural Web I/O Interface server must have the same protocol version as the Natural process that is started by the server. If Natural detects that the server is using a different protocol version, an error message is sent to the user and the connection is closed.

Terminology

On the different Natural platforms for which the Natural Web I/O Interface is supported, different techniques are used for implementing the server part of the Natural Web I/O Interface. On Natural for Linux, it is implemented as a daemon. On Natural for Windows, it is implemented as a service. On z/OS, it is implemented as a server. In this documentation, the general term “server” is therefore used for all different kinds of implementation.

Differences in a SPoD Development Environment

The previous sections of this introduction have described how the Natural Web I/O Interface works in a runtime (production) environment. This section briefly explains the differences in a SPoD development environment.

A special version of the Natural Web I/O Interface is used when working in a remote development environment with Natural for Windows (SPoD). In this case, the Natural Web I/O Interface is an integrated component which does not require a separate installation. The server is part of the Natural Development Server (NDV), and the client is part of Natural Studio. Other than in the runtime environment, the screen is not displayed in a browser but in a normal window. Rich GUI pages created by Natural for Ajax are not supported in the development environment.

It is important that I/O via the Natural Web I/O Interface has been enabled on the Natural host. Otherwise, the Natural Web I/O Interface cannot be invoked. See also *Unicode Input/Output Handling in Natural Applications* in the *Unicode and Code Page Support* documentation.

Restrictions When Using the Natural Web I/O Interface with Natural Applications

There are several restrictions when using the Natural Web I/O Interface with Natural applications on Linux, z/OS or Windows hosts.



Note: The term “application” refers to application software. It does not refer to system software or software for development.

The following restrictions apply:

- **GUI controls**

GUI controls are not supported: dialogs, buttons, radio buttons, list boxes, list views, check boxes etc. The Natural Web I/O Interface only supports Natural applications developed without GUI controls.

- **File transfer**

File transfer (for example, with the `DOWNLOAD` statement) is not supported by the Natural Web I/O Interface.

- **Runtime errors**

This restriction applies to older Natural versions on Linux and Windows. As of version 6.3.3, this restriction no longer applies.

Runtime errors in Natural applications are not handled by the Natural Web I/O Interface. This leads to a loss of the session. Bypass: use the Natural system variable *ERROR-TA to handle the error.

```
DEFINE DATA
LOCAL
1 ERR_INFO
  2 ERR_NR(N5)
  2 ERR_LINE(N4)
  2 ERR_STAT(A1)
  2 ERR_PNAM(A8)
  2 ERR_LEVEL(N2)
END-DEFINE
INPUT ERR_INFO
DISPLAY ERR_INFO
TERMINATE
END
```

■ **Terminal commands**

Terminal commands are not supported. They do not work when entered in the Natural Web I/O Interface client.

■ **Natural system variable *INIT-ID**

When using the Natural Web I/O Interface client with Natural applications on Linux, z/OS or Windows hosts, the Natural system variable *INIT-ID will not be filled with a value for the terminal type. On Linux and Windows, it will contain the value "notty". On z/OS, it will contain a session ID that is unique on that server.

The following restrictions apply to Natural on Linux and Windows hosts (z/OS does not have these restrictions):

■ **Return to the Natural main screen**

You must not use Natural applications that return to the Natural main screen as this leads to wrong screen display and a loss of the session.

■ **Natural editors and utilities**

You must not use Natural utilities such as SYSMAIN or SYSDDM and editors such as the program editor as this leads to wrong screen display and a loss of the session.

■ **Natural system commands**

You must not use any Natural system command such as CATAL, FIND, GLOBALS, HELP, KEY, LIST, RETURN, SCAN, SETUP or XREF as this leads to wrong screen display and a loss of the session.

Differences between the Natural Web I/O Interface Client and Terminal Emulation

The Natural Web I/O Interface client runs as an HTML terminal emulator inside a browser control. The look and feel of the Natural Web I/O Interface client display is quite similar to that of the regular terminal (emulation), but there are some differences due to browser functionality:

- A double-click with the mouse pointer on any field simulates the `ENTER` key.
- It is not possible to position the cursor outside the range of input and output fields.
- The cursor can be moved with the left and right arrow keys within one input field. It is also possible to jump from one input field to another using the left, right, up and down arrow keys.
- The insert mode can be switched on and off using the `INSERT` key.
- For Unicode character sets (type `U`; for example, Chinese), one character may require more space than an ordinary alphanumeric character, because the Unicode character representation is proportional. The application design must take this into account, because Natural is based on characters with fixed width. For input fields it is possible to scroll within the field, but for output fields there may not be sufficient space to display the Unicode characters. The display length for a field can be controlled by the session parameter `DL`.
- Type-ahead mode is not supported.
- Paste in overwrite mode is not supported.
- Key schemes are fixed; keys such as the right `CTRL` key and the `ENTER` key on the numeric pad are no longer definable.
- Screen update is slower since the complete screen is sent rather than updates.
- The blink attribute is not supported in Internet Explorer.
- The keys `PF1` through `PF12` are simulated by the key combinations `F1` through `F12`.
- The keys `PF13` through `PF24` are simulated by the key combinations `SHIFT+F1` through `SHIFT+F12`.
- The keys `PF25` through `PF36` are simulated by the key combinations `CTRL+F1` through `CTRL+F12`.
- The keys `PF37` through `PF48` are simulated by the key combinations `ALT+F1` through `ALT+F12`.
- The program attention keys (`PA1`, `PA2` and `PA3`) are simulated by the key combinations `CTRL+SHIFT+F1`, `CTRL+SHIFT+F2`, `CTRL+SHIFT+F3`.
- The clear key is simulated by `CTRL+SHIFT+F4`.

IBM z/OS Only

- The terminal screen size is controlled by the Natural profile parameter `TMODEL`. The default setting `TMODEL=0` means 24 lines and 80 columns.
- There is no `ATTN` (attention interrupt) key, no `RESET` key and no `EEOF` (erase end of file) key.

VT Only

The I/O occurs in block mode. Therefore, the Natural program will only react when a function key is pressed.

II Installing and Configuring the Natural Web I/O Interface Server

3 Installing and Configuring the Natural Web I/O Interface

Server

- Installing the Natural Web I/O Interface Daemon 18
- Setting Up the Natural Web I/O Interface Components 18
- Directories 20
- Configuring the Natural Web I/O Interface Daemon on Linux 21
- PAM Module for OIDC 26
- Logging Information 32
- SSL Support 34
- Working with the Linux Components of the Natural Web I/O Interface 35

On Linux, the server part of the Natural Web I/O Interface runs in the background as a so-called daemon.

Installing the Natural Web I/O Interface Daemon

The Natural Web I/O Interface daemon is installed with Natural for Linux if the corresponding option is set during the installation. See the *Installation* documentation for further information.

Setting Up the Natural Web I/O Interface Components

Setting up the Natural Web I/O Interface on Linux consists of the following steps:

- [Step 1: Stop the Natural Web I/O Interface Daemons](#)
- [Step 2: Establish the Environment](#)
- [Step 3: Install Natural and the Natural Web I/O Interface](#)
- [Step 4: Check the Environment Variables for the Natural Web I/O Interface](#)
- [Step 5: Read the READ_NWO Files](#)

Step 1: Stop the Natural Web I/O Interface Daemons

This step is only required for an upgrade installation. It is not required when you install the Natural Web I/O Interface for the first time.

1. Stop the *nwosrvd* process using the following command:

```
nwosrvd.sh portnumber stop
```

Or use the script `$NAT_HOME/INSTALL/nwosrvd.bsh` which will be generated during the Natural Web I/O Interface installation for a specified port.

```
nwosrvd.bsh stop
```

2. Repeat the above command (with an adapted port in script *nwosrvd.bsh*, if applicable) for each Natural Web I/O Interface service that is needed.

Step 2: Establish the Environment

Besides the settings for the Natural environment, additional settings for the Natural Web I/O Interface environment must be set. Ensure that the environment settings for Natural are set by the *natenv* environment script. The *nwoenv* environment script is called by the *natenv* environment script. Therefore, the Natural Web I/O Interface environment will be set with the Natural environment if it is set after the Natural Web I/O Interface installation.

If the Natural Web I/O Interface environment is to be separate from the Natural environment, use the shell script *nwoenv* or *nwoenv.csh* by entering one of the following commands:

```
source nwoenv
```

```
source nwoenv.csh
```

These scripts can be found after the installation in *\$NAT_HOME/INSTALL*.

Step 3: Install Natural and the Natural Web I/O Interface

The Natural Web I/O Interface can be selected in the **Choose Packages** screen during the Natural installation.

Optionally, you may install a runlevel script to start/stop a Natural Web I/O Interface daemon when the machine starts/stops.

After the Natural installation has finished, the Natural Web I/O Interface must be activated by starting Natural through a Natural Web I/O Interface client on Windows.

When a runlevel script is used, the Natural Web I/O Interface daemon can only be administered by the user "root".

When you install Natural with the Natural Web I/O Interface, the directory *\$NAT_HOME/nwo/\$NWONODE* is created. The template files located in *\$NAT_HOME/nwo/node-name* are then copied to this new directory.

Step 4: Check the Environment Variables for the Natural Web I/O Interface

The Natural Web I/O Interface-specific settings are shown below:

Environment Variable	Description
NWODIR	The home directory for the product located at <i>\$NAT_HOME/nwo</i> .
NWONODE	The name of the node (machine) on which the Natural Web I/O Interface is installed.
NWO_SRVDCONF	The configuration file <i>\$NAT_HOME/nwo/\$NWONODE/nwosrvd.conf</i> for the Natural Web I/O Interface daemon.

Environment Variable	Description
NWO_TIMEOUT	The maximum time, in seconds, that the Natural Web I/O Interface daemon will wait for a response. "0" means no timeout. The Natural Web I/O Interface daemon will terminate when it receives the timeout.

Step 5: Read the READ_NWO Files

1. Access the directory `$NAT_HOME/nwo` and check the files `READ_NWO.TXT` and `READ_NWO.FIX` for any version-specific installation considerations concerning the particular platform.
2. Add the services as described in the file `READ_NWO.TXT`.

Directories

The following directories are created when Natural is installed together with the Natural Web I/O Interface on a Linux system:

Directory	Description
<code>\$NAT_HOME</code>	Top-level Natural directory.
<code>\$NATDIR</code>	Only used for compatibility with previous versions. Top-level Natural directory.
<code>\$NATDIR/\$NATVERS</code>	Only used for compatibility with previous versions. The version subdirectory has been removed. Since <code>\$NATVERS</code> is set to ".", it equals <code>\$NAT_HOME</code> and <code>\$NATDIR</code> .
<code>\$NWODIR</code>	Directory with the Natural Web I/O Interface components for the current version.
<code>\$NWONODE</code>	Contains the name of the machine (<code>uname -n</code>).
<code>\$NAT_HOME/INSTALL</code>	Shell scripts and environment files for the Natural Web I/O Interface (<code>nwoenv</code> , <code>nwoenv.csh</code>).
<code>\$NWODIR/bin</code>	Natural Web I/O Interface executable files (<code>nwosrvd</code> , <code>nwosrvd.tr</code>).
<code>\$NWODIR/node-name</code>	Contains the template files (<code>nwosrvd.sh</code> , <code>nwo.sh</code> , <code>nwosrvd.conf</code>).
<code>\$NAT_HOME/nwo/\$NWONODE</code>	Work directory, contains the configuration files (<code>nwosrvd.sh</code> , <code>nwo.sh</code> , <code>nwosrvd.conf</code>).



Note: The above table lists the most important directories and files.

Configuring the Natural Web I/O Interface Daemon on Linux

When the Natural installation has finished, the directory `$NAT_HOME/nwo/$NWONODE` contains the files `nwosrvd.conf`, `nwosrvd.sh` and `nwo.sh`.

The configuration of the Natural Web I/O Interface daemon can be done using the Natural Web I/O Interface daemon commands or by editing the configuration file `nwosrvd.conf`.

The following topics are covered below:

- [Natural Web I/O Interface Daemon Commands](#)
- [nwosrvd.conf - Configuration File for the Natural Web I/O Interface Daemon](#)
- [nwosrvd.sh - Shell Script for Starting and Stopping the Natural Web I/O Interface Daemon](#)
- [nwo.sh - Shell Script for Starting Natural](#)
- [Environment Variables](#)

Natural Web I/O Interface Daemon Commands

The following commands can be specified at the Linux command prompt:

Command	Description
<code>nwosrvd -help</code>	Shows all available Natural Web I/O Interface daemon commands and subcommands.
<code>nwosrvd -v</code>	Shows the version of the Natural Web I/O Interface daemon.
<code>nwosrvd nnnn</code>	Defines the listening port number.
<code>nwosrvd -show</code>	Shows the configuration of the Natural Web I/O Interface daemon.
<code>nwosrvd -config keys</code>	Changes the configuration of the Natural Web I/O Interface daemon. The following keys can be specified: <ul style="list-style-type: none"> <code>-host=hostname</code> The host name used. <code>-passparam=parameters</code> The message defined with this key is saved in the Parameters key of the configuration file <code>nwosrvd.conf</code>, section [PasswdArguments]. <code>-passwd=message</code> The message defined with this key is saved in the EnterOldPassword key of the configuration file <code>nwosrvd.conf</code>, section [PasswdMessages]. <code>-passnew=message</code> The message defined with this key is saved in the NewPassword key of the configuration file <code>nwosrvd.conf</code>, section [PasswdMessages]. <code>-passreenter=message</code> The message defined with this key is saved in the ReEnterNewPassword key of the configuration file <code>nwosrvd.conf</code>, section [PasswdMessages].

Command	Description
	<p><code>-passsuccess=<i>message</i></code> The message defined with this key is saved in the <code>PasswordSuccessful</code> key of the configuration file <code>nwosrvd.conf</code>, section <code>[PasswdMessages]</code>.</p> <p><code>-logging=<i>option</i></code> The option defined with this key is saved in the <code>Logging</code> key of the configuration file <code>nwosrvd.conf</code>, section <code>[Miscellaneous]</code>.</p> <p><code>-ssl=[yes no]</code> The option defined with this key is saved in the <code>ssl</code> key of the configuration file <code>nwosrvd.conf</code>, section <code>[SSL]</code>.</p> <p><code>-pam=[yes no]</code> The option defined with this key is saved in the <code>pam</code> key of the configuration file <code>nwosrvd.conf</code>, section <code>[PAM]</code>. PAM itself also has a configuration file or section (depends on the PAM implementation); the PAM configuration name must be <code>nwosrvd</code>.</p>

nwosrvd.conf - Configuration File for the Natural Web I/O Interface Daemon

The configuration file `nwosrvd.conf` contains information needed for the Natural Web I/O Interface daemon. It has the following content:

```
[Miscellaneous]
Logging=I

[PasswdArguments]
Parameters=

[PasswdMessages]
EnterOldPassword=Enter existing login password:
NewPassword=New Password:
ReEnterNewPassword=Re-enter new Password:
PasswordSuccessful=passwd: password successfully changed for*

[SSL]
ssl=no

[PAM]
pam=no

[HA]
ha=no
```

Section in Configuration File	Description
[Miscellaneous]	<p>The key <code>Logging</code> is used to define the amount of logging information that is to be reported. One of the following options can be specified:</p> <p>E for errors. W for warnings. I for information.</p> <p>See also Logging Information.</p>
[Host]	The hostname used. (optional)
[PasswdArguments]	The key <code>Parameters</code> is used to define any additional parameter(s) that have to be passed to the <code>passwd</code> command.
[PasswdMessages]	<p>The keys in this section define the messages that are to be returned by the system (<code>passwd</code> command) when a user changes the password. If any of these messages is not identified by the daemon, an error will be returned to the client.</p> <p>Password Mechanism</p> <p>The password and new password are encrypted on the client side and decrypted on the Linux side. A maximum of 8 characters is allowed.</p> <p>The daemon checks whether user name and password are correct for the system. If a new password is sent, the daemon changes the password by calling the Linux command <code>passwd</code>.</p>
[SSL]	<p>The key <code>ssl</code> is used to define whether the SSL protocol is to be used. One of the following values can be specified: "yes" or "no".</p> <p>See also SSL Support.</p>
[PAM]	<p>The key <code>pam</code> is used to define whether the PAM (Pluggable Authentication Modules) mechanism is to be used. One of the following values can be specified: "yes" or "no".</p> <p>PAM itself also has a configuration file or section (depends on the PAM implementation); the PAM configuration name must be <code>nwosrzd</code>.</p>
[HA]	The key <code>ha</code> is used to define whether HA protocol is to be used. One of the following values can be specified: "yes" or "no".

nwosrzd.sh - Shell Script for Starting and Stopping the Natural Web I/O Interface Daemon

The shell script `nwosrzd.sh` is used to start and stop the Natural Web I/O Interface daemon. For further information, see [Starting and Stopping the Natural Web I/O Interface Daemon](#).

nwo.sh - Shell Script for Starting Natural

In order to start a Natural session, the Natural Web I/O Interface service executes a shell script. The shell script prepares the environment for the Natural session and eventually starts Natural. It must therefore contain all environment settings needed to run the Natural session.

The shell script receives certain parameters from the Natural Web I/O Interface client. The parameters can either be evaluated by the shell script itself or passed on to Natural. A client who wants to start a Natural session can specify the shell script to be used.

The shell script *nwo.sh* is called from the Natural Web I/O Interface daemon in order to start a Natural session. It has the following content:

```
#!/bin/sh

echo "Number of arguments $# " > nwo.log

IPAddress=""
ClientId=""
CodePage=""
CustomParameters=""
NaturalParameters=""

if [ "$1" != "null" ]
then
  IPAddress="$1"
fi

if [ "$2" != "null" ]
then
  ClientId="$2"
fi

if [ "$3" != "null" ]
then
  CodePage="$3"
fi

if [ "$4" != "null" ]
then
  CustomParameters="$4"
fi

if [ "$5" != "null" ]
then
  NaturalParameters="$5"
fi

#echo "IP Address="$IPAddress >> nwo.log
#echo "Client Id="$ClientId >> nwo.log
```

```
#echo "Code Page="$CodePage >> nwo.log
#echo "Custom Parameters="$CustomParameters >> nwo.log
#echo "Natural Parameters="$NaturalParameters >> nwo.log
#echo "NWO_BROWSER_IO="$NWO_BROWSER_IO >> nwo.log

$NAT_HOME/bin/natural $NaturalParameters etid=$$ > /dev/null 2>&1
```

You have to create such a shell script for each Natural application. It can have any name and it must be located in a directory which is defined in the environment variable `PATH`.

The name of the shell script is taken from the configuration file for the session. It is taken from the configuration file section that is defined for the session that the user has selected in the logon page. For further information, see [Configuring the Client](#).

Arguments

The shell script will receive the following arguments:

Order	Argument	Description
1	IPAddress	The client IP address from where the session is opened. Note: If there is a proxy, this will not be the IP address of the client workstation. Instead, it will be the IP address of the proxy.
2	ClientId	The user name from the logon page is passed as the client ID.
3	CodePage	The encoding that is defined in the configuration file for the session. This value can be used to set the Natural system variable *CODEPAGE.
4	CustomParameters	From the logon page, it is possible to pass any values to the script in order to execute any desired action. Example: you pass a small text to the script which describes an error. When the script receives this error text, it sends it as an e-mail to the administrator.
5	NaturalParameters	These can be any Natural parameters. The parameters are either defined in the configuration file for the session, or they are entered in the logon page. The following is an example of the corresponding entry in the configuration file: <natural_parameter>parm=nwoparm\ stack=(logon\ mylib;start-program;fin)<natural_parameter> The language that is selected in the logon page is added as the first element to the Natural parameters in the form "ulang=x".

Arguments 1 to 4 can be used to audit the client, to allow to run an application from a specific PC (identifying the IP address), to build statistics, to do special actions, etc.

Environment Variables

In the shell script, several environment variables can be set for the Natural session that is started by the daemon:

NWO_ENABLE_ACK=["YES"|"NO"]

This environment variable is used for asynchronous screens (SET CONTROL N).

YES When asynchronous screens are sent to the client, Natural will wait to receive an ACK package before the next screen can be sent.

NO No waiting between asynchronous screens. Default value.

NWO_PF_MSG_LINES_NATIVE_FORMAT=["YES"|"NO"]

This environment variable defines how the PF keys and the message line are to be shown.

YES The PF key prompting lines and the message line are shown as output text, as in the native Linux environment.

NO The PF keys are rendered as buttons and the message line is rendered as a special message line element. Default value.

NWO_TIMEOUT=[*number-of-seconds*]

The maximum time, in seconds, that Natural waits to receive any input from the client before it closes the session. If the number of seconds is "0", Natural waits infinitely (no timeout). The default value is "0".

Error NAT5466 is returned at timeout. In Natural, the application can handle this error and decide how to continue or terminate.

PAM Module for OIDC

PAM_OIDC is a Pluggable Authentication Module (PAM) that authenticates users with an OpenID Connect (OIDC) token.

- [Requirements](#)
- [Files and Folders](#)
- [Authentication Module](#)

- [Account Module](#)

Requirements

A version of OpenSSL 3 or OpenSSL 1.1.1 must be installed on the system.

For version 1.1.1, the `pam_oidc.so` from the subfolder `openssl1.1.1` should be used.

Files and Folders

The PAM module is located at `<install-dir>/Natural/INSTALL/pam`.

The package brings along the following resources:

<code>readme.txt</code>	A readme with instructions.
<code>nwosrod_example</code>	An example configuration for <code>/etc/pam.d/nwosrod</code> .
<code>create_user.sh</code>	Example script for the <code>pam_oidc</code> account module. Automatically creates a local user account for <code>\$PAM_USER</code> if it does not already exist, with secure logging and error handling.
<code>pam_oidc.so</code>	Contains the Pluggable Authentication Modules for OpenID Connect build for OpenSSL 3.
<code>openssl1.1.1/pam_oidc.so</code>	Contains the Pluggable Authentication Modules for OpenID Connect build for OpenSSL 1.1.1.

Authentication Module

This section describes the configuration and features of the PAM authentication module (`auth`) provided by `pam_oidc`. In typical `pam.d` configurations, the `pam_oidc` module must be listed first with the `auth` type, as authentication is always the initial step in the PAM stack. Additional modules or account checks can follow as needed.

- [Supported Signing Algorithms](#)
- [Configuration Options](#)
- [JSON Web Key Set \(JWKS\)](#)
- [Configuration of userClaim and userClaimRegex](#)
- [Leeway](#)
- [Logging](#)
- [Configuration](#)

- [Example Configuration for Google](#)

Supported Signing Algorithms

The following signing algorithms are supported:

RS256
 RS384
 RS512
 PS256
 PS384
 PS512
 ES256
 ES384
 ES512

Configuration Options

jwtks	Required	Path to the JSON Web Key Set (JWKS) file.
issuer	Required	The issuer URL of the OpenID Connect provider.
aud	Required	The audience claim that the token must contain.
userClaim	Required	The claim that contains the username.
userClaimRegex	Optional	A regex to extract the username from the userClaim.
azp	Optional	The party to which the ID Token was issued.
acr	Optional	Authentication Context Class Reference of the token.
iatLimit	Optional	Limit the max age of the iat. The value is in seconds. 0 is interpreted as no limit. If the iat is older than iatLimit, the token is rejected.
maxAge	Optional	The maximum age of the token in seconds. If the token is older, it will be rejected.
verbose	Optional	If verbose is set to true, additional system logs are written.
logFile	Optional	Writes logs to a specified file instead of to the system logs.

JSON Web Key Set (JWKS)

A JSON Web Key Set (JWKS) is a JSON document that contains a set of public keys used to verify the signatures of tokens.

A JWKS is obtained from an OIDC provider. Typically, it is available at a well-known URL, following a pattern such as *https://example.com/.well-known/openid-configuration*, which points to the JWKS URL. In the configuration, the JWKS URL is specified in the `jwtks_uri` field.



Note: Providers may update their JWKS over time, so it is important to fetch the latest version periodically. Also, ensure that the JWKS file has appropriate permissions to prevent unauthorized access.

Example - Download JWKS:

```
curl -o exampleJwks.json https://example.com/protocol/openid-connect/certs
```

Example - Download Google JWKS:

```
curl -o googleJwks.json https://www.googleapis.com/oauth2/v3/certs
```

Configuration of `userClaim` and `userClaimRegex`

To validate if the PAM user and the user that issues the tokens match, *pam_oidc.so* needs a claim that includes the user.

If the user is only part of the user claim, the `userClaimRegex` configuration can be used to extract the username. The username is the sum of all regex capturing groups.

Example:

```
(\w*)@softwareag.com
johnsmith@softwareag.com --> User: johnsmith
↵
```

Example:

```
(\w*).(\w*)@softwareag.com
John.Smith@softwareag.com --> User: JohnSmith
↵
```

Leeway

Leeway is a time buffer used to account for small differences in system time between the token issuer and the token receiver. It allows for a tolerance when verifying timestamps in the token, such as the validity period. The *pam_oidc* module uses a leeway of 60 seconds.

Logging

The *pam_oidc.so* module uses the Linux Syslog for logging. By default, only a single Syslog entry is added. This entry provides information on whether the authentication was successful or not. Should the authentication fail, the reason will be written into the logs.

If you need additional information, you can use the `verbose` option. The token itself will never be written to the logs.

With a configuration in *rsyslog.d*, it is possible to redirect the syslog output of the *pam_oidc.so*.

Example configuration for */etc/rsyslog.d/pam_oidc.conf*:

```
:msg, contains, "pam_oidc" /var/log/pam_oidc.log
& stop
```

You need to create the log file manually and set the appropriate permissions.

Restart the *rsyslog* service to apply the changes.

Configuration

A PAM service can be added in */etc/pam.d/<service_name>*.

General configuration:

```
auth required pam_oidc.so <arguments>
account required pam_oidc.so <arguments>
```

Example Configuration for Google

```
auth required pam_oidc.so \
  jwks=/tmp/googleJwks.json \
  issuer=https://accounts.google.com \
  userClaim=email aud=account \
  userClaimRegex=(.*)@.*\.com
↵
```

Account Module

This section describes the configuration and features of the PAM account module (`account`) provided by `pam_oidc`. This module is typically used after authentication to perform additional checks or actions, such as user provisioning or permission management. In `pam.d` configurations, the `pam_oidc` module can be listed with the `account` type following the initial `auth` entry.

- [Configuration Options](#)
- [runScriptAsUser Requirements](#)
- [Security](#)
- [Example Account Module Configuration](#)

Configuration Options

<code>scriptPath</code>	Required	Path to the script to be executed during the account phase.
<code>scriptArgs</code>	Optional	Arguments to pass to the script. Arguments are separated by commas.
<code>runScriptAsUser</code>	Optional	User under whose privileges the script should be executed.
<code>logFile</code>	Optional	Writes logs to a specified file instead of the system logs.

runScriptAsUser Requirements

The `runScriptAsUser` option can only be used if the calling process is running as root or has the necessary Linux capabilities to change user and group IDs (for example, `CAP_SETUID` and `CAP_SETGID`).

To grant these capabilities to the `pam_oidc` module without running as root, you can use the following command:

```
sudo setcap cap_setuid,cap_setgid+ep /path/to/exe
```

Security

For security reasons, the script specified by `scriptPath` must have permissions set to 750 (`rwxr-x---`). This ensures that only the owner and members of the group can execute the script, but only the owner can modify it. Other users have no access. This approach allows trusted group members to execute shared scripts, while only a single user (the owner) can change the script content.

Example Account Module Configuration

Below is an example of how to configure the `pam_oidc` module for the account phase in your `/etc/pam.d/<service_name>` file. This configuration executes a user provisioning script as a specific user and writes logs to a dedicated file.

```
account required pam_oidc.so \
    scriptPath=/path/to/create_user.sh \
    runScriptAsUser=root \
    logFile=/tmp/pam_oidc.account.txt
```

<code>scriptPath</code>	Path to the script that will be executed during the account phase.
<code>runScriptAsUser</code>	The user under whose privileges the script will be executed (requires root or appropriate capabilities).
<code>logFile</code>	Path to the log file where output will be written instead of syslog.



Note: Make sure the `pam_oidc` module has the necessary permissions or capabilities if you use `runScriptAsUser` (see [runScriptAsUser Requirements](#)).

Logging Information

The logging information system reports errors, warnings and/or session information, depending on the option that has been defined with the following [Natural Web I/O Interface daemon command](#):

```
nwosrzd -config -logging=option
```

option can be one of the following:

Option	Description
E	<p>Error.</p> <p>When this option is specified, the Natural Web I/O Interface daemon reports only errors.</p> <p>In the case of an error, the daemon usually exits immediately.</p>
W	<p>Warning.</p> <p>When this option is specified, the Natural Web I/O Interface daemon reports errors and warnings for uncritical errors.</p> <p>In the case of a warning, the daemon continues to run.</p>
I	Information.

Option	Description
	When this option is specified, the Natural Web I/O Interface daemon reports errors, warnings and information. The information messages allow to check the session parameters, IP address, etc.

Help information, for example, on how to run, configure and install the Natural Web I/O Interface daemon is always provided. The messages which inform you when the daemon has been started or stopped are also part of the help information.

To find out which logging option is currently active, enter the following Natural Web I/O Interface daemon command:

```
nwosrvd -show
```

The logging messages are shown directly for the standard output. The format of the messages is as in the following example:

```
%NWOSRVD-E: 18.01.2008 14:55:20 NWO_SRVDCONF is not established.
```

The following information is provided:

- %NWOSRVD is the internal name of the Natural Web I/O Interface daemon.
- The message type is shown directly after %NWOSRVD. It can be one of the following: -E (error), -W (warning), -I (information), or -H (help).
- Date and time when the message was reported.
- Any text or message which pertains to the error, warning, information or help.

If you want to save these messages, you have to redirect the standard output to a file.

Example for csh:

```
nwosrvd 5454 >& nwosrvd_5454.log
```

Example for sh, ksh and bsh:

```
nwosrvd 5454 >& nwosrvd_5454.log 2>&1
```

SSL Support

SSL is used for a secure connection between the Natural Web I/O Interface server and the Natural Web I/O Interface client or Natural for Ajax. Server authentication cannot be switched off. A certificate and a private key is always required on the server.

To establish an SSL connection, you have to proceed as described in the following topics:

- [Creating an SSL Certificate and a Private Key](#)
- [Configuring the Daemon](#)
- [Configuring the Client](#)

Creating an SSL Certificate and a Private Key

To create and use an SSL certificate and a private key on the server, proceed as described below.

1. Adapt the example configuration file *openssl.cnf* to your needs.



Note: *openssl.cnf* is delivered in `<install-dir>/common/security/openssl` and *openssl* is delivered in `<install-dir>/common/security/openssl/bin`.

2. Set the environment variable so that it points to the file *openssl.cnf*:

```
set OPENSSL_CONF=<install-dir>/common/security/openssl/openssl.cnf
export OPENSSL_CONF;
```

3. Generate a certificate signing request:

```
openssl req -new > server.cert.csr
```

4. Generate a private RSA key:

```
openssl rsa -in privkey.pem -out server.cert.key
```

5. Generate a self-signed certificate:

```
openssl x509 -in server.cert.csr -out server.cert.crt -req -signkey ↵
server.cert.key -days 365
```

It is important that the name of the generated certificate is *server.cert.crt* and that the name of the generated private key is *server.cert.key*.



Note: The certificate can be self-signed or it can be signed by a CA (Certificate Authority) such as VeriSign.

6. Put the generated files into the same directory as the scripts which start the Natural Web I/O Interface server.

Configuring the Daemon

After you have created an SSL certificate and a private key as described above, proceed as follows:

1. Change the configuration of the Natural Web I/O Interface daemon using the following command:

```
nwosrvd -config -ssl=yes
```

2. Restart the Natural Web I/O Interface daemon.

See also [Configuring the Natural Web I/O Interface Daemon on Linux](#).

Configuring the Client

After you have configured the daemon as described above, you have to import the generated *server.cert.crt* file to a truststore on the client. For information on how to do this for the Natural Web I/O Interface client, see [Configuring SSL](#). If you are using Natural for Ajax as the client, see [Configuring SSL in the Natural for Ajax documentation](#).

Working with the Linux Components of the Natural Web I/O Interface

The Linux components of the Natural Web I/O Interface are used to start the Natural applications linked with the Natural Web I/O Interface library.

The following topics are covered below:

- [Starting and Stopping the Natural Web I/O Interface Daemon](#)
- [Starting a Natural Application](#)

Starting and Stopping the Natural Web I/O Interface Daemon

The Natural Web I/O Interface daemons are responsible for accepting new sessions.

Since the daemon checks the user name and password, the following permissions must be set as follows (for setting the permissions, you must be super-user):

```
chmod 6755 nwosrvd.sh
```

```
chown root nwosrvd.sh
```

The Natural installation attempts to set permissions and owner. However, you have to verify this before you start the Natural Web I/O Interface daemon.

The daemon can be started and stopped using the following command:

```
cd $NAT_HOME/nwo/$NWONODE
nwosrvd.sh portnumber [start|stop]
```

Alternatively:

```
cd $NAT_HOME/INSTALL
nwosrvd.bsh [start|stop]
```



Note: The daemon must be started on a port which is not yet used.

The shell script you have created must be in the same directory as the *nwosrvd.sh* script. It will be used by the Natural Web I/O Interface (configuration file for the session; see [Configuring the Client](#)). The following is an example of the corresponding entry in the configuration file:

```
<natural_program>your-shell-script.sh</natural_program>
```

Starting a Natural Application

Almost any Natural application can be used with the Natural Web I/O Interface. See also [Differences between the Natural Web I/O Interface Client and Terminal Emulation](#).

To start a new Natural application with the Natural Web I/O Interface, proceed as follows:

1. Create a new parameter file from NWOPARM using the Configuration Utility.
2. In this new parameter file, modify the STACK command as follows:

```
logon library; startprogram; fin
```



Note: Only “real” Natural applications can be used. The Natural **Main Menu** cannot be used as a Natural application.

Add the new service as follows:

1. Look for a port number which is not yet used.
2. Create a new shell script (similar to *nwo.sh*) for starting the Natural application:

```
cd $NAT_HOME/nwo/$NWONODE
copy nwo.sh your-shell-script.sh
vi your-shell-script.sh
```

You have to decide which (last) line you will use in the script. Use one of the following:

```
$NAT_HOME/bin/natural parm=parameter-file etid=$$ >output-file 2>&1
```

```
$NAT_HOME/bin/natural $5 etid=$$ >output-file 2>&1
```

When using the line with `parm=parameter-file`, the above step in which you modify the `STACK` command is mandatory.

When using `$5`, the Natural parameter (`parameter-file` and `STACK` command) is taken from the configuration file for the session (see [Configuring the Client](#)). The following is an example of the corresponding entry in the configuration file:

```
<natural_parameter>parm=myparm stack=(logon mylib;menu;fin)<natural_parameter>
```

3. If you want to define special settings for the Natural session, you can set the environment variables in your shell script. See [above](#).
4. Set the permissions for the shell script which starts the service as follows:

```
chmod 775 script-name
```

The service is now available for use with a PC.

III

Installing the Natural Web I/O Interface Client

This part explains how to install the Natural Web I/O Interface client on Tomcat so that it can be used with the server part of the Natural Web I/O Interface that is running in a Natural for z/OS, Natural for Linux or Natural for Windows runtime environment.

The following topics are covered:

[Prerequisites](#)

[Installing the Natural Web I/O Interface Client on Apache Tomcat](#)

[Migrating the Natural Web I/O Interface Client from IIS to Apache Tomcat](#)

4 Prerequisites

- Servlet Container 42
- Natural for z/OS 42
- Natural for Linux 42
- Natural for Windows 43
- Browser Prerequisites 43

Servlet Container

The following servlet container is supported. The servlet container is not delivered with the Natural Web I/O Interface. It can be obtained from the location indicated below, according to its license terms.

Apache Tomcat 9 and 10 (see <http://tomcat.apache.org/>).

Natural for z/OS

If you want to use the Natural Web I/O Interface client with Natural for z/OS, the following must be installed:

- Natural for z/OS Version 8.2.5 or above, and
- the Natural Web I/O Interface server.

For detailed information, see:

- the *Installation* documentation for the different operating systems which is provided for Natural for z/OS;
- the section *Installing and Configuring the Natural Web I/O Interface Server* in the version of this *Natural Web I/O Interface* documentation which is provided for Natural for z/OS.

Natural for Linux

If you want to use the Natural Web I/O Interface client with Natural for Linux and Cloud, the following must be installed:

- Natural on Linux and Cloud Version 9.2.1 or above, and
- the Natural Web I/O Interface server and daemon.

For detailed information, see:

- the *Installation* documentation which is provided for Natural for Linux;
- the section *Installing and Configuring the Natural Web I/O Interface Server* in the version of this *Natural Web I/O Interface* documentation which is provided for Natural for Linux.

Natural for Windows

If you want to use the Natural Web I/O Interface client with Natural for Windows, the following must be installed:

- Natural for Windows Version 9.2.1 or above, and
- the Natural Web I/O Interface server and service.

For detailed information, see:

- the *Installation* documentation which is provided for Natural for Windows;
- the section *Installing and Configuring the Natural Web I/O Interface Server* in the version of this *Natural Web I/O Interface* documentation which is provided for Natural for Windows.

Browser Prerequisites

Supported browsers in this version are:

Microsoft Edge (Chromium) - current versions

Mozilla Firefox Extended Support Release – current versions⁽¹⁾

Google Chrome – current versions⁽²⁾

Notes:

⁽¹⁾ Only the Extended Support Releases of Mozilla Firefox are explicitly supported. Due to frequent upgrades of the Mozilla Firefox consumer release, the compatibility of Natural Web I/O Interface client with future versions of Mozilla Firefox cannot be fully guaranteed. Possible incompatibilities will be removed during the regular maintenance process of Natural Web I/O Interface client.

⁽²⁾ Due to frequent version upgrades of Google Chrome, compatibility of Natural Web I/O Interface client with future versions of Google Chrome cannot be fully guaranteed. Possible incompatibilities will be removed during the regular maintenance process of Natural Web I/O Interface client.



Important: Cookies and JavaScript must be enabled in the browser.

5 Installing the Natural Web I/O Interface Client on Apache

Tomcat

- Installation Steps 46
- Installation Verification 47

If you want to use the Natural Web I/O Interface client with Apache Tomcat, you must proceed as described in this chapter.

Installation Steps

The Natural Web I/O Interface client is installed using the Tomcat Manager.

The following is assumed:

- `<install-dir>` is the path to the main installation directory. By default, this is `C:\SoftwareAG` on Windows and `/opt/softwareag` on Linux.
- `<host>` is the name of the machine on which Apache Tomcat is installed.
- `<port>` is the name of the port where Apache Tomcat is installed. In a default installation, this is port 8080.
- `<tomcat>` is the path to the directory in which Apache Tomcat is installed.

The following topics are covered below:

- [First-time Installation](#)
- [Update Installation](#)

First-time Installation

➤ To install the Natural Web I/O Interface client

- 1 Natural for Windows and Linux: Copy the complete contents of the `<install-dir>/natural/INSTALL/nwoclient/tomcat` directory to a directory of your choice on your hard disk.
- 2 Make sure that Apache Tomcat is running.
- 3 Open your web browser and enter the following URL:

```
http://<host>:<port>/manager/html
```

This opens the Tomcat Manager.

- 4 Deploy the web application file `natuniweb.war`:
 - Under **Select WAR file to upload** select the path to the file `natuniweb.war`.
 - Choose **Deploy**.
- 5 In the Tomcat Manager, look for the application **Natural Web I/O Interface Client** and choose **Reload**.

Update Installation

➤ To update the Natural Web I/O Interface client

- 1 Natural for Windows and Linux: Copy the complete contents of the `<install-dir>/natural/INSTALL/nwoclient/tomcat` directory to a directory of your choice on your hard disk.

Or:

Download the Natural Web I/O Interface client for Apache Tomcat from <https://empower.softwareag.com/> and unzip the contents to a directory of your choice on your hard disk.

- 2 Shut down Apache Tomcat.
- 3 Create a backup copy of your `sessions.xml` file, which is located in `<tomcat>/webapps/natuniweb/WEB-INF`.
- 4 Start Apache Tomcat.
- 5 Open your web browser and enter the following URL:

```
http://<host>:<port>/manager/html
```

This opens the Tomcat Manager.

- 6 Select `natuniweb.war` in the list of installed applications.
- 7 Choose **Undeploy**.
- 8 Deploy the new version of the Natural Web I/O Interface client as in a first-time installation.
- 9 Restore the `sessions.xml` file that you have backed up previously.

Installation Verification

It is assumed that `http://<host>:<port>` is the URL of your application server.

To verify the installation, enter the following URL in your web browser:

```
http://<host>:<port>/natuniweb/natural.jsp
```

For example:

```
http://myhost:8080/natuniweb/natural.jsp
```

The Natural Web I/O Interface client is now started in your browser. The entries which appear in the resulting logon page depend on the settings in your configuration file. For further information, see [Configuring the Client](#).

6 Migrating the Natural Web I/O Interface Client from IIS to Apache Tomcat

- Before You Install the Natural Web I/O Interface Client 50
- Installing the Natural Web I/O Interface Client on Apache Tomcat 51
- Configuring the Natural Web I/O Interface Client on Apache Tomcat 51

Microsoft Internet Information Services (IIS) is no longer supported. If you are currently using the Natural Web I/O Interface client on IIS, you have to move to Apache Tomcat.



Note: JBoss Application Server and Oracle GlassFish Server are also no longer supported. If you are currently using one of these application servers, you also have to move to Apache Tomcat. In this case, however, you can reuse your previous settings (that is, the URL for logon page and the configuration file *sessions.xml*).

The most simple solution is to migrate the Natural Web I/O Interface client from IIS to Apache Tomcat. Therefore, this chapter gives IIS administrators a quick introduction to a Tomcat installation and describes the migration steps.

Before You Install the Natural Web I/O Interface Client

If Apache Tomcat is not yet installed, proceed as described in the topics below:

- [Installing Tomcat](#)
- [Installing Java](#)
- [Starting the Tomcat Server](#)

Installing Tomcat

Go to <http://tomcat.apache.org/> and download Tomcat as a zip file.

For Microsoft Windows users: download either the 32-bit or the 64-bit Windows zip file.

Unzip the downloaded zip file to a directory of your choice.

Installing Java

Tomcat is based on Java. Therefore, you have to make sure that a Java Runtime Environment (JRE) or a Java Development Kit (JDK) is installed. The version of the Java runtime should be at least Java 6 update 24. This is the minimum version that is required for the Natural Web I/O Interface client on Tomcat.

You can download the Java JRE or JDK from the Oracle website at <http://www.oracle.com/technetwork/java/javase/downloads/index.html>.

If Java is installed on your system, make sure that the environment variable `JAVA_HOME` is set to the Java home directory.

Starting the Tomcat Server

When Tomcat and the appropriate Java version have been installed, you can start Tomcat.

To start Tomcat, execute the *startup.bat* file from the *bin* directory of your Tomcat installation. To check whether Tomcat is running, enter the following URL:

```
http://localhost:8080
```

This should display Tomcat's default home page.

Installing the Natural Web I/O Interface Client on Apache Tomcat

When Apache Tomcat has been installed, install the Natural Web I/O Interface client as described in [Installing the Natural Web I/O Interface Client on Apache Tomcat](#).

Configuring the Natural Web I/O Interface Client on Apache Tomcat

When the Natural Web I/O Interface client has been installed, proceed as described in the topics below:

- [Invoking the Logon Page](#)
- [Changing the Tomcat HTTP Port](#)
- [Using the Settings from Your IIS Configuration File](#)
- [Using the Configuration Tool](#)
- [Protecting the Configuration Tool Against Unauthorized Access](#)
- [Displaying the Logon Page by Default](#)

Invoking the Logon Page

Enter the following URL to invoke the logon page (this is different from the URL that was used with IIS):

```
http://localhost:8080/natuniweb/natural.jsp
```

Changing the Tomcat HTTP Port

IIS usually runs on the default port 80. If you want Tomcat to work with the same port, edit the file *server.xml* which is located in Tomcat's *conf* subdirectory and then search for the following text:

```
<Connector port="8080" protocol="HTTP/1.1"
```

Change the port number so that it looks as follows:

```
<Connector port="80" protocol="HTTP/1.1"
```

Using the Settings from Your IIS Configuration File

With Tomcat, you can reuse the *settings.xml* configuration file of IIS, but you have to rename the file to *sessions.xml*. Proceed as follows:

1. Copy the *settings.xml* file from your IIS installation to the following directory of your Tomcat installation:

```
webapps/natuniweb/WEB-INF
```

2. Either rename the *sessions.xml* file which comes with the Natural Web I/O Interface client installation on Tomcat (for example, to *sessions-original.xml*) or delete it.
3. Rename the *settings.xml* file to *sessions.xml*.

Using the Configuration Tool

When the Natural Web I/O Interface client runs on Tomcat, it is no longer necessary to edit the configuration file manually. Instead, you can use the configuration tool. Using this tool has the advantage that it is not possible for you to create invalid XML code and thus damage the XML file. See [Using the Configuration Tool](#) for further information.

The IIS-specific entries in the renamed configuration file will be ignored. These are:

```
natural_parameter visible  
theme  
screen top  
screen left  
screen size  
screen pfkeypos
```

You can still edit the configuration file manually. However, this is no longer recommended.

Protecting the Configuration Tool Against Unauthorized Access

It is possible to protect the configuration tool against unauthorized access. See [Configuring Container-Managed Security](#) for detailed information.

For detailed information on the necessary realm configuration for Tomcat, see <http://tomcat.apache.org/tomcat-6.0-doc/realms-howto.html>.

Displaying the Logon Page by Default

When you enter the URL `http://localhost:8080/natuniweb`, Tomcat shows the default page of the Natural Web I/O Interface client which allows you to access either the **logon page** or the **configuration tool** of the Natural Web I/O Interface client.



Note: If you have defined a different port (for example, 80), make sure to use that port number in the URL.

This behavior is different from IIS which displays the logon page by default. If you also want Tomcat to display the logon page by default, edit the file `web.xml` which is located in Tomcat's `webapps\natuniweb\WEB-INF` directory and search for the following entry:

```
<welcome-file-list>
  <welcome-file>
    index.html
  </welcome-file>
</welcome-file-list>
```

Change the name of the welcome file to `natural.jsp` as shown in the following example:

```
<welcome-file-list>
  <welcome-file>
    natural.jsp
  </welcome-file>
</welcome-file-list>
```


IV

Configuring the Client

This part explains how to configure the Natural Web I/O Interface client so that it can be used in a Natural runtime environment. The following topics are covered:

[About the Logon Page](#)

[Natural Client Configuration Tool](#)

[Natural Web I/O Style Sheets](#)

[Starting a Natural Application with a URL](#)

[Configuring Container-Managed Security](#)

[Configuring SSL](#)

[Logging](#)

7

About the Logon Page

▪ Starting a Natural Application from the Logon Page	58
▪ Examples of Logon Pages	58
▪ Dynamically Changing the CICS Transaction Name, Host Name, and Port Number when Starting a Session	59
▪ Specifying a Password in the Logon Page	60
▪ Changing the Password in the Logon Page	60
▪ Browser Restrictions	61

Starting a Natural Application from the Logon Page

When you start the Natural Web I/O Interface client in the browser, a logon page appears. The entries in this logon page depend on the settings in your [Session Configuration](#).

In order to start a Natural application from the logon page, you enter the following URL inside your browser:


```
http://<host>:<port>/natuniweb/natural.jsp
```

where *<host>* and *<port>* are the host name and port number of your application server.

Examples of Logon Pages

For each session definition that has been configured in the configuration file, an entry appears on the logon page. If the user selects the corresponding entry, only those parameters that were not pre-configured in the configuration file need to be specified in the logon page in order to start the application. Usually, you will preconfigure all connection parameters except user name and password.

The following example shows part of a logon page which results from a configuration file in which no special entries are defined for a session:



The screenshot shows a web form titled "Enter connection details:". It contains the following elements:

- Session ID:** A dropdown menu with "Connect to Natural" selected.
- Host name:** A text input field.
- Port number:** A text input field.
- User name:** A text input field.
- Password:** A text input field.
- Application:** A text input field.
- Natural parameters:** A text input field.
- Buttons:** "Connect" and "Change password" buttons are located to the right of the Session ID dropdown.

The following example shows part of a logon page which results from a configuration file in which many settings are already predefined (including user ID and password):

The screenshot shows a rectangular box with a light gray border. Inside the box, the text "Enter connection details:" is positioned at the top left. Below this, the label "Session ID:" is followed by a dropdown menu. The dropdown menu is currently open, displaying "Demo Application (localhost.2900)". To the right of the dropdown menu is a rectangular button with the text "Connect".

To log on to a session, you have to specify all required information in the logon page (for example, you select a session from the corresponding drop-down list box). When you choose the **Connect** button, the screen for the selected session appears.

Dynamically Changing the CICS Transaction Name, Host Name, and Port Number when Starting a Session

The following description applies if you want to switch to a different CICS transaction on z/OS. It is also possible to select a different host and port number.

You specify the dynamic server parameters in the same text box in which you also specify the dynamic parameters for the Natural environment. So that the dynamic server parameters can be evaluated, it is important that you specify it before any Natural parameters, using the following syntax:

```
<TA_NAME=name TA_HOST=hostname TA_PORT=number>
```

name

Can be 1 to 4 characters long. This must be the name of an existing CICS transaction which applies to a CICS Adapter. It will override the transaction name, currently defined in the configuration file for the CICS Adapter on the Natural Web I/O Interface server (NWO). Ask your administrator for further information.

hostname

Can be 1 to 32 characters long. This must be the name, or the TCP/IP address of the host the desired CICS is running. It will override the hostname (RFE_CICS_TA_HOST), currently defined in the configuration file for the CICS Adapter on the Natural Web I/O Interface server (NWO). Ask your administrator for further information.

number

Can be a numeric value in the range from 1 to 65535. It is the TCP/IP port of the CICS-supplied listener. It will override the hostname (RFE_CICS_TA_PORT), currently defined in the configuration file for the CICS Adapter on the Natural Web I/O Interface server (NWO). Ask your administrator for further information.

Make sure to put the entire definition in angle brackets. Dynamic server parameters can be separated by a comma or a blank character. Only the parameters to be overwritten must be specified. When this definition is followed by a Natural parameter, insert a blank before the Natural parameter.

Example:

```
<TA_NAME=NA82 TA_HOST=HOST.LOCAL.NET TA_PORT=1898> STACK=(LOGON SYSCP)
```

If one of the dynamic server parameters is incorrect, an error message occurs, and the session cannot be started.

If an incorrect CICS transaction id is specified, the error message `EZY1315E 09/03/24 15:17:46 INVALID TRANID=G PARTNER INET ADDR=ip-address` occurs.

If an incorrect hostname or port number is specified, the error message `NAT9939 Open socket connection failed` occurs.



Note: The above definition of dynamic server parameters can also be specified in the configuration tool, in the same place where you also specify the Natural parameters, and together with the [URL parameter](#) `natparam`.

Specifying a Password in the Logon Page

The following information applies when the field for entering a password appears on the logon page. This field does not appear when a password has already been defined in the configuration file.

Under Windows and Linux, you always have to enter the operating system password, even if Natural Security is active.

On z/OS, this is different: When Natural Security is not active, you have to enter the operating system password. When Natural Security is active, you have to enter the Natural Security password.

Changing the Password in the Logon Page

Currently, this functionality is only available for Natural for Linux and Natural for Windows.

The following information applies when the fields for entering a user ID and a password appear on the logon page. These fields do not appear when user ID and password have already been defined in the configuration file; in this case, it is not possible to change the password in the logon page.

When you try to log on with an expired password, an error message appears.

> To change the password

- 1 Choose the **Change password** button in the logon page.

The name of this button changes to **Don't change password** and the following two input fields are shown in the logon page:

- **New password**
- **Repeat new password**

- 2 Enter your user ID and your current password as usual.
- 3 Enter the new password in the two input fields.
- 4 Choose the **Connect** button to change the password.

Or:

If you do not want to change your password, choose the **Don't change password** button. The two input fields will then disappear.

Browser Restrictions

The browser's "Back" and "Forward" buttons do not work with the Natural Web I/O Interface client and should therefore not be used.

If you want to run two Natural sessions in parallel, you have to start a new instance of the browser (for example, by choosing the corresponding icon in the Quick Launch toolbar of Windows). You must not use the browser's "New Window" function. This would result in one session running in two browsers, which is not allowed.

8

Natural Client Configuration Tool

▪ Invoking the Configuration Tool	64
▪ Session Configuration	65
▪ Logging Configuration	73
▪ Logon Page	73
▪ Logout	73

Invoking the Configuration Tool

The Natural Web I/O Interface client offers a configuration tool. The configuration tool is used to create the session configurations which are then available in the logon page. It can also be used for logging purposes in case of problems; however, this should only be done when requested by support.

The configuration tool is automatically installed when you install the Natural Web I/O Interface client .

> To invoke the configuration tool

- Enter the following URL in your browser:


```
http://<host>:<port>/natuniweb/conf_index.jsp
```

where *<host>* and *<port>* are the host name and port number of your application server.



Note: You might wish to protect the configuration tool against unauthorized access. See [Configuring Container-Managed Security](#) for information on how to restrict the access to sensitive areas of the application server environment. If you have restricted access to the configuration tool, an authentication dialog appears. The appearance of this dialog depends on the authentication model you have chosen.

The configuration tool appears.



The configuration tool has two frames.

The home page of the configuration tool is initially shown in the right frame. It provides brief descriptions for the links provided in the left frame.

When you have invoked a function (for example, when you are currently viewing the session configuration), you can always choose the **Home** link in the left frame to return to the home page of the configuration tool.

The functions that are invoked by the other links in the left frame are described below.

Session Configuration

This section explains how to manage the content of the configuration file for the sessions. It covers the following topics:

- [Invoking the Session Configuration Page](#)
- [Global Settings](#)
- [Adding a New Session](#)
- [Editing a Session](#)
- [Overview of Session Options](#)
- [Duplicating a Session](#)
- [Deleting a Session](#)
- [Adding a New User](#)
- [Saving the Configuration](#)

Invoking the Session Configuration Page

The content of the configuration file for the sessions is managed using the **Session Configuration** page.

To invoke the **Session Configuration** page, choose the **Session Configuration** link in the frame on the left.

The **Session Configuration** page appears in the right frame. It shows the global settings and lists all sessions and users that are currently defined. For a session, some of the configuration file information is shown. Example:

Session Configuration

Global Settings

Last activity timeout (n seconds):

Trace directory:

SSL trust file path:

SSL trust file password:

Sessions

Session ID	Host Name	Port Number	Application	Natural Parameters	Edit	Duplicate	Delete
Connect to Natural					Edit	Duplicate	Delete
localtestserver	localhost	6640			Edit	Duplicate	Delete

Users

User ID	Edit	Duplicate	Delete
user1	Edit	Duplicate	Delete

Global Settings

The global settings apply for all defined sessions. You can define the following global settings in the configuration file:

Option	Description
Last activity timeout (n seconds)	The number of seconds that the client waits for the next user activity. When the defined number of seconds has been reached without user activity, the session is closed. The default is 3600 seconds.
Trace directory	<p>Optional. Location of a different trace directory.</p> <p>When a different trace directory is not defined, the trace files are written to the default trace directory. By default, the trace files are written to the directory which has been set by the Java property <code>java.io.tmpdir</code>. On Windows, this is normally the environment variable <code>TMP</code> for the user who started the application server. On Linux, this is normally <code>/tmp</code> or <code>/var/tmp</code>.</p> <p>You can also set this property in the start script for the application server.</p> <p>Tracing can be enabled individually for each session (see Overview of Session Options below). However, it should only be enabled when requested by support.</p>

Option	Description
SSL trust file path	Optional. The path to your trust file. See Configuring SSL for further information.
SSL trust file password	<p>If your trust file is password-protected, you have to specify the appropriate password.</p> <p>When you do not specify the password for a password-protected trust file, the trust file cannot be opened and it is thus not possible to open an SSL session.</p> <p>When your trust file is not password-protected, you should not specify a password.</p>

Adding a New Session

You can add a new session to the configuration file.

» To add a new session

- 1 Choose the **Add New Session** button.

The **Edit Session** page appears.

- 2 Specify all required information as described below in the section [Overview of Session Options](#).

- 3 Choose the **OK** button to return to the **Session Configuration** page.

The new session is not yet available in the configuration file.

- 4 Choose the **Save Configuration** button to write the new session to the configuration file.

Editing a Session

You can edit any existing session in the configuration file.

» To edit a session

- 1 Choose the **Edit** link that is shown next to the session that you want to edit.

The **Edit Session** page appears.

- 2 Specify all required information as described below in the section [Overview of Session Options](#).

- 3 Choose the **OK** button to return to the **Session Configuration** page.

The modifications are not yet available in the configuration file.

- 4 Choose the **Save Configuration** button to write the modifications to the configuration file.

Overview of Session Options

The **Edit Session** page appears when you

- **add** a new session, or
- **edit** an existing session.

Example:

Edit Session

Session ID:	<input type="text"/>
Type:	Undefined <input type="text"/>
Host name:	<input type="text"/>
Port number:	<input type="text"/>
Use SSL	<input type="radio"/> Yes <input checked="" type="radio"/> No
User name:	<input type="text"/>
User name in upper case:	<input type="radio"/> Yes <input checked="" type="radio"/> No
Password:	<input type="text"/>
Application:	<input type="text"/>
Natural parameters:	<input type="text"/>
Double-click behavior:	Enter <input type="text"/>
Screen rows:	24 <input type="text"/>
Screen columns:	80 <input type="text"/>
Show function key numbers:	<input type="radio"/> Yes <input checked="" type="radio"/> No
Check for numeric input:	<input checked="" type="radio"/> Yes <input type="radio"/> No
Trace:	<input type="radio"/> Yes <input checked="" type="radio"/> No
Timeout (in seconds):	60 <input type="text"/>
Filler character:	<input type="text"/>

The **Edit Session** page provides the following options:

Option	Description
Session ID	Mandatory. A session name of your choice. On the logon page, the session name is provided in a drop-down list box.
Type	<p>The platform on which user ID and password are authenticated. You can select the required setting from the drop-down list box.</p> <ul style="list-style-type: none"> ■ Undefined Default. User ID and password can have a maximum of 32 characters. See also the description for Natural for Windows or Linux below. ■ Natural for z/OS User ID and password can have a maximum of 8 characters. ■ Natural for z/OS with Natural Security User ID and password can have a maximum of 8 characters. The user ID must comply with the Natural naming conventions for library names . ■ Natural for Windows or Linux User ID and password can have a maximum of 32 characters. When a domain is required, you have to specify it together with the user ID (in the form " <i>domain \ user-ID</i> ").
Host name	The name or TCP/IP address of the server on which Natural and the Natural Web I/O Interface server are running. When this is specified, the corresponding field does not appear on the logon page.
Port number	The TCP/IP port number on which the Natural Web I/O Interface server is listening. When this is specified, the corresponding field does not appear on the logon page.
Use SSL	<p>If set to Yes , a secure connection is established between the Natural Web I/O Interface client on the application server and the Natural Web I/O Interface server.</p> <p>Important: If you want to use SSL with Natural for z/OS, one of the corresponding types must be selected; the type must not be Undefined or Natural for Windows or Linux . The other way around, if you want to use SSL with Natural for Windows or Linux, you must not select one of the platform-specific types; the type may also be Undefined in this case.</p>
User name	Optional. A valid user ID for the current machine. When this is specified, the corresponding field does not appear on the logon page.
User name in upper case	If selected, the input field for the user ID is in upper-case mode.
Password	<p>Optional. A valid password for the above user ID.</p> <p>Under Windows and Linux, this is always the operating system password of the user, even if Natural Security is active.</p> <p>On z/OS, this is different: When Natural Security is not active, this is the operating system password of the user. When Natural Security is active, this is the Natural Security password.</p>

Option	Description
	<p>When a password is specified, the corresponding field does not appear on the logon page. The configuration tool saves the password in encrypted form.</p>
<p>Application</p>	<ul style="list-style-type: none"> ■ Natural for z/OS The name of the Natural program or a command sequence that starts your application as you would enter it on the NEXT prompt. Example: <code>TEST01 data1,data2</code> ■ Natural for Linux The name of the Linux shell script for starting the Natural application (a file similar to <i>nwo.sh</i>). ■ Natural for Windows The name of the Windows command file (<i>.bat</i>) for starting the Natural application. <p>When this is specified, the corresponding field does not appear on the logon page.</p>
<p>Natural parameters</p>	<p>Optional. Parameters for starting the Natural application. This can be stack parameters, a parameter file/module or other Natural-specific information.</p> <ul style="list-style-type: none"> ■ Natural for z/OS Used to pass dynamic Natural profile parameters to the session, for example: <code>SYSPARM=(MYPARMS) STACK=(LOGON MYAPPL)</code> <p>Note: It is recommended to specify the Natural program that starts the application with the option Application instead of passing it with the profile parameter <code>STACK</code> .</p> <ul style="list-style-type: none"> ■ Natural for Linux and Natural for Windows Used when the above shell script (Linux) or command file (Windows) uses the parameter \$5 after "natural" , for example: <code>PARM=MYPARM STACK=(LOGON MYLIB;MENU)</code>
<p>Double-click behavior</p>	<p>The key that is to be simulated when double-clicking an output field. By default, this is the ENTER key.</p> <p>It is possible to disable the double-click behavior, or to define a function key (PF1 through PF12).</p> <p>You can select the required setting from the drop-down list box.</p> <p>Tip: When context-sensitive help has been defined for the output fields, it may be useful to define PF1 . The help function will then be invoked when the user double-clicks an output field.</p>
<p>Screen rows</p>	<p>The number of rows in the output window. Possible values: minimum 24, no upper limit. Default: 24.</p> <p>Not used by Natural for z/OS which uses the profile parameter <code>TMODEL</code> instead.</p>

Option	Description
Screen columns	The number of columns in the output window. Possible values: minimum 80, no upper limit. Default: 80. Not used by Natural for z/OS which uses the profile parameter TMODEL instead.
Show function key numbers	If set to Yes , the PF key numbers are shown next to the PF keys.
Trace	Should only be set to Yes when requested by support.
Check for numeric input	If set to Yes (default), numeric input fields are validated. In this case, only the following characters are allowed in numeric input fields (in addition to the numbers "0" through "9"): <i>blank</i> + (plus) - (minus) _ (underscore) , (comma) . (period) ? (question mark) If set to No , numeric input fields are not validated.
Timeout (in seconds)	The number of seconds that the client waits for a response after an updated page was sent to the Natural session. When the defined number of seconds has been reached without response, the session is closed. The default is 60 seconds. Normally, you need not change this value.
Filler character	Optional. The filler character that is to be removed from the input fields. An application can define, for example, an underscore (<code>_</code>) as the filler character. Trailing filler characters will be removed from the input fields, and leading filler characters will be replaced with blanks.

Duplicating a Session

You can add a copy of any existing session to the configuration file.

➤ To duplicate a session

- 1 Choose the **Duplicate** link that is shown next to the session that you want to duplicate.

A new entry is shown at the bottom of the list of sessions. Its name is "Copy of *session-ID*". The duplicated session is not yet available in the configuration file.

- 2 **Edit** and save the duplicated session as described above.

Deleting a Session

You can delete any existing session from the configuration file.

➤ To delete a session

- 1 Choose the **Delete** link that is shown next to the session that you want to delete.

The session is deleted from the list of sessions. It is not yet deleted in the configuration file.

- 2 Choose the **Save Configuration** button to delete the session from the configuration file.

Adding a New User

You can predefine Natural users and their passwords in the configuration file.

When a Natural page is opened with a URL that specifies a user in the URL parameter `natuser`, the specified user is matched against the list of users in the configuration file. When the specified user is defined in the configuration file, the corresponding password is used to authenticate the user when the Natural session is started. See also [Starting a Natural Application with a URL](#).

Example - when the following URL is used, the password defined for "user1" is used:

`http://myhost:8080/natuniweb/natural.jsp?natuser=user1...`

➤ To add a new user

- 1 Choose the **Add New User** button.

The **Edit User** page appears.

- 2 Specify a user name and password
- 3 Choose the **OK** button to return to the **Session Configuration** page.

The new user is not yet available in the configuration file.

- 4 Choose the **Save Configuration** button to write the new user to the configuration file.



Note: You edit, duplicate and delete a user in the same way as a session (see the corresponding descriptions above).

Saving the Configuration

When you choose the **Save Configuration** button, all of your changes are written to the configuration file. The server picks up the new settings automatically the next time it reads data from the configuration file.



Caution: If you do not choose the **Save Configuration** button but log out instead or leave the configuration tool by entering another URL, the new settings are not written to the configuration file.

Logging Configuration

The content of the configuration file for logging is managed using the **Logging Configuration** page. See the section [Logging](#) for detailed information.

Logon Page

The configuration tool provides the following link in the left frame:

- **Natural Web I/O Interface Logon**

This link opens the logon page in the right frame.

The logon page uses the current settings in the configuration file. When you select a session from the drop-down list box, you can check whether the connection details are shown as desired. If not, you can go back to the session configuration and modify the settings of the corresponding session.

See also [About the Logon Page](#) .

Logout

When the configuration tool is protected against unauthorized access and you log out of the configuration tool, you make sure that no other user can change the client configuration when you leave your PC unattended for a while.

➤ **To log out**

- In the frame on the left, choose the **Logout** link.

When the configuration tool is protected against unauthorized access, the authentication dialog is shown again.

When it is not protected, the home page is shown again.

9 Natural Web I/O Style Sheets

- Name and Location of the Style Sheets 76
- Editing the Style Sheets 76
- Modifying the Position of the Main Output and of the PF Keys 76
- Modifying the Font Size 77
- Modifying the Font Type 78
- Defining Underlined and Blinking Text 79
- Defining Italic Text 80
- Defining Bold Text 80
- Defining Different Styles for Output Fields 81
- Modifying the Natural Windows 81
- Modifying the Message Line 82
- Modifying the Background Color 82
- Modifying the Color Attributes 83
- Modifying the Style of the PF Key Buttons 84
- JavaScript and XSLT Files 85

Name and Location of the Style Sheets

Several aspects on a page (such as font, font style or color) are controlled by a style sheet (CSS file).

The Natural Web I/O Interface client is delivered with the style sheet `3270.css` , which is located in:

```
../natuniapp.ear/natuniweb.war/resources
```



Note: For more information on style sheets, see <http://www.w3.org/Style/CSS/> .

Editing the Style Sheets

It is recommended that you have a basic understanding of CSS files.

You can edit the predefined style sheets or create your own style sheets.

It is recommended that you work with backup copies. When a problem occurs with your style sheet, you can thus always revert to the original state.

To see your changes in the browser, you have to

1. delete the browser's cache, and
2. restart the session.

Modifying the Position of the Main Output and of the PF Keys

Applies when only the named PF keys are displayed. This feature cannot be used when all PF keys are displayed, since they are always displayed at the same position. See also [Overview of Session Options](#) .

The following elements are available:

Element Name	Description
.mainlayer	Controls the position of the main output in the output window. Used for languages that are written from left-to-right (LTR).
.mainlayer_rtl	Controls the position of the main output in the output window. Used for languages that are written from right-to-left (RTL).
.pfkeydiv	Controls the position of the PF keys in the output window. Used for languages that are written from left-to-right (LTR).
.pfkeydiv_rtl	Controls the position of the PF keys in the output window. Used for languages that are written from right-to-left (RTL).

The *_rtl elements are only used if Natural sends the web I/O screen with a right-to-left flag (SET CONTROL 'VON'). In the browser, the screen elements are then shown on the right side (instead of the left side).

For web I/O in applications where only the left-to-right orientation is used, the *_rtl elements are not required.

If the PF keys are to appear at the bottom, define the elements as shown in the following example:

```
/* Defines the main screen position */ .mainlayer { top: 5px;
  left: 0px;
  height: 550px; } /* Defines the main screen position for right-to-left */ ←
.mainlayer_rtl{ top: 5px;
  right: 30px;
  height: 550px; } /* Defines the PF keys screen position */ .pfkeydiv { height: ←
70px;
  left: 0px;
  top: 580px; width: 100%; } /* Defines the PF keys screen position for ←
right-to-left */ .pfkeydiv_rtl { height: 70px;
  right: 30px;
  top: 580px; width: 100%; }
```

Modifying the Font Size

Depending on the screen resolution, one of the following style sheets for defining the font size is used in addition to the default style sheet:

- *model2.css*
- *model3.css*
- *model4.css*
- *model5.css*

These style sheets are located in the *tmodels* subdirectory of the *resources* directory in which all style sheets are located.

Depending on what comes closest to the standard 3270 screen model, the corresponding style sheet from the *tmodels* subdirectory is automatically used. It is selected according to the following criteria:

Standard 3270 Screen Model	Criteria	Style Sheet
Model 2 (80x24)	30 rows or less.	<i>model2.css</i>
Model 3 (80x32)	Between 31 and 40 rows.	<i>model3.css</i>
Model 4 (80x43)	41 rows or more.	<i>model4.css</i>
Model 5 (132x27)	30 rows or less, and more than 100 columns.	<i>model5.css</i>

The font sizes in the above style sheets can be adjusted. Example for *model4.css* :

```
body { font-size: 10px; }
```

The default font sizes for the above 3270 screen models are:

Standard 3270 Screen Model	Default Font Size
Model 2	16px
Model 3	14px
Model 4	10px
Model 5	12px

Modifying the Font Type

As a rule, you should only use monospace fonts such as Courier New or Lucida Console. With these fonts, all characters have the same width. Otherwise, when using variable-width fonts, the output will appear deformed.

If you want to define a different font type, you should define the same font type for the body, the output fields and the input fields as shown in the following example:

```
body {
    background-color: #F3F5F0;
    font-family: Lucida Console;
}

.OutputField {
    white-space:pre;
    border-width:0;
    font-family: Lucida Console;
```

```

    font-size: 100%;
}

.InputField {
    background-color: white;
    font-family: Lucida Console;
    border-width: 1px;
    font-size: 100%;
    border-color: #A7A9AB;
}

```

Use the CSS at-rule `@font-face` to specify a custom font with which to display text.

For example, Arabic fonts to be used with `InputFields` for the presentation of "Arabic-Indic numerals" instead of "European numerals":

```

@font-face {
    font-family: CustomFont;
    src: url( CustomFont.woff );
}

```

Defining Underlined and Blinking Text

The following elements are available:

Element Name	Description
<code>.natTextDecoUnderline</code>	Defines underlined text.
<code>.natTextDecoBlinking</code>	Defines blinking text.
<code>.natTextDecoNormal</code>	Defines normal text (no underline, no blinking).

Example:

```

/* Text decoration */
.natTextDecoUnderline { text-decoration:underline; }
.natTextDecoBlinking {text-decoration:blink; }
.natTextDecoNormal {text-decoration:normal;}

```

Blinking text is not supported by the Internet Explorer.

Defining Italic Text

The following elements are available:

Element Name	Description
<code>.natFontStyleItalic</code>	Defines italic text.
<code>.natFontStyleNormal</code>	Defines normal text (no italics).

Example:

```
/* font style */
.natFontStyleItalic {font-style:italic;}
.natFontStyleNormal {font-style:normal;}
```

Defining Bold Text

The following elements are available:

Element Name	Description
<code>.natFontWeightBold</code>	Defines bold text.
<code>.natFontWeightNormal</code>	Defines normal text (not bold).

```
/* Font weight */
.natFontWeightBold {font-weight:bolder;}
.natFontWeightNormal {font-weight:normal;}
```

When you define bold text (`{font-weight:bolder;}`) for the default font Courier New, your text always has the same width as with normal text (`{font-weight:normal;}`).

However, when you define bold text for Courier or Lucida Console, the bold text will be wider than the normal text and your output may thus appear deformed. It is therefore recommended that you switch off bold text for Courier and Lucida Console:

```
.natFontWeightBold {font-weight:normal;}
```

Defining Different Styles for Output Fields

The following elements are available:

Element Name	Description
.FieldVariableBased	Defines the style for output fields that are based on a variable.
.FieldLiteralBased	Defines the style for output fields that are based on a literal.

Example:

```
.FieldVariableBased {
  /* font-style:italic; */
}

.FieldLiteralBased {
  /* font-style:normal; */
}
```



Note: In the above example, as well as in the standard CSS files delivered by the product, the variable-based output fields are defined as italic, but are commented out.

Modifying the Natural Windows

The following elements are available:

Element Name	Description
.naturalwindow	Controls the rendering of the Natural windows.
.wintitle	Controls the rendering of the titles of the Natural windows.

Example:

```
.naturalwindow {
  border-style: solid;
  border-width: 1px;
  border-color: white;
  background-color: black;
}

.wintitle {
  left: 0px;
  top: 1px;
  height: 17px;
}
```

```
width: 100%;
color: black;
font-size: 100%;
font-weight: bold;
background-color: white;
text-align: center;
font-family: Verdana;
border-bottom-style: solid;
border-bottom-width: 2px;
}
```

 **Note:** In a z/OS environment, you have to set the Natural profile parameter `WEBIO` accordingly to enable this feature. See *WEBIO - Web I/O Interface Screen Rendering* in the *Parameter Reference* which is provided with Natural for z/OS.

Modifying the Message Line

The rendering of the message line is controlled by the `.MessageLine` element.

Example:

```
.MessageLine {
  color: blue;
}
```

 **Note:** In a z/OS environment, you have to set the Natural profile parameter `WEBIO` accordingly to enable this feature. See *WEBIO - Web I/O Interface Screen Rendering* in the *Parameter Reference* which is provided with Natural for z/OS.

Modifying the Background Color

The background color is defined in the `body` element.

Example:

```
body {
  background-color: #F3F5F0;
  font-family: Lucida Console;
}
```

Modifying the Color Attributes

You can define different colors for all Natural color attributes. These are:

Red
Green
Blue
Yellow
White
Black
Pink
Turquoise
Transparent

You can define these color attributes for input fields and output fields, and for normal output and reverse video.

The following examples show how to define the color attribute “Red” .

Define the color for a normal output field:

```
.natOutputRed {color: darkred;}
```

Define the foreground and background colors for an output field with reverse video:

```
.reverseOutputRed {background-color: darkred; color:#F3F5F0;}
```

Define the color for a normal input field:

```
.natInputRed {color: darkred;}
```

Define the foreground and background colors for an input field with reverse video:

```
.reverseInputRed {background-color: darkred; color:#F3F5F0;}
```

Modifying the Style of the PF Key Buttons

The following elements are available:

Element Name	Description
.PFButton	Controls the style for normal rendering.
.PFButton:hover	Controls the style that is used when the mouse hovers over a PF key button.

Example:

```
.PFButton {
  text-align: center;
  width: 90px;
  border-style: ridge;
  border-width: 3px;
  padding: 2px;
  text-decoration: none;
  font-family: Verdana;
  font-size: 12px;
  height: 22px;
}

.PFButton:hover {
  color: #FFFF00;
  background-color: #222222;
}
```



Note: In a z/OS environment, you have to set the Natural profile parameter `WEBIO` accordingly to enable this feature. See *WEBIO - Web I/O Interface Screen Rendering* in the *Parameter Reference* which is provided with Natural for z/OS.

JavaScript and XSLT Files

About XSLT Files in the Natural Web I/O Interface

In addition to the CSS files described above, the Natural Web I/O Interface client uses XSLT files with specific names for the conversion of the Natural Web I/O Interface screens from the internal XML format to HTML. The HTML also contains calls to JavaScript. For Web I/O screens the following conversion is done:

- Input text is placed into the HTML element `<input>`.
- Output text is placed into the HTML element `<input>` (with attribute `readonly="readonly"`).
- A message line is placed into the HTML element ``.
- PF keys are embedded in an XML island and then rendered with JavaScript.
- Window elements are embedded in an XML island and then rendered with JavaScript.

The conversion is done at runtime by the following product files of your web application:

1. `<mywebapp>/WEB-INF/transuni.xml`
2. `<mywebapp>/scripts/natuniscrpt.js`

The XSLT file `transuni.xml` is only read once when the server is started.

 **Important:** Do not change the above files. The functionality of these files may change in new versions or service packs of the product, which would overwrite your changes.

Customizing JavaScript

You can copy your own JavaScript file with extended JavaScript functionality into the directory `<mywebapp>/scripts`. This file must have the name `usernaticscript.js`. Define your new functionality in this JavaScript file.

If a `usernaticscript.js` is found when the server is started, it is read additionally to the JavaScript file `natuniscrpt.js`.

For the new JavaScript functionality to be executed, you may also need to [customize the XSLT file](#).

Customizing XSLT

Make a copy of `<mywebapp>/WEB-INF/transuni.xml` and save it as `<mywebapp>/WEB-INF/usertransuni.xml`. Modify the XSL elements to your needs.

After making changes to `usertransuni.xml` user file, you have to restart the server so that your changes become effective. If a `usertransuni.xml` file is found when the server is started, it is read instead of the default XSLT file.

Customizing Overwrite / Insert mode in Input fields

Up to NJX 9.1.1, Internet Explorer always used “overwrite” mode whereas all other browsers used “insert” mode. With NJX 9.1.2 this inconsistency was fixed. The default behavior is now “overwrite” mode for all browsers. This reflects the default behavior of Natural applications.

If you prefer “insert” mode, do the following:

1. Copy the file `WEB-INF/transuni.xml` to `WEB-INF/usertransuni.xml` – refer to the section [customize the XSLT file](#) above.
2. Open `usertransuni.xml` in a text editor. Search for the following line:

```
<xsl:attribute name="onkeypress">handleKeyPress(this.name, this);</xsl:attribute>
```

3. Remove this line and save the file.

Packaging Customized Files in Natural for Ajax WAR Files

When using the *Deployment Wizard for Web Applications* of NaturalONE to deploy your Natural for Ajax `.war` file, you can automatically package a custom `usertransuni.xml` in the `.war` file for deployment:

- Add a `webconfig` directory to your NaturalONE project as described in the documentation *NaturalONE > Natural for Ajax > Deploying the Application > Content of the Sample webconfig Directory*.
- Copy your `usertransuni.xml` to the `webconfig/web-inf` folder of your NaturalONE project.

10 Starting a Natural Application with a URL

The connection parameters available in the configuration file for the session and on the logon page can also be specified as URL parameters of the logon page URL. This allows bookmarking the startup URL of a Natural application or starting an application by clicking a hyperlink in a document.

The URL parameters overrule the definitions in the configuration file, with the exception described in the table below.

The following URL parameters are available for the logon page:

URL Parameter	Corresponding Option in the Session Configuration
<code>natsession</code>	Session ID
<code>natserver</code>	Host name
<code>natport</code>	Port number
<code>natuser</code>	User name
<code>natprog</code>	Application
<code>natparam</code>	Natural parameters
<code>natparamext</code>	Natural parameters The URL parameter <code>natparamext</code> extends an existing Natural parameter definition in the configuration file. The extension works in the following way: the Natural parameters defined in the configuration file come first. Then, the Natural parameters defined in the URL parameter <code>natparamext</code> are added, separated by a space character. If you want to overrule the definition in the configuration file, use the URL parameter <code>natparam</code> instead.
<code>nattimeout</code>	Timeout (n seconds)



Important: All parameter values must be URL-encoded.

Example: In order to start the Natural program `dump`, while your application server is running on `myhost:8080` and your Natural Web I/O Interface server is running on `myserver1:4811`, you can use the following URL:

`http://myhost:8080/natuniweb/natural.jsp?natserver=myserver1&natport=4811&natprog=dump&natuser=my-username`

11

Configuring Container-Managed Security

▪ About Container-Managed Security	90
▪ Name and Location of the Configuration File for Security	90
▪ Activating Security	90
▪ Defining Security Constraints	91
▪ Defining Roles	91
▪ Selecting the Authentication Method	92
▪ Configuring the UserDatabaseRealm	92

About Container-Managed Security

The Natural Web I/O Interface client comes as a Java EE-based application. For the ease of installation, the access to this application is by default not secured. You might, however, wish to restrict the access to certain parts of the application to certain users. An important example is the **configuration tool**, which enables you to modify the Natural session definitions and the logging configuration of the Natural Web I/O Interface client . Another example is the Natural logon page.

This section does not cover the concepts of JAAS-based security in full extent. It provides, however, sufficient information to activate the preconfigured security settings of the Natural Web I/O Interface client and to adapt them to your requirements.

Name and Location of the Configuration File for Security

Security is configured in the file *web.xml* . This file is located in the following directory:

```
<tomcat-install-dir>/webapps/natuniweb/WEB-INF
```

Activating Security

Great care must be taken when editing and changing the configuration file *web.xml* . After a change, the application server must be restarted.

Edit the file *web.xml* and look for the section that is commented with "Uncomment the next lines to add security constraints and roles." . Uncomment this section by removing the comment marks shown in boldface below:

```
<!-- Uncomment the next lines to add security constraints and roles. -->
<!--
<security-constraint>
    <web-resource-collection>
        <web-resource-name>Administration Tools</web-resource-name>
        <url-pattern>/njxruntime/*</url-pattern>
    </web-resource-collection>
    ...
<security-role>
    <description>Administrator</description>
    <role-name>nwoadmin</role-name>
</security-role>
-->
```

Defining Security Constraints

The security constraints defined by default are just examples. A `<security-constraint>` element contains of a number of `<web-resource-collection>` elements combined with an `<auth-constraint>` element. The `<auth-constraint>` element contains a `<role-name>`. The whole `<security-constraint>` element describes which roles have access to the specified resources.

Example - the following definition specifies that only users in the role "nwoadmin" have access to the configuration tool:

```
<security-constraint>
  <web-resource-collection>
    <web-resource-name>Administration Tools</web-resource-name>
    <url-pattern>/njxruntime/tools/*</url-pattern>
  </web-resource-collection>
  <auth-constraint>
    <role-name>nwoadmin</role-name>
  </auth-constraint>
</security-constraint>
```

In the following section, you will see where and how the roles are defined.

Defining Roles

A few lines below in the file `web.xml`, there is a section `<security-role>`. Here, the roles that can be used in `<security-constraint>` elements are defined. You can define additional roles as needed. The assignment of users to roles is done outside this file and will often be done in a user management that is already established at your site.

Example:

```
<security-role>
  <description>Administrator</description>
  <role-name>nwoadmin</role-name>
</security-role>
```

Selecting the Authentication Method

In the file *web.xml*, there is a section `<login-config>`. The only element that should possibly be adapted here is `<auth-method>`. You can choose between the authentication methods "FORM" and "BASIC". Form-based authentication displays a specific page on which users who try to access a restricted resource can authenticate themselves. Basic authentication advises the web browser to retrieve the user credentials with its own dialog box.

Example:

```
<login-config>
  <auth-method>FORM</auth-method>
  ...
</login-config>
```

Configuring the UserDatabaseRealm

In the *tomcat-users.xml* file (which is located in the *conf* directory), specify the role "nwoadmin" for any desired user name and password. For example:

```
<user username="pepe" password="pepe123" roles="nwoadmin"/>
```

For detailed information on the necessary realm configuration for Tomcat, see <http://tomcat.apache.org/tomcat-6.0-doc/realms-howto.html#UserDatabaseRealm>.

12

Configuring SSL

- About Configuring SSL 94
- Creating Your Own Trust File 94
- Defining SSL Usage in the Configuration File 95

About Configuring SSL

Trust files are used for a secure connection between the Natural Web I/O Interface server and the Natural Web I/O Interface client . Server authentication cannot be switched off. A trust file is always required.

A trust file contains the certificates that you trust. These can be certificates of a CA (Certificate Authority) such as VeriSign, or self-signed certificates.

For information on the steps that are required on the Natural Web I/O Interface server and how to generate a self-signed certificate which needs to be imported to the client, see *SSL Support* .

To establish a secure connection, you have to proceed as described in the topics below.

Creating Your Own Trust File

To create your own trust file, you can use, for example, the `keytool` utility in the `bin` directory of the Java Runtime Environment (JRE). Here are some helpful examples:

- Create a password-protected keystore containing a private key and self-signed certificate:

```
keytool -genkey -alias foo -keyalg RSA -keystore truststore.jks - keysize 2048
```

You will be prompted for a password. You must set a password.

```
keytool -genkey -alias foo -keyalg RSA -keystore truststore.jks - keysize 2048 ↵  
-storepass your-password
```

The password is provided inline.

Both commands

- create a key pair (private key and self-signed certificate),
 - store it under the alias `foo`,
 - save it in a file named `truststore.jks`,
 - protect the file with a password.
- Import a certificate:

```
keytool -import -alias "name-for-ca" -keystore truststore.jks -storepass ←  
"your-password" -file server.cert.crt
```



Note: You *must* provide an alias, and you should use a meaningful name for the alias. You can add multiple certificates to your trust file, but each one must have a unique alias.

- List the certificates in a trust file:

```
keytool -list -v -keystore truststore.jks
```

- Delete a certificate from a trust file:

```
keytool -delete -alias "name-for-ca" -keystore truststore.jks
```

When you modify the trust file or its password, you must restart the application server so that your modification takes effect.

Defining SSL Usage in the Configuration File

Invoke the [configuration tool](#) and proceed as follows:

1. In the global settings for all defined sessions, define the **SSL trust file path** and, if required, the **SSL trust file password** . See also [Global Settings](#) in *Natural Client Configuration Tool* .

With the server authentication, the Natural Web I/O Interface client checks whether the certificate of the Natural Web I/O Interface server is known. If it is not known, the connection is rejected.

When a trust file is not defined in the configuration tool, the Natural Web I/O Interface client tries to read the file *calist* from the *lib/security* directory of the Java Runtime Environment (JRE). The default password for this file is "changeit" .

2. Define a session and set the session option **Use SSL** to **Yes** . See also [Overview of Session Options](#) in *Natural Client Configuration Tool* .

13 Logging

- About Logging 98
- Name and Location of the Configuration File for Logging 98
- Invoking the Logging Configuration Page 98
- Overview of Options for the Output File 100

About Logging

The Natural Web I/O Interface client uses the Java Logging API. In case of problems with the Natural Web I/O Interface client , you can enable logging and thus write the logging information to an output file. This should only be done when requested by support.

You configure logging using the [configuration tool](#) .



Note: Some logging information is also written to the console, regardless of the settings in the configuration file. The console shows the information which is normally provided by the logging levels SEVERE , WARNING and INFO .

Name and Location of the Configuration File for Logging

The name of the configuration file is *natlogger.xml* , which is located in: .

`<application-server-install-dir> server/default/deploy/naturalunicode.rar/log`

Invoking the Logging Configuration Page

The content of the configuration file *natlogger.xml* is managed using the **Logging Configuration** page of the [configuration tool](#) .

➤ **To invoke the Logging Configuration page**

- 1 In the frame on the left, choose the **Logging Configuration** link.

The **Logging Configuration** page appears in the right frame. Example:

Logging Configuration

Specify the output log file characteristics.

- "/" : The local pathname separator
- "%t": The system temporary directory
- "%h": The value of the "user.home" system property
- "%g": The generation number to distinguish rotated logs
- "%u": A unique number to resolve conflicts
- "%%": Translates to a single percent sign "%"

File pattern name:

File type:

File size (in Kbytes; 0=unlimited):

Number of files:

File enabled: Yes No

Append mode: Yes No

Specify log levels for individual modules. The available settings are:

- SEVERE: Events that interfere with normal program execution
- WARNING: Warnings, including exceptions
- INFO: Messages related to server configuration or server status, excluding errors
- CONFIG: Messages related to server configuration
- FINE: Minimal verbosity
- FINER: Moderate verbosity
- FINEST: Maximum verbosity

Communication:

Resource adapter:

Session beans:

Message beans:

Configuration file:

Logging:

Utilities:

Natural Web I/O Interface pages:

- 2 Specify the characteristics of the output file as described below in the section [Overview of Options for the Output File](#) .
- 3 Specify the log levels for individual modules by selecting the log level from the corresponding drop-down list box.

A brief description for each log level is provided on the **Logging Configuration** page.

- 4 Choose the **Save Configuration** button to write the modifications to the configuration file.



Caution: When you do not choose the **Save Configuration** button but log out instead or leave the configuration tool by entering another URL, your modifications are not written to the configuration file.

Overview of Options for the Output File

The following options are provided for specifying the characteristics of the output file:

Option	Description
File pattern name	<p>The pattern for generating the output file name. Default: "%h/nwolog%g.log" .</p> <p>The default value means that an output file with the name <i>nwolog <number> .log</i> will be created in the home directory of the user who has started the application server.</p> <p>For detailed information on how to specify the pattern, see the Java API documentation .</p>
File type	<p>The format of the output file. Select one of the following entries from the drop-down list box:</p> <ul style="list-style-type: none"> ■ Text format Output in simple text format (default). ■ XML format Output in XML format. <p>The corresponding formatter class is then used.</p>
File size	The maximum number of bytes that is to be written to an output file. Zero (0) means that there is no limit. Default: "0" .
Number of files	The number of output files to be used. This value must be at least "1" . Default: "10" .
File enabled	If set to Yes (default), the file handler is enabled. If set to No , the file handler is disabled.
Append mode	If set to Yes , the logging information is appended to the existing output file. If set to No (default), the logging information is written to a new output file.