

Output Management GUI Client

Installation and Customization

Version 3.5.2

September 2025

This document applies to Output Management GUI Client Version 3.5.2 and all subsequent releases.

Specifications contained herein are subject to change and these changes will be reported in subsequent release notes or new editions.

Copyright © 2003-2025 Software GmbH, Darmstadt, Germany and/or its subsidiaries and/or its affiliates and/or their licensors.

The name Software AG and all Software GmbH product names are either trademarks or registered trademarks of Software GmbH and/or its subsidiaries and/or its affiliates and/or their licensors. Other company and product names mentioned herein may be trademarks of their respective owners.

Detailed information on trademarks and patents owned by Software GmbH and/or its subsidiaries is located at <https://softwareag.com/licenses>.

Use of this software is subject to adherence to Software GmbH's licensing conditions and terms. These terms are part of the product documentation, located at <https://softwareag.com/licenses> and/or in the root installation directory of the licensed product(s).

This software may include portions of third-party products. For third-party copyright notices, license terms, additional rights or restrictions, please refer to "License Texts, Copyright Notices and Disclaimers of Third-Party Products". For certain specific third-party license restrictions, please refer to section E of the Legal Notices available under "License Terms and Conditions for Use of Software GmbH Products / Copyright and Trademark Notices of Software GmbH Products". These documents are part of the product documentation, located at <https://softwareag.com/licenses> and/or in the root installation directory of the licensed product(s).

Use, reproduction, transfer, publication or disclosure is prohibited except as specifically provided for in your License Agreement with Software GmbH.

Document ID: NGC-ONOMINSTALL-352-20250930

Table of Contents

Installation and Customization	v
1 About this Documentation	1
Document Conventions	2
Online Information and Support	2
Data Protection	3
2 Installation of Output Management GUI Client (NGC)	5
Prerequisites	6
Installation Notes	6
Installation Procedure	7
Initializing the Output Management GUI Client	7
Customizing ESM Configuration for Natural	8
Starting the Output Management GUI Client	9
Customizing the Output Management GUI Client Startup	9

Installation and Customization

Notations *vr_s* and *vr*

When used in this documentation, the notations *vr_s* and *vr* represent the product version number.

1 About this Documentation

▪ Document Conventions	2
▪ Online Information and Support	2
▪ Data Protection	3

Document Conventions

Convention	Description
Bold	Identifies elements on a screen.
Monospace font	Identifies service names and locations in the format <code>folder.subfolder.service</code> , APIs, Java classes, methods, properties.
<i>Italic</i>	Identifies: Variables for which you must supply values specific to your own situation or environment. New terms the first time they occur in the text. References to other documentation sources.
Monospace font	Identifies: Text you must type in. Messages displayed by the system. Program code.
{ }	Indicates a set of choices from which you must choose one. Type only the information inside the curly braces. Do not type the { } symbols.
	Separates two mutually exclusive choices in a syntax line. Type one of these choices. Do not type the symbol.
[]	Indicates one or more options. Type only the information inside the square brackets. Do not type the [] symbols.
...	Indicates that you can type multiple options of the same type. Type only the information. Do not type the ellipsis (...).

Online Information and Support

Product Documentation

You can find the product documentation on our documentation website at <https://documentation.softwareag.com>.

Product Training

You can find helpful product training material on our Learning Portal at <https://learn.software-ag.com>.

Tech Community

You can collaborate with Software GmbH experts on our Tech Community website at <https://tech-community.softwareag.com>. From here you can, for example:

- Browse through our vast knowledge base.
- Ask questions and find answers in our discussion forums.
- Get the latest Software GmbH news and announcements.
- Explore our communities.
- Go to our public GitHub and Docker repositories at <https://github.com/softwareag> and <https://hub.docker.com/publishers/softwareag> and discover additional Software GmbH resources.

Product Support

Support for Software GmbH products is provided to licensed customers via our Empower Portal at <https://empower.softwareag.com>. Many services on this portal require that you have an account. If you do not yet have one, you can request it at <https://empower.softwareag.com/register>. Once you have an account, you can, for example:

- Download products, updates and fixes.
- Search the Knowledge Center for technical information and tips.
- Subscribe to early warnings and critical alerts.
- Open and update support incidents.
- Add product feature requests.

Data Protection

Software AG products provide functionality with respect to processing of personal data according to the EU General Data Protection Regulation (GDPR). Where applicable, appropriate steps are documented in the respective administration documentation.

2 Installation of Output Management GUI Client (NGC)

■ Prerequisites	6
■ Installation Notes	6
■ Installation Procedure	7
■ Initializing the Output Management GUI Client	7
■ Customizing ESM Configuration for Natural	8
■ Starting the Output Management GUI Client	9
■ Customizing the Output Management GUI Client Startup	9

See the *Natural* documentation for information on how to start the installation; then follow the instructions of the installation program.

Prerequisites

See *Release Notes* for the current version.

Installation Notes

Broker Access

Ensure that your desired broker is accessible. This means that your installation requires the correct RPC server (SRVNAME) and broker (SRVNODE) names to be entered in your Natural parameter module (usually SYSESM2). Alternatively, you can add the parameter **Specify RPC Client's Default Server Address (DSF)** dynamically at your startup shortcut.

Logical Files

Ensure that your RPC server has got the definitions for logical files 206, 91 and 131.

LFILE 206 must point to your Entire Output Management system file, LFILE 91 must point to your Entire Output Management active data file. If you did not split the Entire Output Management system file, LFILES 206 and 91 will both point to your Entire Output Management system file, because in this case the system file and the active data file are the same file.

LFILE 131 must point to your System Automation Tools log file.

For the editing of separation exit pages, the RPC server has to be started with the Natural profile parameter EDPSIZE being set.

Natural Security

If Natural Security is installed on the server and the server library SYSSAT is protected, the Output Management GUI Client user has to be linked to the library SYSSAT or has to be a member of a group which is linked to SYSSAT.

Installation Procedure

The Output Management GUI Client may already have been installed together with Natural Windows (Development version or Runtime version).

➤ **If not, proceed as follows:**

- 1 Start the Software AG Installer and specify all required information on the different panels.
- 2 When the product selection tree is displayed, expand the **Natural Products > Natural** node.
- 3 Select **Development environment** and/or **Runtime environment**.
- 4 Select **Entire Systems Management**.

This installs Mainframe Navigation, Output Management GUI Client and Entire Operations GUI Client. In addition, it installs the EntireX Miniruntime (if it is not installed already).

- 5 Choose **Next** to continue with the installation.

Initializing the Output Management GUI Client

When the Software AG Installer has finished to installation, you have to initialize the Output Management GUI Client.

➤ **To do so:**

- 1 Select **All Programs > Software AG > Administration > ESM Configuration for Natural *n.n*** (*n.n* = the current version number) from the Windows Start menu.



Note: By default, the Start menu group name is **Software AG**, but this may have been changed by the installation.

- 2 A dialog box will be displayed, in which you open the drop-down list box next to **Output Management GUI Client** and deselect the products you do not want to be initialized.

Save configuration for updates: Select this option, if the configuration of selected/deselected products is to be used again automatically after an INPL of the Natural system library SYSSATGF. Deselect this option, if you wish this dialog to be displayed again to specify a different configuration.

- 3 Choose **OK**.

The Output Management GUI Client will be shown in the Entire Systems Management application window when Entire Systems Management is started again.

Customizing ESM Configuration for Natural

As an administrator, you may customize the dialog of the **ESM Configuration for Natural** *n.n* utility. You can change the following:

- the default setting for the initialization of a GUI component,
- the default language,
- the silent initialization.

To do so, you place an XML file named `esminit.xml` in the `prof` directory of the Natural installation used (typically, this is `C:\SoftwareAG\Natural\prof`).

The basic version of `esminit.xml` contains:

```
<?xml version="1.0" ?>
<!-- language="1" English -->
<!-- language="2" German -->
<esmInit silent="false" language="2">
<!-- Mainframe Navigation -->
<app short="AND" action="remove" />
<!-- Output Management -->
<app short="NOM" action=" " />
<!-- Entire Operations -->
<app short="OPC" action="initialize" />
</esmInit>
```

If you run `ESINIT-D` with the above configuration, the German-language version of the dialog shows the following three actions:

- Initialize for Output Management with default action,
- Initialize for Entire Operations,
- Remove if already installed, or no action for Mainframe Navigation.

Attributes of `esminit.xml`:

Attribute	Explanation	
Optional Entity <code><esmInit></code>		
silent	silent="false"	The dialog is shown for the user action (default).
	silent="true"	The action is performed, but the dialog is not shown.
	If this attribute is not specified, the dialog is shown (as with <code>false</code>).	
language	language="1"	Set dialog language to English (default).
	language="2"	Set dialog language to German.

Attribute	Explanation	
	If this attribute is not specified, the current language of the installed Natural is used.	
update	This attribute can be used to save the configuration which will be used for an automatic restore after an INPL of the Natural system library SYSSATGF. A file named <code>esminitsave.xml</code> containing the selected profile settings will be saved in the <code>prof</code> directory of the Natural installation used (typically, this is <code>C:\SoftwareAG\Natural\prof</code>).	
	update="true"	Save the configuration (default).
	update="false"	Do not save the configuration.
Mandatory Entity <app>		
short	short="AND"	GUI component Mainframe Navigation.
	short="NOM"	GUI component Entire Operations.
	short="OPC"	GUI component Output Management.
	If a GUI component defined by the system is not specified here, its default system settings are used.	
action	action="initialize"	Initialize the GUI component.
	action="remove"	Remove the GUI component.



Note: Previous versions used the program `ESINIT-P` to configure the GUI components. It can still be used. The initialization is then done depending on the existence of the GUI-component-specific Natural library.

Starting the Output Management GUI Client

➤ To start the Output Management GUI Client:

- Select **Entire Systems Management for Natural** from the **Start Menu**, or select the corresponding desktop icon.

Customizing the Output Management GUI Client Startup

It is possible to disable the display of specific applications in the Entire Output Management tree view, even if the applications are installed and shown during normal startup.

➤ To modify your startup:

- Change the `STACK` parameter of your Natural parameter module (usually `SYSESM2`) as follows:

If you want to start ...	STACK Parameter Specification
NGC only	"LOGON SYSSATGF;ESSTRPCD NGC;FIN"
OGC only	"LOGON SYSSATGF;ESSTRPCD OGC;FIN"
OGC and NGC	"LOGON SYSSATGF;ESSTRPCD OGC+NGC;FIN"
OGC and MN	"LOGON SYSSATGF;ESSTRPCD OGC+MN;FIN"

Or:

Make a copy of the Entire Systems Management shortcut (desktop icon) generated by the installation procedure. That is, rename the desktop icon as desired.

Then open the properties of the shortcut and add the following at the end of the target parameter:

If you want to start ...	Target Parameter Specification
NGC only	"STACK=(LOGON SYSSATGF;ESSTRPCD NGC;FIN) "
OGC only	"STACK=(LOGON SYSSATGF;ESSTRPCD OGC;FIN) "
OGC and NGC	"STACK=(LOGON SYSSATGF;ESSTRPCD OGC+NGC;FIN) "
OGC and MN	"STACK=(LOGON SYSSATGF;ESSTRPCD OGC+MN;FIN) "

See the description of the STACK parameter in the *Natural Parameter Reference* documentation for details.