

## **webMethods EntireX Adapter**

### **EntireX Adapter Installation and User's Guide**

Version 9.7

October 2014

This document applies to webMethods EntireX Adapter Version 9.7.

Specifications contained herein are subject to change and these changes will be reported in subsequent release notes or new editions.

Copyright © 2007-2014 Software AG, Darmstadt, Germany and/or Software AG USA, Inc., Reston, VA, USA, and/or its subsidiaries and/or its affiliates and/or their licensors.

The name Software AG and all Software AG product names are either trademarks or registered trademarks of Software AG and/or Software AG USA, Inc. and/or its subsidiaries and/or its affiliates and/or their licensors. Other company and product names mentioned herein may be trademarks of their respective owners.

Detailed information on trademarks and patents owned by Software AG and/or its subsidiaries is located at <http://softwareag.com/licenses>.

This software may include portions of third-party products. For third-party copyright notices, license terms, additional rights or restrictions, please refer to "License Texts, Copyright Notices and Disclaimers of Third-Party Products". For certain specific third-party license restrictions, please refer to section E of the Legal Notices available under "License Terms and Conditions for Use of Software AG Products / Copyright and Trademark Notices of Software AG Products". These documents are part of the product documentation, located at <http://softwareag.com/licenses> and/or in the root installation directory of the licensed product(s).

Use, reproduction, transfer, publication or disclosure is prohibited except as specifically provided for in your License Agreement with Software AG.

**Document ID: XAI-OXAIUSER-97-20150409**

## Table of Contents

webMethods EntireX Adapter Installation and User's Guide .....	v
1 Installing the EntireX Adapter .....	1
2 About the EntireX Adapter .....	3
Architecture and Components .....	4
Package Management .....	7
Adapter Connections .....	8
Adapter Services .....	9
Using Adapter Notifications .....	9
Viewing the Adapter's Update Level .....	10
3 Package Management .....	11
EntireX Adapter Package Management .....	12
Group Access Control .....	14
4 EntireX Adapter Connections .....	15
Before Configuring or Managing Adapter Connections .....	16
Configuring Adapter Connections .....	16
Viewing Adapter Connection Parameters .....	18
Editing Adapter Connections .....	18
Deleting Adapter Connections .....	28
Enabling Adapter Connections .....	28
Disabling Adapter Connections .....	29
5 EntireX Adapter Services .....	31
Before Configuring or Managing Adapter Services .....	32
Configuring Adapter Services .....	33
Using Adapter Services .....	33
Viewing Adapter Services .....	35
Deleting Adapter Services .....	35
Runtime Connection Allocation for Adapter Services .....	36
Configure the Formatting of Decimal and Alphanumeric Parameters .....	36
Configuring Null Value Suppression .....	38
6 Listeners and Adapter Notifications .....	39
Remarks on Reliable RPC Listener Connections .....	40
Before Configuring New Listeners .....	43
Configuring New Listeners .....	43
Testing Listeners .....	45
Viewing Listener Parameters .....	45
Before Configuring or Managing Notifications .....	46
Configuring Adapter Notifications .....	47
Managing EntireX Adapter Notifications .....	48
Viewing Notifications .....	48
Editing Notifications .....	49
Deleting Notifications .....	49
7 Settings and Information .....	51
Adapter Settings .....	52

Connections Information .....	52
Built-in Services for Connections Information .....	53
Support Information .....	55
Services Information .....	55
License Information .....	56
Application Monitoring .....	56
8 Direct RPC .....	59
Configuring Direct RPC .....	60
Encoding for RPC Clients and Servers (Default and Available Codepages) .....	61
Monitoring .....	61
Services .....	62
Servers .....	62
Built-in Services for Direct RPC .....	62
Limitations of Direct RPC .....	64
9 IDL Extraction from Integration Server .....	65
Using the Service <code>pub.wmentirex.listener.generateIDLfromService</code> .....	66
Integration Server Data Types to IDL Mapping .....	67
10 Security Support .....	69
Security Support for Adapter Services .....	70
Security Support for Adapter Listeners .....	71
Support for SSL/TLS .....	72
11 Message Class 0800 - webMethods EntireX Adapter .....	73
12 Message Class 2011 - Connections to IMS Connect .....	77
13 Message Class 2012 - Connections to CICS ECI .....	81
14 Message Class 2023 - Connections to ApplinX .....	85
15 Message Class 0400 - Direct RPC .....	87
16 Message Class 1018 - EntireX RPC-ACI Bridge .....	91
17 Preparing IBM CICS® for ECI .....	95
Defining an ECI Service .....	96
Installation Verification .....	96
Error Handling .....	97
18 Preparing for IMS .....	99
Extracting from COBOL Source .....	100
Extracting from Message Format Service (MFS) .....	100
Troubleshooting .....	100

---

# webMethods EntireX Adapter Installation and User's Guide

---

This guide describes how to install, configure and use the webMethods EntireX Adapter. It contains information for administrators and application developers who want to call remote procedures on mainframes and other hosts, using the EntireX RPC technique. To use this guide effectively, you should be familiar with EntireX's Remote Procedure Call (RPC) technology. For further information see *Related Literature* below.

In this guide the following topics are covered:

<b>Installing</b>	Installing the webMethods EntireX Adapter.
<b>About the EntireX Adapter</b>	EntireX Adapters functionality and features such as calling remote procedures on mainframes and other hosts.
<b>Package Management</b>	How to set up and manage your EntireX Adapter packages and set up access control lists (ACL).
<b>EntireX Adapter Connections</b>	How to configure and manage EntireX Adapter connections.
<b>EntireX Adapter Services</b>	How to configure and manage EntireX Adapter services. EntireX Adapter services allow clients to interact with EntireX RPC servers, using a configured adapter connection.
<b>Listeners and Adapter Notifications</b>	How to configure and manage listeners and adapter notifications.
<b>Settings and Information</b>	Monitoring and tracing in the IS Administration Console.
<b>Direct RPC</b>	Direct communication from an RPC client or server to the EntireX Adapter.
<b>IDL Extraction from Integration Server</b>	Creating an IDL file can be created automatically using IDL Extractor for Integration Server.
<b>Security Support</b>	Security Support in the EntireX Adapter.
<b>EntireX Adapter Messages</b>	A listing of EntireX Adapter messages (message class 0800).
<b>IMS Connect Messages</b>	Messages that can occur with connections from the EntireX Adapter to IMS Connect (message class 2011).
<b>IBM CICS® ECI Messages</b>	Messages that can occur with connections from the EntireX Adapter to IBM CICS® ECI (message class 2012).
<b>ApplinX Messages</b>	Messages that can occur with connections from the EntireX Adapter to ApplinX (message class 2023).
<b>Direct RPC Messages</b>	Messages that can occur with connections from the EntireX Adapter to Direct RPC (message class 0400).
<b>ACI Server Messages</b>	Messages that can occur with connections from the EntireX Adapter to ACI servers (message class 1018).
<b>Preparing IBM CICS® for ECI</b>	The EntireX Adapter supports connections to IBM CICS® ECI to call programs in CICS. Here we describe how to set up the External Call Interface (ECI) within CICS.

## Preparing for IMS

The EntireX Adapter supports connections to IMS. Here we describe how to extract from Message Format Service (MFS).

## Related Literature

---

- *Integration Server Administrator's Guide*. See <https://empower.softwareag.com/Products/Documentation/default.asp> under "webMethods" > "webMethods Product Suite" > "Integration Server" > "Documentation by Product"
- the documentation on *webMethods EntireX*, including the *webMethods EntireX Broker* and *webMethods EntireX RPC Servers*. See <https://empower.softwareag.com/Products/Documentation/default.asp> under "webMethods" > "webMethods Product Suite" > "Documentation by Product".
- the documentation on the Software AG Designer. See <https://empower.softwareag.com/Products/Documentation/default.asp> under "webMethods" > "webMethods Product Suite" > "Documentation by Product"
- The Software AG Designer Online Help.
- *Software AG Installer*. See <https://empower.softwareag.com/Products/Documentation/default.asp> under "Software AG Installer and Update Manager"
- *webMethods Adapter Development Kit User's Guide*. See <https://empower.softwareag.com/Products/Documentation/default.asp> under "webMethods" > "webMethods Adapters and eStandards Modules" > "Adapters"
- the documentation of the Eclipse Update Manager, located at <http://help.eclipse.org/helios/topic/org.eclipse.platform.doc.user/tasks/tasks-129.htm>
- Natural Product Documentation at <https://empower.softwareag.com/Products/Documentation/default.asp>.

This documentation is part of a documentation module including the following documents:

- *webMethods EntireX Adapter Release Notes*.
- For the EntireX Workbench (*webMethods Integration Server Wrapper* and *Software AG IDL Extractor for webMethods Integration Server*), refer to <https://empower.softwareag.com/Products/Documentation/default.asp>.

# 1 Installing the EntireX Adapter

---

This chapter describes how to install and configure the EntireX Adapter and is intended for system administrators. For prerequisites, see *Supported Versions of webMethods Integration Server and EntireX Workbench* in the *Release Notes*.

- To install the EntireX Adapter into an Integration Server, use the Software AG Installer. For further information, see *Software AG Installation Guide*.
- To use connections to IMS Connect, CICS ECI or Direct RPC, you need a license file for the EntireX Adapter.

▶ **To use connections to IMS Connect, CICS ECI, or Direct RPC**

- 1 Copy the license file to a safe folder. The package WmEntireX is not a safe folder. The Integration Server deletes the license file on update.
- 2 Change the location of the license file in the License Information Screen in the Adapter Administration GUI (see [License Information](#)).

The EntireX Adapter does not assume that the EntireX Mini Runtime is installed. Installing the EntireX Adapter into the Integration Server is all that is required on the machine of the Integration Server.

- To configure the EntireX Adapter, see [Settings and Information](#) and [Direct RPC](#).



## 2 About the EntireX Adapter

---

▪ Architecture and Components .....	4
▪ Package Management .....	7
▪ Adapter Connections .....	8
▪ Adapter Services .....	9
▪ Using Adapter Notifications .....	9
▪ Viewing the Adapter's Update Level .....	10

The EntireX Adapter is an add-on to the webMethods Integration Server that enables you to call remote procedures on mainframes and other hosts, using the EntireX RPC technique. The adapter provides seamless and real-time communication with EntireX RPC servers and clients, Natural RPC servers and clients, ACI Servers, ApplinX, IMS Connect, and CICS ECI. Using the EntireX Adapter, Integration Server applications can create and run services that can exchange messages with RPC servers and clients on mainframe and other hosts.


## Architecture and Components

---

The EntireX Adapter enables you to configure the following components:

- **Adapter Connections**  
Enable the webMethods Integration Platform to connect at runtime to EntireX RPC servers, Natural RPC servers, ACI servers, ApplinX, IMS Connect, and CICS ECI.
- **Adapter Services**  
Perform operations on EntireX RPC servers and clients, using the built-in services provided with the EntireX Adapter.
- **Listener Notifications**  
Provides synchronous notification of RPC messages that are called by EntireX RPC clients.

The following diagram illustrates how the EntireX Adapter interfaces with EntireX RPC servers and clients. The various architectural pieces involved in the integration process are described below the diagram.



### ■ webMethods Integration Server

The EntireX Adapter is installed and runs on the Integration Server.

### ■ WmART Package

The WmART package provides a common framework for webMethods Adapters to utilize the Integration Server functionality, making the Integration Server the runtime environment for the EntireX Adapter. The WmART package is installed with the Integration Server.

### ■ EntireX Adapter

The EntireX Adapter is delivered as an adapter with the Software AG Installer. The package is called WmEntireX. The EntireX Adapter provides IS Administration Console and Software AG Designer user interfaces that enable you to configure and manage adapter connections, adapter services, and adapter notifications. However, it is recommended to use the Eclipse-based EntireX Workbench with the plug-ins for the EntireX Adapter to generate adapter connections and all

other nodes for the Integration Server. The plug-in supports secure connections to the Integration Server and updating the nodes.

■ **Adapter Connection Templates**

Adapter connections enable the EntireX Adapter to connect to EntireX RPC servers and clients. You must configure an adapter connection before you can configure adapter services or adapter notifications. The EntireX Adapter's connections are generated from a Software AG IDL file at design time with the EntireX Workbench (Eclipse-based). The IDL (Interface Definition Language) defines the interface of the remote procedures. Use the IS Administration Console to configure adapter connections. For a detailed description of adapter connections, see *EntireX Adapter Connections* (main section).

■ **Adapter Notification Template**

Adapter notifications enable the EntireX Adapter to listen to requests from EntireX RPC clients. These are used only for Reliable RPC Listener connections. The EntireX Adapter provides an adapter notification template that enables you to configure adapter notifications. You automatically create adapter notifications in the Eclipse plug-in when you create a Reliable RPC Connection with the Listener. However, you can use the Designer using the EntireX Adapter's notification templates. For a detailed description of adapter notifications, see *Listeners and Adapter Notifications*.

■ **EntireX RPC Servers and Clients**

See the *webMethods EntireX Administration* (at <https://empower.softwareag.com/Products/Documentation/default.asp>) for details on RPC servers and clients. The following table gives an overview of the connection types discussed above:

Connection Type	Connects to	Integration Server outbound	Integration Server inbound	IDL	Additional Nodes	Settings to generate	IDL Parameters
RPC Connection	EntireX Broker	X	-	one per IDL library	one adapter service for each IDL program	RPC Connection & Adapter Services	IN, INOUT, OUT
Reliable RPC Connection	EntireX Broker	X	-	one per IDL library	one adapter service for each IDL program	Reliable RPC Connection & Adapter Services	IN
RPC Listener Connection	EntireX Broker	-	X	one per IDL library	one adapter listener per IDL library	RPC Connection & Listener	IN, INOUT, OUT
Reliable RPC Listener Connection	EntireX Broker	-	X	one per IDL library	one adapter Listener per IDL library and for each IDL program a notification, a document type, a	Reliable RPC Connection & Listener	IN

Connection Type	Connects to	Integration Server outbound	Integration Server inbound	IDL	Additional Nodes	Settings to generate	IDL Parameters
					trigger, and a wrapping service		
Connection to IMS Connect	IMS Connect	X	-	one per IDL library (with one IDL program)	one adapter service for the IDL program	IMS Connect	IN, INOUT, OUT
CICS ECI Connection	CICS ECI	X	-	one per IDL library	one adapter service for each IDL program	CICS ECI Connection & Adapter Services	IN, INOUT, OUT
ApplinX Connection	ApplinX Server	X	-	one per ApplinX procedure group	one adapter service for each ApplinX path procedure	ApplinX Connection & Adapter Services	(invisible)
Direct RPC Connection	RPC Server	X	-	one per IDL library	one adapter service for each IDL program	Direct RPC Connection & Adapter Services	IN, INOUT, OUT
Direct RPC Listener Connection	PRC Client	-	X	one per IDL library	one adapter per IDL library	Direct RPC Connection & Listener	IN, INOUT, OUT
ACI Server Connection	EntireX BrokerXx	X	-	one per IDL library	one adapter service for each IDL program	ACI Server Connection & Adapter Services	IN, INOUT, OUT

## Package Management

The EntireX Adapter is provided as a package called WmEntireX. The adapter package is managed the same way as any package on the Integration Server. There are several considerations when you set up and manage your packages on the Integration Server:

- Create user-defined packages for your connections and adapter services. See [EntireX Adapter Package Management](#) for details.
- Understand how package dependencies work so you make the best decisions regarding how you manage your connections and adapter services. See [Package Dependency Requirements and Guidelines](#) for details.
- Control which groups have access to which adapter services. See [Group Access Control](#) for details.

- Enable and disable packages. See [Importing and Exporting Packages](#) for details.

## Adapter Connections

---

The EntireX Adapter uses adapter connections to define how its adapter services and adapter notifications connect to EntireX RPC servers and clients. Each EntireX Adapter connection contains a set of connection parameters, including the logon parameters that the adapter requires to connect to the EntireX Broker. You configure *extended properties* of a connection using the IS Administration Console. For instructions on configuring and managing EntireX Adapter connections, see [EntireX Adapter Connections](#) (main section). EntireX Adapter connections can be used only for adapter services or only for adapter notifications. A connection cannot be used simultaneously by services and notifications. If this is required, duplicate a connection and use one connection for services and the other for notifications.

This section covers the following topics:

- [Connection Pooling](#)
- [Runtime Behavior of Connection Pools](#)
- [Built-in Services for Connections](#)

### Connection Pooling

The Integration Server includes a connection management service that dynamically manages connections and connection pools based on configuration settings that you specify for the connection. All adapter services use connection pooling. A connection pool is a collection of connections with the same set of attributes. The Integration Server maintains connection pools in memory. Connection pools improve performance by enabling adapter services to reuse open connections rather than opening new connections.

### Runtime Behavior of Connection Pools

When you enable a connection, the Integration Server initializes the connection pool, creating the number of connection instances you specified in the connection's `Minimum Pool Size` field. Whenever an adapter service needs a connection, the Integration Server provides a connection from the pool. If no connection is available in the pool, and the `Maximum Pool Size` has not been reached, the server creates one or more new connections (according to the number specified in `Pool Increment Size`) and adds them to the connection pool. If the pool is full (as specified in `Maximum Pool Size`), the requesting service will wait for the Integration Server to obtain a connection, up to the length of time specified in the `Block Timeout` field, until a connection becomes available. Periodically, the Integration Server inspects the pool and removes inactive connections that have exceeded the expiration period specified in `Expire Timeout`. You can enable the system to retry the initialization any number of times, at specified intervals. For information on configuring connections, see [EntireX Adapter Connections](#) (main section).

## Built-in Services for Connections

Integration Server provides built-in services that enable you to programmatically control connections. You can use them to enable and disable a connection, and to return usage statistics, the current state ("Enabled" or "Disabled") and error status for a connection. These services are located in the WmART package, in the *pub.art.connection* folder. For details, see the *webMethods Integration Server Built-in Services Reference*.

## Adapter Services

---

Adapter services enable the EntireX Adapter to initiate operations that interact with EntireX providers. You configure adapter services using adapter service templates, which are provided with the EntireX Adapter. Configuring a new service from an adapter service template is straightforward. There are two alternatives: use the EntireX Workbench or use the Designer. Using the EntireX Workbench is recommended. You create an adapter connection together with a set of adapter services, one for each IDL program in the IDL library you are using to create the connection. Using the Designer, you assign a default adapter connection to the service, select the adapter service template, and select the EntireX subprogram to call. This has to be done for each service separately.

After you configure a service, you can incorporate it into a flow or Java service to interact with an EntireX broker. For example, you can create a flow service that calls an EntireX RPC server.

## Using Adapter Notifications

---

Adapter notifications are only needed for Reliable RPC Listener connections, sending RPC messages with only IN parameters to the Integration Server. The EntireX Adapter provides a notification called *Asynchronous Listener Notification*, which monitors a specified Reliable RPC Listener connection and notifies the adapter when an RPC call arrives at that connection. You configure the notification to invoke a flow or Java service using the data from the notification. See [Configuring Adapter Notifications](#) for instructions.

Using the Eclipse plug-ins of the adapter will generate all the objects needed for a Reliable RPC Listener connection automatically, including the listener and adapter notifications.

## Viewing the Adapter's Update Level

---

You can view the list of updates that have been applied to the adapter. The list of updates appears in the Updates field on the “About page” in the IS Administration Console.

# 3 Package Management

---

- EntireX Adapter Package Management ..... 12
- Group Access Control ..... 14

This chapter describes how to set up and manage your EntireX Adapter packages, set up access control lists (ACLs).

## EntireX Adapter Package Management

---

The EntireX Adapter is provided as a package called WmEntireX. This section covers the following topics:

- [Package Dependency Requirements and Guidelines](#)
- [Enabling and Disabling Packages](#)
- [Importing and Exporting Packages](#)

### Package Dependency Requirements and Guidelines

This section contains a list of dependency requirements and guidelines for user-defined packages. For instructions on setting package dependencies, see *webMethods Service Development Help*.

- A user-defined package must be dependent on its associated adapter package, WmEntireX. (The WmEntireX package is dependent on the WmART package.)
- Package dependencies ensure that at startup the Integration Server automatically loads or reloads all packages in the proper order: the WmART package first, the adapter package next, and the user-defined package(s) last. The WmART package is automatically installed when you install the Integration Server. You should not need to reload the WmART package manually.



**Tip:** When you create connections, adapter services, and adapter notifications, define them in user-defined packages rather than in the WmEntireX package. This makes it easier to manage packages. As you create user-defined packages in which to store connections, adapter services, and adapter notifications, use the package management functionality provided in the Designer and set the user-defined packages to be dependent on the WmEntireX package. That way, whenever the WmEntireX package loads or reloads, the user-defined packages load automatically as well.

- If the connections and adapter services of an adapter are defined in different packages, then:
  - a package that contains the connection(s) must have a dependency on the adapter package.
  - packages that contain adapter services must have a dependency on their associated connection package.
- Keep connections for different adapters in separate packages so that you do not create interdependencies between adapters. If a package contains connections for two different adapters, and you reload one of the adapter packages, the connections for both adapters will reload automatically.

- The Integration Server will not allow you to enable a package if it has a dependency on another package that is disabled. That is, before you can enable your package, you have to enable all packages on which your package depends. For information on enabling packages, see [Enabling and Disabling Packages](#).
- The Integration Server will allow you to disable a package even if another package that is enabled has a dependency on it. Therefore, you have to manually disable any user-defined packages that have a dependency on the adapter package before you disable the adapter package. For information on disabling packages, see [Enabling and Disabling Packages](#).
- You can give connections, adapter services, and notifications the same name provided that they are in different folders and packages.

## Enabling and Disabling Packages

All packages are automatically enabled by default. To temporarily prohibit access to the elements in a package, disable the package. When you disable a package, the server unloads all of its elements from memory. Disabling a package prevents the Integration Server from loading that package at startup.

### ▶ To enable a package

- 1 Open the IS Administration Console if it is not already open.
- 2 In the **Packages** menu of the navigation area, click **Management**.
- 3 Click **No** in the **Enabled** column.

As a result, the server displays a tick and "Yes" in the **Enabled** column.



**Note:** Enabling an adapter package will not cause its associated user-defined package(s) to be reloaded. For information on reloading packages, see the *webMethods Service Development Help*.



**Important:** Before you manually enable a user-defined package, you first have to enable its associated adapter package (WmEntireX). Similarly, if your adapter has multiple user-defined packages, and you want to disable some of them, disable the adapter package first. Otherwise, errors will be issued when you try to access the remaining enabled user-defined packages. See *Managing Packages* in the *webMethods Service Development Help* documentation or choose **Software AG Designer Guides > webMethods Service Development Help > Managing Packages** in the Software AG Designer online help.

### ▶ To disable a package

- 1 Open the IS Administration Console if it is not already open.
- 2 In the **Packages** menu of the navigation area, click **Management**.

- 3 Click **Yes** in the **Enabled** column for the package that you want to disable. The server issues a prompt to verify that you want to disable the package. Click **OK** to disable the package. When the package is disabled, the server displays "No" in the **Enabled** column.

A disabled package will:

- remain disabled until you explicitly enable it using the IS Administration Console.
- not listed in the Designer.

### Importing and Exporting Packages

To export packages, use the Designer. You can export the package to a ZIP file and save it to your hard drive. The ZIP file can then be imported for use by another Integration Server.

 **Important:** Do not rename packages you export. The rename function is comparable to moving a package: when you import the renamed package, you lose any triggers, connections, and notifications associated with this package. For details on managing packages, see *webMethods Service Development Help*.

### Group Access Control

---

To control which development group has access to which adapter services, use access control lists (ACLs). You can use ACLs to prevent one development group from inadvertently updating the work of another group, or to allow or deny access to services that are restricted to one group but not to others. For general information on assigning and managing ACLs, see *webMethods Service Development Help*.

# 4 EntireX Adapter Connections

---

- Before Configuring or Managing Adapter Connections ..... 16
- Configuring Adapter Connections ..... 16
- Viewing Adapter Connection Parameters ..... 18
- Editing Adapter Connections ..... 18
- Deleting Adapter Connections ..... 28
- Enabling Adapter Connections ..... 28
- Disabling Adapter Connections ..... 29

This chapter describes how to configure and manage EntireX Adapter connections.



**Tip:** It is recommended to create connections with the webMethods Integration Server Wrapper of the EntireX Workbench. Connections which are used dynamically can be created with the IS Administration Console.

## Before Configuring or Managing Adapter Connections

---

### ▶ To prepare to configure or manage adapter connections

- 1 Install the webMethods Integration Server and the EntireX Adapter on the same machine, using the Software AG Installer.
- 2 Make sure you have webMethods administrator privileges so that you can access the EntireX Adapter's administrative screens. See the *Administering webMethods Integration Server* for information on setting user privileges.
- 3 Start your Integration Server and the IS Administration Console, if they are not already running.
- 4 Using the IS Administration Console, make sure the WmEntireX package is enabled. See *Importing and Exporting Packages* for instructions.
- 5 If you have not already done so, use the Designer to create a user-defined package to contain the connection. For more information on managing packages for the adapter, see *EntireX Adapter Package Management*.

## Configuring Adapter Connections

---

When you configure EntireX Adapter connections, you specify information that the Integration Server uses to connect to an EntireX RPC server or client, or to IMS Connect or CICS ECI. You create EntireX Adapter connections using the EntireX Workbench. This ensures that the information generated from the interface definition stored in the Software AG IDL file is present. A wizard inside the EntireX Workbench allows you to configure the most common parameters of the connection. Using the IS Administration Console, you have access to all parameters of a connection.

The EntireX Adapter supports the following connection types:

1. EntireX RPC Connection
2. EntireX Reliable RPC Connection
3. EntireX Direct RPC Connection
4. EntireX RPC Listener Connection

5. EntireX Reliable RPC Listener Connection
6. EntireX Direct RPC Listener Connection
7. Connection to IMS Connect
8. CICS ECI Connection
9. ApplinX Connection
10. ACI Server Connection

For connections of type “EntireX RPC”, “EntireX Reliable RPC”, “ApplinX”, “EntireX Direct RPC”, “IMS Connect”, “CICS ECI”, and “ACI Server”, the EntireX Workbench wizard additionally creates an EntireX Adapter service for each program of the IDL file; see [EntireX Adapter Services](#) for further information.

For connections of type “EntireX RPC Listener”, “EntireX Direct RPC Listener” and “EntireX Reliable RPC Listener”, the EntireX Workbench wizard additionally creates an EntireX Adapter listener; see also [Listeners and Adapter Notifications](#).

▶ **To create a connection**

- 1 Start the EntireX Workbench.
- 2 Navigate to the Software AG IDL file you want to use.
- 3 On the IDL file, right-click and choose **Generate webMethods IS Connection from Software AG IDL...**
- 4 Follow the wizard (Integration Server Wrapper), which guides you through the creation of the adapter connection and the adapter services or adapter listener.

As a result, the connection you created appears on the adapter's connections screen and in the Designer **Package Navigator** view.



**Note:** It is not possible to generate new connections using **Configure New Connection** on the **Connections screen** of the EntireX Adapter in the IS Administration Console because such connections would not have any metadata. Only connections generated by the Designer have the mandatory metadata. However, it is possible to create a new connection by copying an existing connection on the **Connections screen**. This is useful for dynamically selected connections where the metadata is not generated from the interface definition (Software AG IDL file). To use dynamically selected connections with `$connectionName`, see chapter 8 in *webMethods Adapter Development Kit User's Guide Version 6.5*, see <https://empower.softwareag.com/Products/Documentation/default.asp> under “webMethods” > “Adapters”.

## Viewing Adapter Connection Parameters

---

You can view a connection's parameters using the IS Administration Console or the Designer.

▶ **To view the parameters for a connection using the IS Administration Console**

- 1 In the **Adapters** menu in the IS Administration Console navigation area, click **EntireX Adapter**.
- 2 On the **Connections** screen, click the **View** icon for the connection you want to see. The **View Connection** screen displays the parameters for the connection. For descriptions of the connection parameters, see [Configuring Adapter Connections](#).
- 3 Click **Return to EntireX Adapter Connections** to return to the main connections screen.

▶ **To view the parameters for a connection using the Designer**

- 1 Start the Designer if it is not already running.
- 2 From the Designer **Package Navigator** view, open the package and folder in which the connection is located.
- 3 Click the connection you want to view. The parameters for the connection appear on the **Connection Information** tab. For descriptions of the connection parameters, see [Configuring Adapter Connections](#).

## Editing Adapter Connections

---

If the login information for a server changes, or if you want to redefine parameters that a connection uses when connecting to a server, you can update the connection's parameters. This section describes how to edit a connection and lists parameter settings for the connection types covered. The following topics are covered:

- [Editing a Connection](#)
- [Connection Parameters for RPC Connections](#)
- [Connection Parameters for Reliable RPC Connections](#)
- [Connection Parameters for RPC Listener Connections and Reliable RPC Listener Connections](#)
- [Connection Parameters for Direct RPC Connections](#)
- [Connection Parameters for Direct RPC Listener Connections](#)
- [Connection Parameters for ACI Server Connections](#)
- [Connection Parameters for Connections to IMS Connect](#)
- [Connection Parameters for CICS ECI Connections](#)
- [Connection Parameters for ApplinX Connections](#)

- [Common Connection Management Properties \(for all Connection Types\)](#)

## Editing a Connection

You edit (and modify) adapter connections using the IS Administration Console.

### ▶ To edit a connection

- 1 In the **Adapters** menu in the IS Administration Console navigation area, click **EntireX Adapter**.
- 2 Make sure that the connection is disabled before editing it. See [Disabling Adapter Connections](#) for instructions.
- 3 On the **Connections** screen, click the **Edit** icon for the connection you want to edit. The **Edit Connection** screen displays the current parameters for the connection. Update the connection's parameters by typing or selecting the values you want to specify. The tables below give a complete listing of parameters for the following connection types:
  - [“RPC Connection”](#)
  - [“Reliable RPC Connection”](#)
  - [“RPC Listener Connections”](#) and [“Reliable RPC Listener Connections”](#)
  - [“Direct RPC Connection”](#)
  - [“Direct RPC Listener Connection”](#)
  - [“ACI Server Connection”](#)
  - [“IMS Connect”](#)
  - [“CICS ECI ”](#)
  - [“ApplinX Connections”](#)
- 4 On the Connections screen, edit the connection management properties (connection pooling). The tables in [Common Connection Management Properties \(for all Connection Types\)](#) give a complete listing of parameters.
- 5 Click **Save Changes** to save the connection and return to the Connections screen.

## Connection Parameters for RPC Connections

Parameter	Description	Default	Can be set from the EntireX Workbench	Can be set with service
Broker ID	The ID of the broker you want to connect to. This ID consists of a host and an optional port. Default for the port is 1971.	localhost	Yes	No
Server Address	The address of the RPC server registered to the broker above. The address is given in the format <class>/<server>/<service>.	RPC/SRV1/CALLNAT	Yes	Yes
Logon User	The name of the user to log on to the broker.		Yes	Yes
Logon Password	The password for the user above.		Yes	Yes
Retype Logon Password	Verification of the password.		Not applicable	Not applicable
Encryption	The level of broker encryption to be used for the RPC call.	No_Encryption	No	No
Encoding	The character encoding to be used for the RPC connection in the Integration Server. Default: the encoding of the Integration Server.		Yes	No
Compression Level	The level of broker data compression.	NO_COMPRESSION	No	No
Timeout	The number of seconds to wait for a response from the RPC server.	60S	No	No
RPC Library Name	The name of the RPC library. Default: the library name used to generate the connection. Mainly used to override the library name for Natural RPC servers. <sup>(1)</sup>		No	Yes
RPC User	The RPC user for Natural Security. <sup>(1)</sup>		No	Yes
RPC Password	The password for the user above. <sup>(1)</sup>		No	Yes
Retype RPC Password	Verification of the password above.		Not applicable	Not applicable
Metadata Information	<b>Caution:</b> Do not change this generated property. It contains timestamp, IDL file name, library name, and version of the EntireX Workbench.		Generated	No
Transaction Type	The transaction type, "local transactions" and "no transactions" are supported.	none	No	No

**Notes:**

1. Depending on the server configuration, some Natural RPC servers need the RPC library name. See the documentation of the Natural RPC Server at <https://empower.softwareag.com/Products/Documentation/default.asp> for details.

The transaction type “local” of the Integration Server is mapped to conversational RPC for RPC connections and Reliable RPC with client-commit for Reliable RPC connections. See Appendix B in *webMethods Adapter Development Kit User's Guide Version 6.5* for transactions of the Integration Server. XA transactions are not supported by the EntireX Adapter.

**Connection Parameters for Reliable RPC Connections**

Parameter	Description	Default	Can be set from the EntireX Workbench	Can be set dynamically with service
Broker ID	The ID of the broker you want to connect to. This ID consists of a host and an optional port. Default for the port is "1971".	localhost	Yes	No
Server Address	The address of the RPC server registered to the broker above. The address is given in the format <class>/<server>/<service>.	RPC/SRV1/CALLNAT	Yes	Yes
Logon User	The name of the user to log on to the broker.		Yes	Yes
Logon Password	The password for the user above.		Yes	Yes
Retype Logon Password	Verification of the password.		Not applicable	Not applicable
Encryption	The level of broker encryption to be used for the RPC call	No_Encryption	No	No
Encoding	The character encoding to be used for the RPC connection in the Integration Server. Default: the encoding of the Integration Server.		Yes	No
Compression Level	The level of broker data compression.	NO_COMPRESSION	No	No
RPC Library Name	The name of the RPC library. Default: the library name used to generate the connection. Mainly used to override the library name for Natural RPC servers.		No	Yes
RPC User	The RPC user for Natural Security.		No	Yes
RPC Password	The password for the user above		No	Yes

Parameter	Description	Default	Can be set from the EntireX Workbench	Can be set dynamically with service
Retype RPC Password	Verification of the password above.		Not applicable	Not applicable
Metadata Information	<b>Caution:</b> Do not change this generated property. It contains timestamp, IDL file name, library name, and version of the EntireX Workbench.		Generated	No
Transaction Type	The transaction type. "local transactions" and "no transactions" are supported.	none	No	No

### Connection Parameters for RPC Listener Connections and Reliable RPC Listener Connections

Parameter	Description	Default	Can be set from the EntireX Workbench
Broker ID	The ID of the broker you want to connect to. This ID consists of a host and an optional port. Default for the port is "1971".	localhost	Yes
Server Address	The address of the RPC server registered to the broker above. The address is given in the format <class>/<server>/<service>.	RPC/SRV1/CALLNAT	Yes
Logon User	The name of the user to log on to the broker.		Yes
Logon Password	The password for the user above.		Yes
Retype Logon Password	Verification of the password.		Not applicable
Encryption	The level of broker encryption to be used for the RPC call.	No_Encryption	No
Encoding	The character encoding to be used for the RPC connection in the Integration Server. Default: the encoding of the Integration Server.		Yes
Compression Level	The level of broker data compression.	NO_COMPRESSION	No
Metadata Information	<b>Caution:</b> Do not change this generated property. It contains timestamp, IDL file name, library name, and version of the EntireX Workbench.		Generated

## Connection Parameters for Direct RPC Connections

Parameter	Description	Default	Can be set from the EntireX Workbench	Can be set dynamically with service
Server Address	The address of the RPC server. The address is given in the format <class>/<server>/<service>.	RPC/SRV1/CALLNAT	Yes	Yes
Timeout	The number of seconds to wait for a response from the RPC server.	60S	No	No
RPC Library Name	The name of the RPC library. Default: the library name used to generate the connection. Mainly used to override the library name for Natural RPC servers.		No	Yes
RPC User	The RPC user for Natural Security.		No	Yes
RPC Password	The password for the user above.		No	Yes
Retype RPC Password	Verification of the password above.		Not applicable	Not applicable
Metadata Information	Caution: Do not change this generated property. It contains timestamp, IDL file name, library name, and version of the EntireX Workbench.		Generated	No
Transaction Type	The transaction type "local transactions" and "no transactions" are supported.	none	No	No

The transaction type "local" of the EntireX Adapter connection is mapped to conversational RPC for RPC connections and Reliable RPC with client-commit for Reliable RPC connections. See Appendix B in *webMethods Adapter Development Kit User's Guide*, Version 6.5 for transactions of the Integration Server. XA transactions are not supported by the EntireX Adapter.

## Connection Parameters for Direct RPC Listener Connections

Parameter	Description	Default	Can be set from the EntireX Workbench
Server Address	The address of the RPC server. The address is given in the format <class>/<server>/<service>.	RPC/SRV1/CALLNAT	Yes
Metadata Information	<b>Caution:</b> Do not change this generated property. It contains timestamp, IDL file name, library name, and version of the EntireX Workbench.		Generated

## Connection Parameters for ACI Server Connections

Parameter	Description	Default	Can be set from the EntireX Workbench
Broker ID	The ID of the broker you want to connect to. This ID consists of a host and an optional port. Default for the port is 1971.	localhost	Yes
Server Address	The address of the RPC server registered to the broker above. The address is given in the format <class>/<server>/<service>. The address may contain an asterix ( '*') as a wildcard which is substituted by the IDL program name at runtime. This helps you to use only one connection for multiple IDL programs or adapter services.	RPC/SRV1/CALLNAT	Yes
Logon User	The name of the user to log on to the broker.		Yes
Logon Password	The password for the user above.		Yes
Retype Logon Password	Verification of the password.		Not applicable
Encryption	The level of broker encryption to be used for the RPC call.	No_Encryption	No
Encoding	The character encoding to be used for the RPC connection in the Integration Server. Default: the encoding of the Integration Server.		No
Timeout	The number of seconds to wait for a response from the RPC server.	60S	No
Server Type	Defines how arrays of groups are marshalled. Allowed values are "COBOL" and "Natural".  <b>Note:</b> See <i>Writing ACI Servers for the RPC-ACI Bridge in COBOL/Natural</i> in the <i>EntireX RPC-ACI Bridge</i> documentation for restrictions concerning ACI servers.	COBOL	No
Metadata Information	<b>Caution:</b> Do not change this generated property. It contains timestamp, IDL file name, library name, and version of the EntireX Workbench.		Generated

## Connection Parameters for Connections to IMS Connect

Parameter	Description	Default	Can be set from EntireX Workbench	Can be set dynamically with service
Host	Hostname of IMS Connect.		Yes	No
Port	IMS Connect Port.		Yes	No
IMS Connect Datastore ID	Name of the data store, as defined in the IMS Connect configuration member.		Yes	Yes
Encoding	The character encoding used to call IMS Connect. It is recommended to specify the appropriate EBCDIC encoding.	cp037	Yes, default value is cp037	No
Socket Timeout <sup>1</sup>	Socket timeout (in milliseconds). The minimum value is 2.000 ms. If a lower value is specified, it will be changed to 2.000.	10000	No	No
Check for DFS Errors	Return an error and do not return the message if it might contain a DFS error message.	true	No	No
Logical Terminal ID	IMS Connect logical terminal ID, maximal 8 bytes (optional).		No	Yes
Use old Exit	Use old IMS Connect user message exit if set to "true". The old exit name is "*SAMPLE*", the new exit name is "*SAMPL1*".	true	No	No
Exit Name	Optional name of the IMS Connect user message exit.	Default name for old exit is "*SAMPLE*", for new exit "*SAMPL1*"	No	No
RACF User ID	The name of the user to log on to IMS Connect.		Yes	Yes
RACF Password / PassTicket	The password of the user above.		Yes	Yes
Retype RACF Password / PassTicket	Verification of the password above.		Not applicable	Not applicable
RACF Group Name	Security setting		No	Yes
RACF Application Name	Defined to RACF on the PKTDATA definition.		No	Yes
SSL Parameters	Truststore and optional certificate. Example: trust_store=CACerts.jks		No	No
Metadata Information	<b>Caution:</b> Do not change this generated property. It contains timestamp, IDL file		Generated	No

Parameter	Description	Default	Can be set from EntireX Workbench	Can be set dynamically with service
	name, library name, and version of the EntireX Workbench.			
Use IDL program as transaction name	Automatically use the IDL program name as transaction name. If set to "true" or "yes", 10 bytes are used for the transaction name. If set to a number, this number of bytes is used for the transaction name.	false	No	No

**Notes:**

1. The socket timeout value is used to set the IMS Connect timer value. The timer value specifies the delay that IMS Connect will wait until IMS returns data to IMS Connect, which in turn will be sent to the adapter. If the socket timeout is less than one minute, the IMS timer value is one second less than the socket timeout. If the socket timeout is less than one hour, the IMS timer value is one minute less than the socket timeout. The maximum IMS timer value is 60 minutes.

**Connection Parameters for CICS ECI Connections**

Parameter	Description	Default	Can be set from EntireX Workbench	Can be set dynamically with service
Host	Hostname of CICS.		Yes	No
Port	CICS Port		Yes	No
CICS Mirror Transaction ID	Name of the CICS mirror transaction. Default is "CPMI", which is the default dispatching transaction for ECI.	CPMI	Yes	Yes
Encoding	The character encoding used to call CICS ECI. It is recommended to specify the appropriate EBCDIC encoding	cp037	Yes	No
Socket Timeout	Socket timeout (in milliseconds)	10000	No	No
RACF User ID	The name of the user to log on to CICS ECI.		Yes	Yes
RACF Password / PassTicket	The password for the user above.		Yes	Yes
Retype RACF Password / PassTicket	Verification of the password above		No	No
SSL Parameters	Truststore and optional certificate. Example: trust_store=CACerts.jks		No	No
Metadata Information	<b>Caution:</b> Do not change this generated property. It contains timestamp, IDL file		Generated	No

Parameter	Description	Default	Can be set from EntireX Workbench	Can be set dynamically with service
	name, library name, and version of the EntireX Workbench.			

### Connection Parameters for ApplinX Connections

Parameter	Description	Default	Can be set from EntireX Workbench
Host	Hostname of ApplinX server.		Yes
Port	ApplinX server Port.		Yes
Secure connection	Set to "true" for a secure connection.	false	No
Metadata Information	<b>Caution:</b> Do not change this generated property. It contains timestamp, IDL file name, library name, and version of the EntireX Workbench.		Generated

### Common Connection Management Properties (for all Connection Types)

Parameter	Description
Enable Connection Pooling	Enables the adapter to use connection pooling. Default: <code>true</code> . See <a href="#">EntireX Adapter Connections</a> for more information on connection pooling.
Minimum Pool Size	If connection pooling is enabled, this field specifies the minimum number of connection objects that remain in the connection pool at all times. When the adapter creates the pool, it creates this number of connections. Default: 1.
Maximum Pool Size	The maximum number of connection objects that can exist in the connection pool. The adapter will reuse any inactive connections in the pool or, if all connections are active and the connection pool has reached its maximum size, the adapter will wait for a connection to become available. Default: 10.
Pool Increment Size	If connection pooling is enabled, this field specifies the number of connections by which the pool will be incremented if connections are needed, up to the maximum pool size. Default: 1.
Block Timeout	If connection pooling is enabled, this field specifies the number of milliseconds that the Integration Server will wait to obtain a connection before it times out and returns an error. Default: 1000.
Expire Timeout	If connection pooling is enabled, this field specifies the number of milliseconds that an inactive connection can remain in the pool before it is closed and removed from the pool. For example, to specify 10 seconds, specify 10000. Enter 0 to specify no timeout. Default: 1000.  <b>Note:</b> The adapter will never violate the <code>Minimum Pool Size</code> parameter. These connections remain in the pool regardless of how long they are inactive.

Parameter	Description
Startup Retry Count	The number of times that the system should attempt to initialize the connection pool at startup if the initial attempt fails. Default: 0.
Startup Backoff Timeout	The number of seconds that the system should wait between attempts to initialize the connection pool.

---

## Deleting Adapter Connections

---

If you no longer want to use a particular EntireX Adapter connection, you can delete it by following the instructions in this section. You delete adapter connections using the IS Administration Console. If you delete an EntireX Adapter connection, the adapter services that are defined to use the connection will no longer work. You can change the connection an adapter service uses. Therefore, if you delete an EntireX Adapter connection, you can assign a different connection to an adapter service and reuse the service.

### ▶ To delete a connection

- 1 In the **Adapters** menu in the IS Administration Console navigation area, click **EntireX Adapter**.
- 2 Make sure that the connection is disabled before deleting. To disable the connection, click **Yes** in the Enabled column and click **OK** to confirm. The Enabled column now shows "No" (Disabled) for the connection.
- 3 On the Connections screen, click the **Delete** icon for the connection you want to delete.

As a result, the Integration Server deletes the adapter connection.

---

## Enabling Adapter Connections

---

An EntireX Adapter connection must be enabled before you can configure any adapter service using the connection, or before an adapter service can use the connection at runtime. You enable adapter connections using the IS Administration Console.



**Note:** When you reload a package that contains enabled connections, the connections will automatically be enabled when the package reloads. If the package contains connections that are disabled, they will remain disabled when the package reloads.

### ▶ To enable a connection

- 1 In the **Adapters** menu in the IS Administration Console navigation area, click **EntireX Adapter**.

- 2 On the **Connections** screen, click **No** in the **Enabled** column for the connection you want to enable.

As a result, the IS Administration Console enables the adapter connection and displays a tick and "Yes" in the **Enabled** column.



**Note:** The EntireX broker configured in the Connections does not need to be running to enable a connection. Only the parameters are checked for correctness while enabling a connection.

## Disabling Adapter Connections

---

EntireX Adapter connections must be disabled before you can edit or delete them. You disable adapter connections using the IS Administration Console.

### ▶ To disable a connection

- 1 In the **Adapters** menu in the IS Administration Console navigation area, click **EntireX Adapter**.
- 2 On the **Connections** screen, click **Yes** in the **Enabled** column for the connection you want to disable.

As a result, the adapter connection becomes disabled and you see a "No" in the **Enabled** column.



# 5 EntireX Adapter Services

---

- Before Configuring or Managing Adapter Services ..... 32
- Configuring Adapter Services ..... 33
- Using Adapter Services ..... 33
- Viewing Adapter Services ..... 35
- Deleting Adapter Services ..... 35
- Runtime Connection Allocation for Adapter Services ..... 36
- Configure the Formatting of Decimal and Alphanumeric Parameters ..... 36
- Configuring Null Value Suppression ..... 38

This chapter describes how to configure and manage EntireX Adapter services. EntireX Adapter services allow clients to interact with EntireX RPC servers, Natural RPC servers, ACI servers, ApplinX, IMS Connect, and CICS ECI using a configured adapter connection. EntireX Adapter services are available for synchronous and asynchronous RPC calls (RPC and reliable RPC).

## Before Configuring or Managing Adapter Services

---

### ▶ To prepare configuration and management of EntireX Adapter services

- 1 Start your Integration Server and the IS Administration Console, if they are not already running.
- 2 Make sure you have webMethods administrator privileges so that you can access the EntireX Adapter's administrative screens. See the *Administering webMethods Integration Server* for information on setting user privileges.
- 3 Using the IS Administration Console, make sure the WmEntireX package is enabled. See [Enabling and Disabling Packages](#) for instructions.
- 4 Start the Designer if it is not already running.
- 5 Make sure you are viewing the Designer in the **Service Development** perspective, as described in *Switching Perspectives* in the Designer help.
- 6 Using the Designer, create a user-defined package to contain the service, if you have not already done so. Add a dependency on WmEntireX package (version \*.\*.) to your user-defined package. When you configure adapter services, you should always define them in user-defined packages rather than in the WmEntireX package. For more information on managing packages for the adapter, see [Package Management](#).
- 7 Generate the adapter connection with the EntireX Workbench.

Or:

Using the IS Administration Console, configure an adapter connection to use with the adapter service. See [Configuring Adapter Connections](#) for instructions.

## Configuring Adapter Services

---

The EntireX Adapter service enables you to send RPC calls to an EntireX RPC server or Natural RPC server. You configure EntireX Adapter services using a specific adapter connection. After you follow the steps in this section to configure the adapter service, you can invoke it from a flow or Java service. To use EntireX Adapter services, you provide values for the service's input signature in the pipeline. For more information on using EntireX Adapter services, see [Using Adapter Services](#).

### ▶ To create EntireX Adapter services

- 1 In the EntireX Workbench, select the Software AG IDL file to use.
- 2 In the context menu, choose **Generate webMethods IS Connection from Software AG IDL...**

## Using Adapter Services

---

### ▶ To enable the EntireX Adapter service to send an RPC call to an EntireX RPC server

- Provide values for the parameters in the service's input signature when configuring the adapter service within a flow service in the Designer. You can either map in values from the pipeline, or you can set constant values using the **Pipeline View**.

This has the following effect on the input and output signature:

- The input signature of an adapter service wraps all input parameters of the EntireX subprogram in the `inRec`.

A parameter `throwException` is added to the signature. If this optional parameter is set to "true", errors are returned as exceptions and not by means of parameters in the output signature. A parameter `$connectionname` is added to the signature. If this optional parameter

A parameter `throwException` is added to the signature. If this optional parameter is set to "true", errors are returned as exceptions and not by means of parameters in the output signature.

A parameter `$connectionname` is added to the signature. If this optional parameter, is set to a connection name, it overrides the default connection name of the service.

Depending on the connection type, adapter services have optional parameters that can be used to overwrite the corresponding values of the connection. These optional parameters are:

- **CICS ECI Connection**
  - RACF user ID
  - RACF password/PassTicket
  - CICS Mirror Transaction ID
- **EntireX Direct RPC Connection**
  - RPC library name
  - RPC user
  - RPC password
  - Server address
- **EntireX RPC Connection / EntireX Reliable RPC Connection**
  - Logon user
  - Logon password
  - RPC library name
  - RPC user
  - RPC password
  - Server address
- **IMS Connect Connection**
  - Logical terminal ID
  - RACF user ID
  - RACF password/PassTicket
  - RACF group name
  - RACF application name
  - IMS datastore ID
  - Maximum segment length
- **EntireX ACI Connection**
  - Logon user
  - Logon password

See [EntireX Adapter Connections](#) for details on the parameters.

- The output signature of an adapter service wraps all output parameter of the EntireX sub-program in the `outRec`. Three parameters `errorFlag`, `errorMessage` (optional), and `errorCode` are added to the signature. If `errorFlag` is `true`, `errorMessage` contains the error message. `errorCode` contains "00000000" for a successful call, otherwise the EntireX message class (4 digits) and message code (4 digits).

---

## Viewing Adapter Services

---

Use the Designer to view adapter services. Make sure you are viewing the Designer in the **Service Development** perspective, as described in *Switching Perspectives* in the Designer online help.

▶ **To view a service**

- 1 In the Designer **Package Navigator** view, expand the package and folder that contain the service you want to view.
- 2 Select the service you want to view. The Designer displays the service in the **Service Editor**.

As a result, the Adapter Service Editor for the EntireX Adapter service appears.



**Notes:**

1. You can select the **Adapter Settings** tab at any time to confirm adapter service properties such as the **Adapter Name**, **Adapter Connection Name**, and **Adapter Service Template**, as necessary.
2. On the **RPC Call** tab, the EntireX Subprogram Name field holds the name of the IDL program called by this service. The tables **Input Parameter** and **Output Parameter** display names, the IDL types, and the parameter types in the pipeline.
3. The **Input/Output** tab shows the service's input and output signatures. To use the EntireX Adapter service, you provide values for the signature input within the service pipeline in the Designer. See [Using Adapter Services](#) for instructions on using the EntireX Adapter service.
4. For information on configuring the **Input/Output** and **Adapter Settings** tabs, see *webMethods Service Development Help*. These tabs apply to all services that you configure using the Designer. The information on **Audit** and **Permissions** appears in the **Properties** panel. For the results, see the **Results** panel.

---

## Deleting Adapter Services

---

Use the Designer to delete adapter services. Make sure you are viewing the Designer in the **Service Development** perspective, as described in *Switching Perspectives* in the Designer online help.

▶ **To delete a service**

- 1 In the Designer **Package Navigator** view, expand the package and folder that contain the service you want to delete.

- 2 Right-click the service and then click **Delete**.

## Runtime Connection Allocation for Adapter Services

---

Adapter services of the EntireX Adapter are enabled for dynamically selecting a connection node. The connection name may be specified on the pipeline in the `$connectionName` field. This field has to be part of the services input signature. If `$connectionName` is not specified, the default connection name is used, usually the connection used to create the service.

See chapter 8 in *webMethods Adapter Development Kit User's Guide*, version 6.5 for more details on connection selection.

Connection selection is applicable to services that are generated with the EntireX Adapter (version 8.0 or higher) and helps to:

- **Switch between development and test environment**
  - Generate the connections and services as usual.
  - Design your services that call the adapter services to set `$connectionName` to one single connection.
  - Then you can switch to a different environment by changing this single connection to a different resource.
- **Reduce the number of connection pools**
  - Generate the connections and services as usual.
  - Then for each IDL library one connection is generated and one connection pool is used at runtime.
  - Design your services that call the adapter services to set `$connectionName` to one single connection.
  - This reduces the connection pools to a single pool associated with this connection.

## Configure the Formatting of Decimal and Alphanumeric Parameters

---

Adapter services have two parameters to configure the formatting of decimal parameters (IDL data types `N`, `NU`, `P` and `PU`, and alphanumeric parameters of fixed length (IDL data types `A`, `K`, and `U`).

To set these options, use the Designer and open the adapter service for the EntireX Adapter. In **RPC Call**, select **Parameters for Decimal Numbers (N/P)** or **Parameters for fixed length Strings (A/K/U)**.

The following tables give an overview of parameters to be configured:

#### ■ Parameters for Decimal Numbers (N/P)

(As an example, we use the value "3.14 " for a parameter defined as N7.2 in the IDL.)

Parameter	Example
Remove leading zeros & keep decimal point (default)	3.14
Remove leading zeros & remove decimal point	314
Keep leading zeros & keep decimal point	0000003.14
Keep leading zeros & remove decimal point	000000314

#### ■ Justify Decimal Numbers (N/P)



**Note:** This parameter is highly deprecated and should be only used for compatibility with webMethods Mainframe.

Parameter	Explanation
not justified (default)	The field formatting is unchanged.
left justified	The numeric field is left justified.
right justified	The numeric field is right justified.

#### ■ Parameters for fixed length Strings (A/K/U)

Parameter	Explanation
Remove whitespace characters (default)	Trim leading and trailing whitespace characters.
Keep whitespace characters	Format the string with the defined number of characters.

#### ■ Justify fixed length Strings (A/K/U)



**Note:** This parameter is highly deprecated and should be only used for compatibility with webMethods Mainframe.

Parameter	Explanation
not justified (default)	The field formatting is unchanged.
left justified	The string field is left justified.
right justified	The string field is right justified.

## Configuring Null Value Suppression

Null value suppression (NVS) allows you to suppress parameters with no specified value. Suppressed parameters will not appear in the result of the adapter service call.

Null value suppression is available for the following IDL data types:

- All string data types
- Groups and structures
- Arrays

To activate NVS in the context of adapter services, you need to modify each adapter service separately using Designer. For each adapter service, select **Null Value Suppression** in **RPC Call**.

To fine tune NVS, the following suppression modes can be selected:

Suppression Mode for Parameters	Explanation
No suppression (default)	No suppression, all parameters are present in the output structure.
Suppress null elements	String parameters with empty strings are suppressed, empty structures and arrays are suppressed.
Suppress null elements and trim array cells at end	Same as above. In addition, all empty array elements at the end of the array will be removed from the array.
Suppress null elements and trim array cells at end containing null elements and zero numbers	Same as above. In addition, numbers of numeric/decimal type (I1, I2, I4, N, P) with the value zero are treated as an empty value.

A string parameter is suppressed if the assigned string is:

- of type variable length (AV/KV/UV) and the string is empty (same for variable length strings with a maximum length).
- of type fixed length (A/K/V) and the parameter **Remove whitespace characters** is enabled, and trimming the leading and the trailing whitespace characters would result in an empty string.

# 6 Listeners and Adapter Notifications

---

- Remarks on Reliable RPC Listener Connections ..... 40
- Before Configuring New Listeners ..... 43
- Configuring New Listeners ..... 43
- Testing Listeners ..... 45
- Viewing Listener Parameters ..... 45
- Before Configuring or Managing Notifications ..... 46
- Configuring Adapter Notifications ..... 47
- Managing EntireX Adapter Notifications ..... 48
- Viewing Notifications ..... 48
- Editing Notifications ..... 49
- Deleting Notifications ..... 49

Listeners are used for inbound connections to the Integration Server. They are needed for RPC Listener connections, Reliable RPC Listener connections, and Direct RPC Listener connections.

Adapter notifications monitor an EntireX RPC service and notify the Integration Server when a message arrives on the EntireX RPC service for Reliable RPC.


**Important:** Use the Integration Server Wrapper of the EntireX Workbench to create RPC Listener connections with listeners and Reliable RPC Listener connections with listeners, notifications, triggers, and document types. This chapter describes steps to manually configure these objects. This is needed for advanced configurations, for example triggers with filters.

## Remarks on Reliable RPC Listener Connections

A generated trigger object needs a trigger service that it can call. The input signature for a trigger service needs to have a document reference to the generated publishable document type. While an Integration Server service normally does not have such an input signature, we have to use a workaround to enable the Integration Server service to retrieve the input data from the publishable document. Therefore you can use the service

`com.softwareag.entirex.wmadapter.Deployment:putDocDataToPipeline`, which retrieves all input data from the incoming document and puts it in the pipeline where the Integration Server service is able to retrieve the data. The following section provides a detailed description on how to use the `putDocDataToPipeline` service.

- Suppose you have a flow service `Service:Flow1` which simply dumps the pipeline to a file:




- The Software AG IDL Extractor for webMethods Integration Server extracts the following IDL:

```

Library 'RelListener' Is

  Program 'Flow1' Is /* Service:Flow1
    Define Data Parameter
      1 message (AV) in
    End-Define
  
```

- Generating a Reliable RPC Listener connection, a listener, a notification, a trigger, and a publishable document results in:



- For the original Service:Flow1, the pipeline looks as follows:


```

- <IDataXMLCoder version="1.0">
  - <record javaclass="com.wm.data.ISMemDataImpl">
    <value name="fileName">Flow1-Pipeline.txt</value>
    - <record name="RelListener:ReliableListenerFlow1PublishDocument" javaclass="com.wm.data.ISMemDataImpl">
      <value name="message">abc1</value>
      + <record name="_env" javaclass="com.wm.data.ISMemDataImpl"></record>
    </record>
  </record>
</IDataXMLCoder>

```

As a result, all parameters of the IDL program are inside the record for the document.

- Now add the invoke node for `com.softwareag.entirex.wmadapter.Deployment:putDocDataToPipeline` to Flow1:



- With the `com.softwareag.entirex.wmadapter.Deployment:putDocDataToPipeline` service the pipeline looks as follows:

```

-<IDataXMLCoder version="1.0">
- <record javaclass="com.wm.data.ISMemDataImpl">
  <value name="fileName">Flow1-Pipeline.txt</value>
  - <record name="RelListener:ReliableListenerFlow1PublishDocument" javaclass="com.wm.data.ISMemDataImpl">
    <value name="message">abc1</value>
    + <record name="_env" javaclass="com.wm.data.ISMemDataImpl"></record>
  </record>
  <value name="message">abc1</value>
  + <record name="_env" javaclass="com.wm.data.ISMemDataImpl"></record>
</record>
</IDataXMLCoder>

```

The parameters of the IDL program (here `message`) are on the top level of the pipeline. Also the `record _env` is on the top level of the pipeline. This enables the service to use the parameters directly.

---

## Before Configuring New Listeners

---

1. Start the Integration Server and the IS Administration Console if they are not already running.
2. Make sure that you have webMethods administrator privileges so that you can access the EntireX Adapter's administrative screens.



**Note:** For information on setting user privileges, see *IS Administration Console's Guide*.

- a. Using the IS Administration Console, make sure that the WmEntireX package is enabled. To verify the status of the WmEntireX package, see [Enabling and Disabling Packages](#).
- b. Using the IS Administration Console, configure a valid connection, for instance by copying a generated connection. For more information on configuring connections, see [EntireX Adapter Connections](#) (main section).
- c. Start the Designer if it is not already running.
- d. Make sure you are viewing the Designer in the **Service Development** perspective, as described in *Switching Perspectives* in the Designer online help.
- e. Using the Designer, create a user-defined package to contain the listener, if you have not already done so. For more information on managing packages, see [Package Management](#).

---

## Configuring New Listeners

---

When you configure listeners of the EntireX Adapter, you specify information that the Integration Server uses to listen for, and get messages on, a specified EntireX broker. The broker is specified in the connection associated with the listener. You configure EntireX Adapter Listeners using the IS Administration Console.

### ▶ To configure a new listener

- 1 In the **Adapters** menu in the IS Administration Console's navigation area, click **EntireX Adapter**.
- 2 In the **EntireX Adapter** menu, click **Listeners**.
- 3 On the **Listeners** screen, click **Configure New Listener**.
- 4 On the **Listener Types** screen, select EntireX Listener.
- 5 On the **Configure Listener Type** screen, in the EntireX Adapter section, use the following fields:

Field	Description
Package	The package in which to create the listener.
Folder Name	The folder in which to create the listener.
Listener Name	The name of the listener.
Connection Name	The connection to associate with the listener. From the list of connections, select an appropriate connection that you created on the <b>Configure Connections Type</b> screen. Use separate connections for the adapter services and the adapter listeners.
Retry Limit	The number of times the adapter tries to reconnect if the adapter fails to connect, or loses connection with the EntireX broker. Default: 5.
Retry Backoff Timeout	The number of seconds that elapse between each of the retries specified in the retry limit. Default: 10.
EntireX Subprogram Names	A list of subprogram names, separated by blanks. This list and the following list of service names is usually generated by the EntireX Workbench.
Service Names	A list of Integration Server services, separated by blanks. Each service corresponds to a subprogram name. For the subprogram the service at the same position in the list is called. The lists must have the same number of names.
Minimum Listener Threads	The number of worker threads for this listener that should be started when the listener is enabled. If set to 0, worker threads are started on demand. Default: 1.
Maximum Listener Threads	The maximum number of listener threads to start. Default: 1.
Entry Handler Service	The name of an Integration Server service which will be called in addition before the listener calls a service listed in <b>Service Names</b> . The specification <code>pub.wmentirex.listener:entryExitHandlerSpecification</code> describes the interface of the handler service.
Exit Handler Service	The name of an Integration Serverservice which will be called in addition after the listener has called a service listed in <b>Service Names</b> . The specification <code>pub.wmentirex.listener:entryExitHandlerSpecification</code> describes the interface of the handler service.
Execute Service with Client Credentials	If enabled, the RPC client has to provide RPC user ID and RPC password. These credentials are then used to execute the Integration Server service. Note that currently the RPC user ID and password are limited to 8 characters. Default: <code>false</code> .
Null Value Suppression	See <a href="#">Configuring Null Value Suppression</a> .

6 Save the listener.

---

## Testing Listeners

---

You can test listeners to ensure that you have configured them correctly.

▶ **To test a listener**

- 1 Configure a listener using the IS Administration Console. For instructions on how to configure a listener, see [Configuring New Listeners](#).
- 2 For Reliable RPC Listener Connections only (asynchronous calls): Configure a listener notification using the Designer. See *webMethods Service Development Help* for more information.
- 3 For Reliable RPC Listener Connections only (asynchronous calls): Enable the listener notification using the IS Administration Console. For instructions on how to enable a listener notification, see [Managing EntireX Adapter Notifications](#).
- 4 Enable the listener using the IS Administration Console.



**Important:** The broker configured in the connection associated with the listener must be running while the listener is enabled.

- 5 Use an RPC client to call the RPC server specified in the connection associated with the listener.

As a result, the listener receives the call, uses the parameters to call the flow service or the Java service, and returns the results to the RPC client.



**Notes:**

1. On error a listener may go into the disabled state.
2. If a listener is disabled, it will not start at next start of Integration Server.

---

## Viewing Listener Parameters

---

You can view a listener's parameters using the IS Administration Console or the Designer. You can also view the notification order of a listener.

▶ **To view a listener's parameters using the IS Administration Console**

- 1 In the **Adapters** menu in the navigation area of the IS Administration Console, click **EntireX Adapter**.

- 2 In the **EntireX Adapter** menu, click **Listeners**.
- 3 On the listeners page, click the **View** icon for the listener that you want to see.

As a result, the View Listener screen displays the parameters for the listener. For descriptions of the listener parameters, see [Configuring New Listeners](#).

- 4 Click **Return to EntireX Adapter Listeners** to return to the main listeners screen.



**Note:** Alternatively, you can use the Designer. See *webMethods Service Development Help* for more information.

## Before Configuring or Managing Notifications

---

### ▶ To prepare to configure or manage EntireX Adapter notifications

- 1 Start your Integration Server and the IS Administration Console, if they are not already running.
- 2 Make sure you have webMethods administrator privileges so that you can access the EntireX Adapter's administrative screens. See *Administering webMethods Integration Server* for information on setting user privileges.
- 3 Using the IS Administration Console, make sure the WmEntireX package is enabled. See [Enabling and Disabling Packages](#) for instructions.
- 4 Using the IS Administration Console, configure an adapter connection to use with the notification. See [Configuring Adapter Connections](#).
- 5 Start the Designer if it is not already running.
- 6 Make sure you are viewing the Designer in the **Service Development** perspective, as described in *Switching Perspectives* in the Designer online help.
- 7 Using the Designer, create a user-defined package to contain the notification, if you have not already done so.



**Important:** When you configure notifications, you should always define them in user-defined packages rather than in the WmEntireX package. For more information on managing packages for the adapter, see [Package Management](#).



**Important:** You must enable a notification before you can use it. See [Managing EntireX Adapter Notifications](#) for instructions.

## Configuring Adapter Notifications

When you configure EntireX Adapter notifications, you specify information that the Integration Server uses to read data from an EntireX broker and call a specified flow service or Java service. For more information on notifications, see [Listeners and Adapter Notifications](#) (separate sections). Be sure to review the section [Before Configuring or Managing Notifications](#) before you configure EntireX Adapter notifications.

Adapter notifications are only used for Reliable RPC Listener Connections.

### ▶ To configure an EntireX Adapter notification

- 1 From the Designer **File** menu, choose **New...**
- 2 Select **Adapter Notification** from the list of elements and click **Next**.
- 3 Select **EntireX Adapter** as the adapter type and click **Next**.
- 4 Select the appropriate **Adapter Connection Name** and click **Next**.
- 5 Select the **Asynchronous Listener Notification** template and click **Next**.
- 6 Select an **Adapter Notification Listener** and click **Next**.
- 7 Type a unique name for the notification and select the appropriate folder. Click **Next**.
- 8 Select a service to be called when an RPC call arrives at the listener. Click **Next**.
- 9 The names of the request and reply documents are displayed. Click **Finish**.

As a result, the editor for the adapter notification appears.



**Note:** You can select the **Adapter Settings** tab at any time to confirm adapter service properties such as the **Adapter Name**, **Adapter Connection Name**, and **Adapter Notification Template**, as necessary.

- 10 Select the **Listener Notification** tab and choose the EntireX Subprogram Name. You may select **Map Data Types to String** to map all IDL parameters to `java.lang.String`. Otherwise, the IDL data types are mapped to Java primitive data types.

As a result, the tables of output parameters and input parameters display the names, the IDL data types and the Java data types in the pipeline.



**Note:** For information on using the **Permissions** tab to assign an access control list (ACL) to an element, see

- 11 From the **File** menu, choose **Save** (or **Save All**).



**Note:** You must schedule and enable the notification using the IS Administration Console before you can use it. See *Managing EntireX Adapter Notifications* for details.

## Managing EntireX Adapter Notifications

---

You must enable an EntireX Adapter notification before you can use it to monitor EntireX brokers for messages. Use the IS Administration Console along with the following procedure to do so.



**Note:** You must have webMethods administrator privileges to access the EntireX Adapter's administrative screens. See the *Administering webMethods Integration Server* for information on setting user privileges.

### ▶ To enable (or disable) an EntireX Adapter notification

- 1 Start the IS Administration Console.
- 2 From the **Adapters** menu in the navigation area of the IS Administration Console, choose **EntireX Adapter**.
- 3 From the navigation area, select **Listener Notifications**.
- 4 In the **Listener Notifications** table, you can enable and disable the notification.



**Important:** You cannot enable a notification if the adapter connection that the notification is using is disabled.

As a result, the name of the package is displayed.

## Viewing Notifications

---

Use the Designer to view a notification. Make sure you are using the Designer in the **Service Development** perspective, as described in *Switching Perspectives* in the Designer online help.

### ▶ To view a notification

- 1 In the Designer **Package Navigator** view, expand the package and folder that contain the notification you want to view.
- 2 Select the notification you want to view.

The Designer displays the notification in the **Adapter Notification Editor**.

## Editing Notifications

---

Use the Designer to edit notifications. Make sure you are using the Designer in the **Service Development** perspective, as described in *Switching Perspectives* in the Designer online help. You can change which connection an adapter notification uses.

### ▶ To edit a notification

- 1 In the Designer **Package Navigator** view, expand the package and folder that contain the notification you want to view.
- 2 Select the notification you want to edit.

The Designer displays the notification in the **Adapter Notification Editor**.

- 3 Modify the values for notification's parameters as needed. For detailed descriptions of the notification's parameters, see the section on configuring a notification.

## Deleting Notifications

---

Use the Designer to delete adapter notifications. Make sure you are viewing the Designer in the **Service Development** perspective, as described in *Switching Perspectives* in the Designer online help.

### ▶ To delete a notification

- 1 In the Designer **Package Navigator** view, expand the package and folder that contain the notification you want to delete.
- 2 Right-click the notification and then click **Delete**.



# 7 Settings and Information

---

▪ Adapter Settings .....	52
▪ Connections Information .....	52
▪ Built-in Services for Connections Information .....	53
▪ Support Information .....	55
▪ Services Information .....	55
▪ License Information .....	56
▪ Application Monitoring .....	56

This chapter describes information and tracing screens in the IS Administration Console.

## Adapter Settings

---

This screen shows the current level of EntireX Tracing. You can change this level with the **Change Settings** link. The trace levels are "0" (no tracing), "1" (trace calls), "2" (trace calls and buffers), "3" (full tracing).

The trace file is written to the standard log directory of the Integration Server or the directory defined in **Change Settings** and has the name *wmentirexYYYYMMDD.log*.

You can change the location (directory) for the trace files with the **Change Settings** link. This has immediate effect.

### Further Setting Options for Tracing:

- The adapter uses the logging facility of the Integration Server. The facility code is "0800" for the EntireX Adapter. The logging level specifies the amount of data logged. These log entries are written to the server log file.

## Connections Information

---

This screen displays the following sections about connections and listeners.

### ■ Broker Information

The status of all brokers used in the connections. A green dot shows that a connection to the broker is successful. As status, the version and the operating system platform is displayed. A red dot shows that a connection to the broker is not possible. As status, the error message is displayed.

### ■ Connections for Services

The status of the external servers such as RPC Server, IMS Connect and CICS ECI used by the connections for adapter services. A green dot shows that connection to the RPC server is successful and the status information from the server is displayed. A red dot shows that a connection to the RPC server or to the Broker is not possible. As status, the error message is displayed. The current number of connection instances is shown in column **Count**.

### ■ Connections for Listeners

For each Listener the corresponding name of the connection, Broker ID, and server address is displayed.

## Built-in Services for Connections Information

The information on connections and listeners shown on the IS Administration Console's page is available with built-in services. The following services are available in the WmEntireX package:

- `pub.wmentirex.connectioninfo:brokerInfo`
- `pub.wmentirex.connectioninfo:brokerList`
- `pub.wmentirex.connectioninfo:listenerList`
- `pub.wmentirex.connectioninfo:serviceInfo`
- `pub.wmentirex.connectioninfo:serviceList`

### **pub.wmentirex.connectioninfo:brokerInfo**

The service retrieves the status of the broker given in the broker ID. Use `pub.wmentirex.connectioninfo:brokerList` before to get the list of broker IDs used in all connections.

#### **Input Parameters**

`brokerID` String     The ID of the broker to be pinged.

`refreshData` String     The number of milliseconds to refresh the data. If `refreshData` is null or not a number, the default of 10 seconds is used.

#### **Output Parameters**

`errorFlag` String     "true" if an error occurred, "false" if the call succeeded.

`message` String     The result of the ping call to the broker.

### **pub.wmentirex.connectioninfo:brokerList**

The service retrieves the list of all broker IDs configured in the connections.

#### **Input Parameters**

`refreshData` String     The number of milliseconds to refresh the data. If `refreshData` is null or not a number, the default of 10 seconds is used.

#### **Output Parameters**

`brokerIDs` String[]     The array of broker IDs.

### **pub.wmentirex.connectioninfo:listenerList**

The service retrieves name, broker ID and server address for each listener.

#### **Input Parameters**

`refreshData` String The number of milliseconds to refresh the data. If `refreshData` is null or not a number, the default of 10 seconds is used.

#### **Output Parameters**

`listeners` IData[] The array of IData objects containing three strings *name*, *brokerID*, *serverAddress* for each listener.

### **pub.wmentirex.connectioninfo:serviceInfo**

The service retrieves the result of the ping call for the connection.

#### **Input Parameters**

`connection` String The name of the connection to ping, e.g. "folder:name".  
`refreshData` String The number of milliseconds to refresh the data. If `refreshData` is null or not a number, the default of 10 seconds is used.

#### **Output Parameters**

`errorFlag` String "true" if an error occurred, "false" if the call succeeded.  
`message` String The result of the ping call to the connection.

### **pub.wmentirex.connectioninfo:serviceList**

The service retrieves the connection names. One of these names can be used as input for `pub.wmentirex.connectioninfo:serviceInfo`.

#### **Input Parameters**

`refreshData` String The number of milliseconds to refresh the data. If `refreshData` is null or not a number, the default of 10 seconds is used.

#### **Output Parameters**

`connections` String[] The array of connection names in the format `folder:connection`.

## Support Information

---

Connections, adapter services and adapter listeners contain metadata which is generated during deployment of connections and services. Use the service `pub.wmentirex.supportinfo:createInfo` to extract this metadata for support purposes and error diagnosis.

### **pub.wmentirex.supportinfo:createInfo**

The service extracts the generated metadata from all connections and adapter services in a package and writes this to a file in the installation folder of the Integration Server.

#### **Input Parameters**

`packageName` String The name of a package. The generated metadata for all connections, adapter services and adapter listeners in this package is written to a file.

#### **Output Parameters**

`result` String File *<filename>* created on host *<hostname>*

## Services Information

---

This screen shows statistics about the adapter services of the EntireX Adapter. Only services that have been executed at least once during the runtime of the Integration Server are shown.

The following information is shown for each service:

- name of the service
- corresponding program name
- number of successful calls
- number of erroneous calls
- average processing time in milliseconds (only successful calls)
- time of last access
- processing time in milliseconds for the last call
- status of last call (detailed error message if the last call failed)



**Note:** All these items except the service name can be reset with the link "Reset Statistics".

## License Information

---

This screen shows information on the license used to enable the usage of Direct RPC, or connections using IMS Connect or CICS ECI connectivity.

- License File Location: *name-of-licence-file*. If the file is not found, the location where the file is expected is shown.
- Valid until: values are a date specification or "Unlimited"
- License for connections to IMS Connect: "Yes" or "No"
- License for connections to CICS ECI: "Yes" or "No"
- License for Direct RPC: "Yes" or "No"
- Error message (only if the license is not granted)



### Notes:

1. The folder `<webMethods installation>/IntegrationServer/config` is the default folder for the license file.
2. You can change the location of the license file (file name with folder) with the **Change Settings** link.
3. The folder `<webMethods installation>/IntegrationServer/packages/WmEntireX` is not a safe folder for the license file, because the Integration Server cleans this folder on update.

## Application Monitoring

---

Application Monitoring is an EntireX feature that enables you to monitor the response times in your distributed applications, and it also enables you to monitor certain error situations. For details, see *Application Monitoring* in the EntireX documentation.

### ▶ To enable application monitoring for Direct RPC, IMS Connect and CICS ECI

- 1 In the administration menu of the EntireX Adapter, choose **Application Monitoring**.
- 2 In the **Configuration** section, enable **Application Monitoring**.
- 3 In the configuration entry **Application Monitoring Data Collector ID**, enter the address of the Application Monitoring Data Collector.

The address has the format *host-name:port-number*, where *host-name* is the host on which the Application Monitoring Data Collector is running and *port-number* is the port number of the Application Monitoring Data Collector. The default port number is 57900.



**Caution:** If you have a Direct RPC scenario and you change the application monitoring configuration, all involved client applications and/or RPC servers have to be restarted (because they are caching information about the Adapter's application monitoring settings).



# 8 Direct RPC

---

- Configuring Direct RPC ..... 60
- Encoding for RPC Clients and Servers (Default and Available Codepages) ..... 61
- Monitoring ..... 61
- Services ..... 62
- Servers ..... 62
- Built-in Services for Direct RPC ..... 62
- Limitations of Direct RPC ..... 64

Direct RPC is a component that enables RPC clients and RPC servers to connect directly to the EntireX Adapter without the EntireX Broker.

## Configuring Direct RPC

To enable Direct RPC, choose **Direct RPC Administration** in the EntireX Adapter's administration menu and follow the wizard. The table below gives an overview of parameters to be specified:

Name	Values	Default	Action	Description
Status	"Stopped", "Running"	"Stopped"	Start or stop.	Current status of the Direct RPC component.
Logging Level	"Fatal", "Error", "Warning", "Info", "Debug", "Trace"	"Fatal"	Change logging level.	Logging level. See <a href="#">Notes</a> .
TCP Port Number	Port number	"1971"	Change port number.	TCP listening port for Direct RPC.
SSL Port Number	Port number	-	Change port number.	SSL (or TLS) listening port for Direct RPC.
Keystore Alias (for SSL)	The alias name of a keystore defined in the Integration Server.	-	Change alias name.	Only needed for SSL. Defined in the IS web admin "Security > Keystore".
Auto Start	Enabled, Disabled	"Disabled"	Enable or disable.	Automatic start of Direct RPC during startup of the Adapter.

### Notes:

- Possible logging levels:

Fatal Fatal errors, Direct RPC cannot work correctly.

Error Severe errors, Direct RPC continues to work correctly.

Warning Errors with low severity.

Info To follow the flow of requests between RPC clients, servers and Direct RPC.

Debug All communication buffers will be written to the log file.

Trace Internal use only (Software AG support).

- *wmentirex.directrpcYYYYMMDD.log* is located in folder *logs* in the Integration Server installation folder. To change the default location, see [Adapter Settings](#).

- It is not recommended to use "Info" , "Debug" or "Trace" in a production.

## Encoding for RPC Clients and Servers (Default and Available Codepages)

The default encoding of an RPC client or server is the same as the default encoding of the platform used. The table below gives an overview on default and available codepages:

Platform	Default Codepage	Available Codepages (single byte only)
Windows/UNIX/Linux	ISO 8859-1	ASCII codepages
IBM mainframe (z/OS, z/VSE)	CP037	EBCDIC codepages
Fujitsu mainframe (BS2000/OSD)	CP273	EBCDIC codepages

To specify the encoding of an RPC client or server, see *webMethods EntireX* documentation.

## Monitoring

The following table gives an overview on monitored objects:

Item	Description
Servers	Number of registered servers.
RPC Requests	Number of RPC requests.
Socket Connections	Number of plain socket connections (TCP) from RPC clients or servers.
Secure Socket Connections	Number of secure socket connections (SSL or TLS) from RPC clients or servers.
Direct Connections	Number of direct connections from Adapter services or Adapter Listeners.
Calls	Number of calls (including calls such as <code>logon</code> ).
Conversations	Number of conversational calls.



### Notes:

1. For each item the following information is provided: Current (number of items currently active), maximum (high watermark) and total (number of activations so far).
2. If Direct RPC connections are enabled, the value of `Direct Connections` can be greater than zero even if Direct RPC is stopped.

## Services

---

The following information is displayed for each service:

Name	The name of the service
Type	"External RPC Server" or "Direct RPC Server".
Instances	Number of registered replicates.
Wait for Server	Number of client requests that are waiting for a free server to be processed. The percentage (number of calls waiting compared to the total number of calls) is helpful in deciding if further server replicates are necessary.
Action	Shutdown (only for external RPC servers).



**Note:** As a prerequisite, at least one server must be registered or listener enabled.

## Servers

---

The following information is displayed for each service:

Service Name	The name of the service
Type	"Listener" or "RPC Server".
Name	Name of the Direct Listener or the external RPC server.
Host	Host where the external RPC Server is running.
Version	Version of the external RPC server.
Action	Shutdown (only for external RPC Servers).



**Note:** Host, Name and Version can only be displayed if the RPC server provides this information.

## Built-in Services for Direct RPC

---

The functionality of Direct RPC as shown on the IS Administration Console's page is available with built-in services in the WmEntireX package. They correspond to the parameters on the IS Administration Console's page. When a service is executed, the signature of the input and output parameters is shown. The following services are available:

- `pub.wmentirex.directrpc.admin:getAutoStart`
- `pub.wmentirex.directrpc.admin:getIbmMainframeDefaultCharset`

- `pub.wmentirex.directrpc.admin:getKeyStoreAlias`
- `pub.wmentirex.directrpc.admin:getLoggingLevel`
- `pub.wmentirex.directrpc.admin:getSSLPortNumber`
- `pub.wmentirex.directrpc.admin:getSiemensMainframeDefaultCharset`
- `pub.wmentirex.directrpc.admin:getStatus`
- `pub.wmentirex.directrpc.admin:getTCPPortNumber`
- `pub.wmentirex.directrpc.admin:getWindowsUnixDefaultCharset`
- `pub.wmentirex.directrpc.admin:setAutoStart`
- `pub.wmentirex.directrpc.admin:setIbmMainframeDefaultCharset`
- `pub.wmentirex.directrpc.admin:setKeyStoreAlias`
- `pub.wmentirex.directrpc.admin:setLoggingLevel`
- `pub.wmentirex.directrpc.admin:setSSLPortNumber`
- `pub.wmentirex.directrpc.admin:setSiemensMainframeDefaultCharset`
- `pub.wmentirex.directrpc.admin:setTCPPortNumber`
- `pub.wmentirex.directrpc.admin:setWindowsUnixDefaultCharset`
- `pub.wmentirex.directrpc.admin:start`
- `pub.wmentirex.directrpc.admin:stop`

In addition, there are 4 services for advanced configuration of the SSL transport:

- `pub.wmentirex.directrpc.admin:getSSLClientAuthentication`
- `pub.wmentirex.directrpc.admin:getTrustStoreAlias`
- `pub.wmentirex.directrpc.admin:setSSLClientAuthentication`
- `pub.wmentirex.directrpc.admin:setTrustStoreAlias`



**Note:** Use the `setSSLClientAuthentication` service to switch on SSL client authentication. Client authentication requires that a truststore alias has been set with `pub.wmentirex.directrpc.admin:setTrustStoreAlias`. The truststore alias is defined in the IS web admin **Security > Keystore**. Note that the names of the keystore alias and the truststore alias must be different.

## Limitations of Direct RPC

---

- **An external RPC client cannot connect to an external RPC server.**  
It is only possible that an adapter service connects to an external RPC server, or an external RPC client connects to an adapter listener.
- Exceptions to the rule above are some components of the EntireX Workbench: the IDL Tester, the IDL Extractor for COBOL, the IDL Extractor for Natural and the Natural Wrapper. This requires the latest version of the EntireX Workbench, and only single-byte encodings can be used.
- Reliable RPC is not supported.
- Command and Information Services (CIS) are not supported. Using this API (directly or through the System Management Hub) can result in errors, or the data returned is incomplete or missing.
- An adapter listener and an external RPC server cannot be registered for the same service.
- Replicates of external RPC servers must use the same encoding.
- EntireX Security is not supported.
- ACI applications are not supported. For Natural RPC clients or servers, Broker ACI is only supported for versions higher than 1. See the documentation on the `ACIVERS` parameter in *Parameter Reference* in the latest *Natural for Mainframe* documentation under <https://empower.softwareag.com/Products/Documentation/default.asp>.

# 9 IDL Extraction from Integration Server

---

- Using the Service `pub.wmentirex.listener.generateIDLfromService` ..... 66
- Integration Server Data Types to IDL Mapping ..... 67

Integration Server services (e.g. flow services) can be called from an RPC client using an adapter listener. For the creation of a listener it is necessary to have a Software AG IDL file which describes the call interface (signature) of the Integration Server service.

This IDL file can be created automatically using the IDL Extractor for Integration Server, a component of the EntireX Workbench which reads a package from the Integration Server and generates a Software AG IDL file from all services which exist in the package. For details how to use the IDL Extractor for Integration Server, see the EntireX documentation.

As an alternative, you can create an IDL file from a specified subset of Integration Server services using a service from the WmEntireX package.

In this chapter we describe this alternative and give an overview of the data type mapping which is relevant for both approaches.

## Using the Service `pub.wmentirex.listener:generateIDLfromService`

---

This service generates an IDL file for a given list of Integration Server services. For each service, a program in the IDL file is created. If the IDL file already exists, it is extended with the newly created program definitions. Duplicate definitions for the same program are possible. In this case, the IDL file has to be corrected manually. Note that this service creates/updates only the IDL file. Creating or updating a listener with the definitions of the IDL file has to be done with webMethods Integration Server Wrapper of the EntireX Workbench. The following parameters are relevant:

### Input Parameters

- `serviceName` *String* The full name of the Integration Server service (e.g. `folder1.folder2:service`). Multiple services can be specified using a semicolon (;) as delimiter.
- `fileName` *String* The name of the IDL file. If a relative file name is specified, the base directory is equal to the directory of the Integration Server instance. An absolute file name such as `/workspace/myproject/idl.idl` can also be specified.
- `libraryName` *String* The library name to be used in the IDL file. If the IDL file already exists, this parameter is ignored.
- `stringType` *String* The IDL data type which is used for string data types. Possible values are AV, AVn, or An. This parameter is optional, default is AV.
- `language` *String* The target language for the RPC clients. Possible values are COBOL, Natural, PL/I, or Other.

### Output Parameters

- `result` *String* Either a success message if the generation was successful (which includes the full pathname of the IDL file) or an error message.

## Integration Server Data Types to IDL Mapping

The signature of an Integration Server service specifies the data types for the parameters of the service. There are three data types: `String`, `Record` and `Object`. Parameters of type `String` are mapped to an IDL alphanumeric data type, parameters of type `Record` to IDL groups. Parameters of type `Object` cannot be mapped to an IDL data type and thus result in an error. If such an error occurs, the IDL program which contains the invalid data type mapping is written to the IDL file, however, all lines are comments.

Starting with version 9.7, a parameter of an EntireX Adapter service of type `Object` is mapped to an IDL binary data type. Depending on the target language, it is either mapped to `BV` (for `Natural` and `Other`) or to `BV256` (for `COBOL` and `PL/I`).

All parameters of type `String` are mapped to an IDL alphanumeric data type, available as variable (`AV`, `AVn`) or fixed (`An`) length. Which alphanumeric type is used is specified in the wizard page of the IDL Extractor for Integration Server or as a parameter of the generation service.

Parameters of type `String` may have an associated context type which is specified in the constraints of the parameter's properties. This content type influences the data type mapping. The content type was already considered in previous versions of the EntireX Adapter (version 9.6 or lower). However, its usage was not documented and the mapping was not yet complete. The handling of the content type has been reworked with version 9.7. The following table shows both the new and the old mapping. The new mapping is different from the old one. If you want to use the old mapping with version 9.7 or higher, you have to set the extended setting `watt.com.softwareag.entirex.wmadapter.extractor.contenttype.handling.pre97=true` (in the Integration Server administration page under **Settings > Extended**).

Integration Server Content Type	IDL Data Type - Adapter version 9.7 or higher	IDL Data Type - Adapter version 9.6 or lower
boolean	L	L
decimal	Nx, Nx.y or String <sup>1</sup>	N10.2
float	F4	F4
double	F8	F8
Date	String <sup>2</sup>	D
dateTime	String <sup>2</sup>	T
base64Binary	String <sup>2</sup>	BV
byte	I1	I1
unsignedByte	NU3	I1
short	I2	I2
unsignedShort	NU5	I2
int	I4	I4

Integration Server Content Type	IDL Data Type - Adapter version 9.7 or higher	IDL Data Type - Adapter version 9.6 or lower
unsignedInt	NU10	I4
long	N19	String <sup>2</sup>
unsignedLong	NU20	String <sup>2</sup>
integer	N29	String <sup>2</sup>
positiveInteger	NU29	String <sup>2</sup>
nonPositiveInteger	N29	String <sup>2</sup>
negativeInteger	N29	String <sup>2</sup>
nonNegativeInteger	NU29	String <sup>2</sup>
string	String <sup>3</sup>	String <sup>2</sup>
all others	String <sup>2</sup>	String <sup>2</sup>



#### Notes:

1. If the content type specifies a total number of digits and a number of fraction digits, then  $N_{x.y}$  is used. If only a total number of digits is specified, then  $N_x$  is used. If no total number of digits is specified, or the total number exceeds the maximum allowed value, or the number of fraction digits exceeds the maximum allowed value, then a string according to 2) is used. The maximum allowed value for the total number of digits is 29, for COBOL it is 31. The maximum allowed value for the number of fraction digits is 7, for COBOL it is 31 and for Natural it is 29.
2. Depending on what is specified in the wizard page of the IDL Extractor for Integration Server or as a parameter of the generation service, the IDL data type  $AV$ ,  $AV_n$  or  $A_n$  is used.
3. If the content type specifies a length  $len$ , then  $A_{len}$  is used. If the content type specifies a maximum length  $max$ , then  $AV_{max}$  or  $A_{max}$  is used, see 2) for the choice between  $A$  versus  $AV$ . If neither length nor maximum length is specified, the choice is the same as in 2).

# 10 Security Support

---

- Security Support for Adapter Services ..... 70
- Security Support for Adapter Listeners ..... 71
- Support for SSL/TLS ..... 72

This chapter covers the following topics:

## Security Support for Adapter Services

---

The EntireX Adapter uses adapter services to send synchronous or asynchronous requests to various backend systems. Access to these systems can be secured in the following ways:


- **Provide security credentials in the adapter connection for security-protected backend systems**  
If access to a backend system is security protected, security credentials (user ID and password) have to be provided in the corresponding adapter connection. This can be done when the connection is configured or edited, see [EntireX Adapter Connections](#). This security support is optional and not available for all connection types, see the overview of available connection parameters in [Editing Adapter Connections](#).

The credentials can also be provided dynamically when calling the adapter service, see [Using Adapter Services](#).

- **Set access control permissions for the adapter service**  
Using the Designer you can set access control permissions to restrict the right to execute an adapter service to a particular user group of the Integration Server:

- ▶ **To set access control permissions using the Designer**

- 1 Choose **Service Development > Package Navigator > Permissions**.



- 2 Set **Enforce Execute ACL** to **When top-level service only** to select the group which is specified on the top-level service. This way, access control is already checked when executing the top-level service.

Or:

Set **Enforce Execute ACL** to **Always** and select a user group in **Execute ACL**.

## Security Support for Adapter Listeners

Adapter listeners receive synchronous or asynchronous requests from external RPC clients. If the RPC request is sent to the EntireX Adapter using an EntireX Broker which is configured to use security then the credentials of the RPC clients are checked to see if the client is permitted to call the adapter listener.

By enabling the listener property **Execute Service with Client Credentials**, an adapter listener can be configured to use the credentials (user ID and password) provided by the RPC client to execute the Integration Server service:

Listener Properties	
EntireX Subprogram Names	SQUARE
Service Names	Default:squareFlow
Minimum Listener Threads	
Maximum Listener Threads	
Entry Handler Service	
Exit Handler Service	
Execute Service with Client Credentials	<input checked="" type="checkbox"/>

Then the RPC client has to provide credentials (RPC user ID and RPC password) which are used to execute the Integration Server service. Note that currently the RPC user ID and password are limited to 8 characters.

## Support for SSL/TLS

Communication between the Adapter and the backend systems is done using TCP/IP or, for secure communication, SSL/TLS.

The configuration of SSL depends on the connection type:

Connection type	Description
Connection types using the EntireX Broker	Use the URL-style syntax by which Broker IDs are defined to select SSL as transport method and to define the SSL parameters. For example: <code>ssl://host:1958?definition_of_sslparameters</code> . The syntax for defining SSL parameters is described in the notes below.
IMS Connect and CICS ECI	Specify the SSL port in the <b>Port</b> property and the SSL parameters in the <b>SSL Parameters</b> property as described in <a href="#">Editing a Connection</a> . The syntax for defining SSL parameters is described in the notes below.
Direct RPC	Specify the SSL port and SSL parameters in the configuration wizard for <a href="#">Direct RPC</a> .



**Notes:**

1. SSL parameters are defined in URL style as name value pairs separated by an ampersand ('&').
2. You always have to specify `trust_store=file`, where `file` is the path name of a Java keystore file which contains the list of trusted certificate authorities. Specify `verify_server=no`, if you do not want to check that the certificate of the SSL server is issued for the specified hostname. Example: `ssl://host:1958?trust_store=/temp/ExxCACert.jks&verify_server=no`
3. If the SSL server requests a client certificate, specify `key_store=file` and `key_passwd=pwd`. Again, `file` is the path name of a Java keystore file which contains the private key and `pwd` is the password which is needed to access the private key entry in the keystore. Example: `ssl://host:1958?trust_store=/temp/ExxCACert.jks&key_store=/temp/ExxJavaAppCert.jks&key_passwd=ExxJavaAppCert`

# 11 Message Class 0800 - webMethods EntireX Adapter

---

Messages are logged with message class 0800. In the Administrator, section **Settings > Logging** you find the logging settings in the tree for Adapters. See the *webMethods Integration Server Administrator's Guide* for changing the logging settings.

The messages have the format:

0800`nnnn`

where 0800 is the message class, and

`nnnn` is the message number in the range 0000 - 9999

**08000211**      **<error detail>**

**Explanation**      An error occurred during the execution of an adapter service. The error message contains a detailed description of the error.

**Action**      Use error detail to fix.

**08000212**      **WmEntireX: exception during register: <exception detail>**

**Explanation**      An error occurred during REGISTER call. This can happen when an adapter listener starts.

**Action**      Use exception detail to fix. This is typically a configuration issue.

<b>08000213</b>	<b>WmEntireX: exception during receive: &lt;exception detail&gt;</b>
<b>Explanation</b>	An error occurred during RECEIVE call in an adapter listener.
<b>Action</b>	Use exception detail to fix.
<b>08000215</b>	<b>WmEntireX: connection: unknown resourceDomainName: &lt;name&gt;</b>
<b>Explanation</b>	An internal error occurred.
<b>Action</b>	Contact Software AG support.
<b>08000219</b>	<b>WmEntireX: connection.receive: unknown server command &lt;actual command&gt;</b>
<b>Explanation</b>	<actual command> was sent to the adapter listener. This is unknown and cannot be handled.
<b>Action</b>	Change command. The only known command is PING.
<b>08000220</b>	<b>WmEntireX: connection.receive: conversational call &lt;actual packet type&gt; rejected</b>
<b>Explanation</b>	The adapter listener does not support conversational RPC.
<b>Action</b>	Use non-conversational calls.
<b>08000221</b>	<b>WmEntireX: connection.receive: illegal packet type &lt;actual packet type&gt;</b>
<b>Explanation</b>	The adapter listener received an illegal packet type.
<b>Action</b>	Change your RPC client to send valid packet types.
<b>08000228</b>	<b>WmEntireX: exception during resource domain lookup: &lt;exception detail&gt;</b>
<b>Explanation</b>	An internal error occurred.
<b>Action</b>	Contact Software AG support.
<b>08000229</b>	<b>WmEntireX: unsupported RPC protocol version: &lt;actual protocol version&gt;</b>
<b>Explanation</b>	The RPC client is sending an old protocol version that is not supported by the adapter listener.
<b>Action</b>	Update your RPC client.
<b>08000231</b>	<b>WmEntireX: Asynchronous Listener Notification can only be used with a Reliable RPC Listener Connection</b>
<b>Explanation</b>	An asynchronous adapter listener notification cannot be used with an RPC Listener connection which is not reliable. This error can only occur if an adapter notification is created manually.
<b>Action</b>	Use a Reliable RPC Listener connection for the adapter notification.

<b>08000234</b>	<b>WmEntireX: connection.receive: illegal call for Reliable RPC rejected</b>
<b>Explanation</b>	A reliable RPC listener received a non-reliable call from an RPC client.
<b>Action</b>	Configure the RPC client to use Reliable RPC.
<b>08000236</b>	<b>WmEntireX: connection.receive: illegal call for non Reliable RPC rejected</b>
<b>Explanation</b>	An RPC listener received a reliable call from an RPC client.
<b>Action</b>	Configure the RPC client not to use Reliable RPC.
<b>08000250</b>	<b>WmEntireX: exception in createManagedConnectionObject: &lt;exception detail&gt;</b>
<b>Explanation</b>	An error occurred when creating an adapter connection. The error message contains a detailed description of the error.
<b>Action</b>	Use exception detail to fix.
<b>08000301</b>	<b>WmEntireX: exception during listener startup: &lt;exception detail&gt;</b>
<b>Explanation</b>	An error occurred while starting a listener. The error message contains a detailed description of the error.
<b>Action</b>	Use exception detail to fix.
<b>08000310</b>	<b>WmEntireX: listener.processNotificationResults error: &lt;error details&gt;</b>
<b>Explanation</b>	The Integration Server runtime reported an error during notification.
<b>Action</b>	Use exception details to fix.
<b>08000311</b>	<b>WmEntireX: listener.waitForData (listener for Reliable RPC) error: &lt;exception detail&gt;</b>
<b>Explanation</b>	An error occurred during processing of an RPC request in a reliable listener. The error message contains a detailed description of the error.
<b>Action</b>	Use exception detail to fix.
<b>08000315</b>	<b>WmEntireX: invalid userid password combination</b>
<b>Explanation</b>	A listener is configured to execute the service with client credentials. Either no credentials (user ID and password) were passed in the RPC call or an invalid user ID or password was specified (for example the user does not exist in the Integration Server).
<b>Action</b>	Configure the RPC client to send a valid user ID / password combination.

- 08000333**            **WmEntireX: exception during syncListener.runNotification: <exception details>**  
**Explanation**        The adapter listener trapped into an exception while processing a notification event.  
**Action**                Use exception details to fix.
- 08000342**            **WmEntireX: listener <entry or exit> handler <service name> throws exception <exception detail>**  
**Explanation**        An error occurred in a listener during the call of an entry or exit handler. The error message contains a detailed description of the error.  
**Action**                Use exception detail to fix.
- 08000343**            **WmEntireX: listener <entry or exit> handler <service name> is not a service**  
**Explanation**        Either a service with the given name does not exist or there is an Integration Server object with the same name which is not a service.  
**Action**                Specify a valid entry or exit handler service in the listener configuration.
- 08000362**            **WmEntireX: exception during listener.runAsyncNotification: <exception detail>**  
**Explanation**        An error occurred during the processing of a notification in a reliable listener. The error message contains a detailed description of the error.  
**Action**                Use exception detail to fix.
- 08000500**            **WmEntireX: exception while executing service: <exception detail>**  
**Explanation**        An error occurred during the processing of an adapter service. The error message contains a detailed description of the error.  
**Action**                Use exception detail to fix.
- 08000603**            **Error in transaction handling(<connection id>): <exception detail>**  
**Explanation**        An error occurred in the transactional logic of an adapter service. The error message contains a detailed description of the error.  
**Action**                Use exception detail to fix.

# 12 Message Class 2011 - Connections to IMS Connect

---

This section describes messages that can occur with connections from the webMethods EntireX Adapter to IMS Connect. The messages have the format:

2011*nnnn*

where 2011 is the message class, and

*nnnn* is the message number in the range 0000 - 9999

**20110001**            **Process request and reply: illegal action <number indicating action>**

**Explanation**        During request/reply processing the next action is illegal in the current state.

**Action**                Contact Software AG support.

**20110009**            **<Exception with detailed message >**

**Explanation**        An exception occurred while formatting the message. In most cases, the reason is an inconsistency in metadata.

**Action**                See detailed message or contact Software AG support.

**20110010**            **Compression=off not possible**

**Explanation**        An RPC with compression "0" or "off" is not supported.

**Action**                Change compression to 1 or 2.

<b>20110011</b>	<b>Type of marshalling not allowed. or Unsupported call type &lt;number of call type&gt;</b>
<b>Explanation</b>	There are two reasons for this error code:  <ol style="list-style-type: none"><li>1. For the <code>marshalling</code> property the values "cobol" and "natural" are allowed. Reason: The value of the property may be invalid. Or: The RPC from the client is in the wrong marshalling.</li><li>2. The RPC call type is wrong.</li></ol>
<b>Action</b>	Check configuration and client.
<b>20110012</b>	<b>&lt;Exception with detailed message&gt;</b>
<b>Explanation</b>	This exception occurs in message processing.
<b>Action</b>	See detailed message and contact Software AG support.
<b>20110013</b>	<b>Preparing message failed, see log for details or Message received from server does not fit buffer</b>
<b>Explanation</b>	There are two reasons for this error code.  <ol style="list-style-type: none"><li>1. Marshalling of message failed before sending to IMS Connect.</li><li>2. The received message does not have the expected layout and the values cannot be unmarshalled from it.</li></ol>
<b>Action</b>	Check the following metadata for consistency or contact Software AG support:  <ul style="list-style-type: none"><li>■ IDL file, see <i>Software AG IDL File</i> in the EntireX IDL Editor documentation.</li><li>■ Server mapping file. A server mapping file is an EntireX Workbench file with extension <code>.svm</code> or <code>.cvm</code>.</li><li>■ Adapter connections.</li></ul>
<b>20110014</b>	<b>Transformation error on reply: &lt;Exception with detailed message&gt;</b>
<b>Explanation</b>	The metadata is inconsistent or this data type is not supported.
<b>Action</b>	See detailed message or contact Software AG support.

<b>20110015</b>	<b>Transformation error on request: &lt;Exception with detailed message&gt;</b>
<b>Explanation</b>	This data type is not supported.
<b>Action</b>	See detailed message or contact Software AG support.
<b>20110022</b>	<b>Unsupported command &lt;command&gt;.</b> <b>or</b> <b>Exception: &lt;Exception with detailed message&gt;</b>
<b>Explanation</b>	There are two reasons for this error code.  <ol style="list-style-type: none"> <li>1. An unknown internal command is used.</li> <li>2. An exception occurred during action processing. The log files contain a stack trace.</li> </ol>
<b>Action</b>	See detailed message and log files or contact Software AG support.
<b>20110023</b>	<b>Preparing message failed, see log for details</b>
<b>Explanation</b>	Marshalling of message failed before sending to IMS Connect.
<b>Action</b>	Check metadata (IDL, SVM, adapter connections) for consistency or contact Software AG support. Details can be found in <code>wmentirex.log</code> with trace level 2.
<b>20110301</b>	<b>Receive only not supported</b>
<b>Explanation</b>	This type of call is not supported.
<b>Action</b>	Modify your client.
<b>20110302</b>	<b>Send only not supported</b>
<b>Explanation</b>	This type of call is not supported.
<b>Action</b>	Modify your client.
<b>20110303</b>	<b>&lt;detailed error message from IMS Connect&gt;</b>
<b>Explanation</b>	IMS Connect reported an error, or the configuration is wrong.  <p>If IMS Connect returns code 16 and reason code 64, one cause is that the IMS exit is not installed or is not running. The default exit name is HWSSMPL0 (old) or HWSSMPL1 (new). Other configurations may also result in this return code and reason code.</p> <p>If the IMS Connect connection in the EntireX Adapter uses a port which is not related to IMS but to some other application, a call may result in the following message:  Unable to invoke adapter service &lt;service name&gt; [ADA.800.500]  WmEntireX: exception while executing service: 2011 0303  java.io.EOFException</p>

If the IMS Connect RPC server uses a port which is not related to IMS but to some other application, a call may result in the following message: exception while executing service: 2011 0303 java.io.EOFException

**Action** Use the error code from IMS Connect to correct this or correct the configuration.

**20110304** **Conversations not supported**

**Explanation** IMS Connect does not support conversational RPC calls.

**Action** Use non-conversational calls.

# 13

## Message Class 2012 - Connections to CICS ECI

---

This message class contains messages that can occur with connections to CICS ECI. The messages have the format:

2012*nnnn*

where 2012 is the message class, and

*nnnn* is the message number in the range 0000 - 9999

**20120001**            **Process request and reply: illegal action <number indicating action>.**

**Explanation**        During request/reply processing the next action is illegal in the current state.

**Action**                Contact Software AG support.

**20120009**            **<Exception with detailed message >**

**Explanation**        An exception occurred while formatting the message. In most cases, the reason is an inconsistency in metadata.

**Action**                See detailed message or contact Software AG support.

**20120010**            **Compression=off not possible.**

**Explanation**        An RPC with compression "0" ("off") is not supported.

**Action**                Change compression to 1 or 2.

<b>20120011</b>	<b>Type of marshalling not allowed. or Unsupported call type &lt;number of call type&gt;</b>
<b>Explanation</b>	There are two reasons for this error code:  <ol style="list-style-type: none"><li>1. For the <code>marshalling</code> property the values "cobol" and "natural" are allowed. Reason: The value of the property may be invalid. Or: The RPC from the client is in the wrong marshalling.</li><li>2. The RPC call type is wrong.</li></ol>
<b>Action</b>	Check configuration and client.
<b>20120012</b>	<b>&lt;Exception with detailed message&gt;</b>
<b>Explanation</b>	This exception occurs in message processing.
<b>Action</b>	See detailed message and contact Software AG support.
<b>20120013</b>	<b>Preparing message failed, see log for details. or Message received from server does not fit buffer</b>
<b>Explanation</b>	There are two reasons for this error code.  <ol style="list-style-type: none"><li>1. Marshalling of message failed before sending to CICS ECI.</li><li>2. The received message does not have the expected layout and the values cannot be unmarshalled from it.</li></ol>
<b>Action</b>	Check the following metadata for consistency or contact Software AG support: <ul style="list-style-type: none"><li>■ IDL file, see <i>Software AG IDL File</i> in the EntireX IDL Editor documentation.</li><li>■ Server mapping file. A server mapping file is an EntireX Workbench file with extension <code>.svm</code> or <code>.cvm</code>.</li><li>■ Adapter connections.</li></ul>
<b>20120014</b>	<b>Transformation error on reply: &lt;Exception with detailed message&gt;</b>
<b>Explanation</b>	The metadata is inconsistent or this data type is not supported.
<b>Action</b>	See detailed message or contact Software AG support.

<b>20120015</b>	<b>Transformation error on request: &lt;Exception with detailed message&gt;.</b>
<b>Explanation</b>	This data type is not supported.
<b>Action</b>	See detailed message or Contact Software AG support.
<b>20120022</b>	<b>Unsupported command &lt;command&gt;.</b> <b>or</b> <b>Exception: &lt;Exception with detailed message&gt;</b>
<b>Explanation</b>	There are two reasons for this error code. First, an unknown internal command is used. Second, an exception occurred during action processing. The log files contain a stack trace.
<b>Action</b>	See detailed message and log files or contact Software AG support.
<b>20120023</b>	<b>Preparing message failed, see log for details</b>
<b>Explanation</b>	Marshalling of message failed before sending to CICS ECI.
<b>Action</b>	Check metadata (IDL, SVM, adapter connections) for consistency or contact Software AG support. Details can be found in <code>wmentirex.log</code> with trace level 2.
<b>20120351</b>	<b>Receive only not supported</b>
<b>Explanation</b>	This type of call is not supported.
<b>Action</b>	Modify your client.
<b>20120352</b>	<b>Send only not supported</b>
<b>Explanation</b>	This type of call is not supported.
<b>Action</b>	Modify your client.
<b>20120353</b>	<b>&lt;detailed error message from CICS ECI&gt;</b>
<b>Explanation</b>	CICS ECI reported an error, or the configuration is wrong. This error number is also issued if the connection to CICS ECI is lost.
<b>Action</b>	Use the error code from CICS to correct this. The CICS error codes are described in the documentation of CICS from IBM.  Possible error codes are (others may occur):  ■ <b>AEIO: DUPKEY</b> possible reasons: Callee not found - the called program does not exist or is not started.

- **ASRA**  
possible reasons: Division by zero.

- **4038: Index overwrite**

- **TCII (CICS Abend)**

A call to CICS ECI can result in an EOF exception because of

- Connection to the wrong port. There is some service listening on the port, but not CICS ECI.
- CICS ECI is not correctly configured.

**20120354**

**Conversations not supported**

**Explanation**

CICS ECI does not support conversational RPC calls.

**Action**

Use non-conversational calls.

# 14 Message Class 2023 - Connections to ApplinX

---

This message class contains messages that can occur with ApplinX Connections in the EntireX Adapter. The messages have the format:

2023*nnnn*

where 2023 is the message class, and

*nnnn* is the message number in the range 0000 - 9999

**20230001**            **Process request and reply: illegal action <number indicating action>.**

**Explanation**        During request/reply processing the next action is illegal in the current state.

**Action**                Contact Software AG support.

**20230009**            **<Exception with detailed message >**

**Explanation**        An exception occurred while formatting the message. In most cases, the reason is an inconsistency in metadata.

**Action**                See detailed message or contact Software AG support.

**20230010**            **Compression=off not possible**

**Explanation**        An RPC with compression "0" ("off") is not supported.

**Action**                Change compression to 1 or 2.

<b>20230011</b>	<b>Type of marshalling not allowed</b>
<b>Explanation</b>	For the <code>marshalling</code> property the values <code>cobol</code> and <code>natural</code> are allowed. First cause: The value of the property may be invalid. Second cause: The RPC from the client is in the wrong marshalling.
<b>Action</b>	Check configuration and client.
<b>20230012</b>	<b>&lt;Exception with detailed message&gt;</b>
<b>Explanation</b>	This exception occurs in message processing.
<b>Action</b>	See detailed message and contact Software AG support.
<b>20230013</b>	<b>Preparing message failed, see log for details or Message received from server does not fit buffer</b>
<b>Explanation</b>	There are two possible reasons for this error code:  <ol style="list-style-type: none"><li>1. Marshalling of message failed before sending to CICS ECI.</li><li>2. The received message does not have the expected layout and the values cannot be unmarshalled from it.</li></ol>
<b>Action</b>	Check the following metadata for consistency or contact Software AG support:  <ul style="list-style-type: none"><li>■ IDL file, see <i>Software AG IDL File</i> in the EntireX IDL Editor documentation.</li><li>■ Server mapping file. A server mapping file is an EntireX Workbench file with extension <code>.svm</code> or <code>.cvm</code>.</li><li>■ Adapter connections.</li></ul>
<b>20230015</b>	<b>Transformation error on request: &lt;Exception with detailed message&gt;.</b>
<b>Explanation</b>	This data type is not supported.
<b>Action</b>	See detailed message or contact Software AG support.
<b>20230022</b>	<b>Unsupported command &lt;command&gt;. or Exception: &lt;Exception with detailed message&gt;</b>
<b>Explanation</b>	There are two possible reasons for this error code:  <ol style="list-style-type: none"><li>1. An unknown internal command is used.</li><li>2. An exception occurred during action processing. The log files contain a stack trace.</li></ol>
<b>Action</b>	See detailed message and log files or contact Software AG support.

# 15

## Message Class 0400 - Direct RPC

---

This message class contains messages that can occur with Direct RPC. The messages have the format:

0400*nnnn*

where 0400 is the message class, and

*nnnn* is the message number in the range 0000 - 9999

<b>04000001</b>	<b>Exception during processing call: &lt;exception text&gt;</b>
<b>Explanation</b>	An unexpected error occurred during processing of a call from an RPC client or server.
<b>Action</b>	Check the exception text for details.
<b>4000002</b>	<b>Transport session not active</b>
<b>Explanation</b>	A call happens on an adapter connection although this connection instance is disabled.
<b>Action</b>	Contact Software AG support.
<b>04000003</b>	<b>Invalid usage of Direct RPC (&lt;class/server/service&gt;)</b>
<b>Explanation</b>	An RPC client sends a request to an RPC server using Direct RPC. This is not supported.
<b>Action</b>	Change your application setup so that <ol style="list-style-type: none"><li>1. an RPC client sends a request to a Direct RPC listener, or</li><li>2. a Direct RPC adapter service sends a request to an RPC server.</li></ol>

<b>04000004</b>	<b>Invalid register: replicate from different transport (&lt;class/server/service&gt;)</b>
<b>Explanation</b>	Both a listener and an RPC server try to register using the same class/server/service name. This is not supported.
<b>Action</b>	Change your application so that only listeners or RPC servers register for the same class/server/service name.
<b>04000005</b>	<b>Send with wait not possible for servers (&lt;class/server/service&gt;)</b>
<b>Explanation</b>	An RPC server issues a synchronous send command, which is not supported.
<b>Action</b>	Check your configuration: for example, an ACI server might be using Direct RPC.
<b>04000006</b>	<b>Send with no wait not possible for clients (&lt;class/server/service&gt;)</b>
<b>Explanation</b>	An RPC client issues an asynchronous send command, which is not supported.
<b>Action</b>	Check your configuration: for example, an ACI client might be using Direct RPC.
<b>04000007</b>	<b>Receive not possible for clients (&lt;class/server/service&gt;)</b>
<b>Explanation</b>	An RPC client issues a receive command, which is not supported.
<b>Action</b>	Check your configuration: for example, an ACI client might be using Direct RPC.
<b>04000008</b>	<b>Direct RPC not started</b>
<b>Explanation</b>	An adapter service or a listener issues a call using Direct RPC, but the Direct RPC component is not started.
<b>Action</b>	Start the Direct RPC component, or ignore error if stopping of Direct RPC is intended.
<b>04000010</b>	<b>Command Service error: &lt;detailed message&gt;</b>
<b>Explanation</b>	An error occurred while processing a Command Service request.
<b>Action</b>	See error message for details.
<b>04000011</b>	<b>Compression not supported</b>
<b>Explanation</b>	The compression feature is not supported.
<b>Action</b>	Disable compression (use value "NO_COMPRESSION") on the RPC client or RPC server.

<b>04000012</b>	<b>Publish and Subscribe not supported</b>
<b>Explanation</b>	The Publish and Subscribe functionality is not supported.
<b>Action</b>	Change your application.
<b>04000013</b>	<b>Character set for &lt;character set type&gt; not available</b>
<b>Explanation</b>	No character set is available for an RPC call.
<b>Action</b>	Contact Software AG support.
<b>04000014</b>	<b>Encoding LS=&lt;char set name&gt; not supported</b>
<b>Explanation</b>	The specified character set is not available. Only character sets supported by the Java JVM can be used.
<b>Action</b>	Change the configuration of the RPC client or server.
<b>04000015</b>	<b>&lt;error message&gt;</b>
<b>Explanation</b>	An error during character set conversion.
<b>Action</b>	See error message for details.
<b>04000017</b>	<b>Information Service error: &lt;detail message&gt;</b>
<b>Explanation</b>	An error occurred while processing an Information Service request.
<b>Action</b>	See error message for details.



# 16

## Message Class 1018 - EntireX RPC-ACI Bridge

---

Messages have the format:

1018*nnnn*

where 1018 is the message class, and

*nnnn* is the message number in the range 0000 - 9999.

### 10180000

**Explanation** This error can occur if the ACI server sends an invalid message. The ACI server is not able to return an error code. It can only send a valid message or quit the Broker communication.

**Action** Correct the ACI server.

### 10180001

**Process request and reply: illegal action <number indicating action>**

**Explanation** During request/reply processing the next action is illegal in the current state.

**Action** Contact Software AG support.

### 10180002

**<Broker Exception with detailed message>**

**Explanation** An exception with the Broker for ACI occurred during SEND.

**Action** See message class and message code of the Broker exception and follow detailed message.

<b>10180003</b>	<b>&lt;Broker Exception with detailed message&gt;</b>
<b>Explanation</b>	An exception with the Broker for ACI occurred during RECEIVE.
<b>Action</b>	See message class and message code of the Broker exception and follow detailed message.
<b>10180004</b>	<b>&lt;Broker Exception with detailed message&gt;</b>
<b>Explanation</b>	An exception with the Broker for ACI occurred during shutdown and logoff.
<b>Action</b>	See message class and message code of the Broker exception and follow detailed message.
<b>10180009</b>	<b>&lt;Exception with detailed message&gt;</b>
<b>Explanation</b>	An exception occurred while formatting the message. In most cases, the reason is an inconsistency in the metadata.
<b>Action</b>	See detailed message or contact Software AG support.
<b>10180010</b>	<b>Compression=off not possible</b>
<b>Explanation</b>	An RPC with compression 0 is not supported.
<b>Action</b>	Change compression to 1 or 2.
<b>10180011</b>	<b>Type of marshalling not allowed or Unsupported call type &lt;number of call type&gt;</b>
<b>Explanation</b>	There are two reasons for this error code.  1. for the marshalling property the values 'cobol', 'natural', and '' are allowed. Reason: The value of the property may be invalid. or: The RPC from the client is in the wrong marshalling.  2. The RPC call type is wrong.
<b>Action</b>	Check configuration and client.
<b>10180012</b>	<b>&lt;Exception with detailed message&gt;</b>
<b>Explanation</b>	This exception occurs in message processing.
<b>Action</b>	See detailed message and contact Software AG support.

<b>10180013</b>	<p><b>Preparing message failed, see log for details</b>  <b>or:</b>  <b>Message received from server does not fit buffer</b></p>
<b>Explanation</b>	<p>There are two reasons for this error code:</p> <ol style="list-style-type: none"> <li>1. Marshalling of message failed before sending to CICS ECI.</li> <li>2. The received message does not have the expected layout and the values cannot be unmarshalled from it.</li> </ol>
<b>Action</b>	<p>Check the following metadata for consistency or contact Software AG support:</p> <ul style="list-style-type: none"> <li>■ IDL file, see <i>Software AG IDL File</i> in the EntireX IDL Editor documentation.</li> <li>■ Server mapping file. A server mapping file is an EntireX Workbench file with extension .svm or .cvm.</li> <li>■ Adapter connections.</li> </ul>
<b>10180015</b>	<p><b>Transformation error on request: &lt;Exception with detailed message&gt;</b></p>
<b>Explanation</b>	<p>This exception occurs in message processing.</p>
<b>Action</b>	<p>See detailed message or contact Software AG support.</p>
<b>10180022</b>	<p><b>Unsupported command &lt;command&gt;</b>  <b>or</b>  <b>Exception: &lt;Exception with detailed message&gt;</b></p>
<b>Explanation</b>	<p>There are two reasons for this error code:</p> <ol style="list-style-type: none"> <li>1. An unknown internal command is used.</li> <li>2. An exception occurred during action processing.</li> </ol> <p>The log files contain a stack trace.</p>
<b>Action</b>	<p>See detailed message and log files or contact Software AG support.</p>



# 17

## Preparing IBM CICS® for ECI

---

▪ Defining an ECI Service .....	96
▪ Installation Verification .....	96
▪ Error Handling .....	97

This chapter describes how to set up the External Call Interface (ECI) within CICS.

 **Important:** If the terms and concepts in this chapter are unfamiliar to you, please work with the appropriate CICS system programmer. Only authorized personnel should make changes to mainframe computer systems.

## Defining an ECI Service

---

The `DFH$SOT` group contains three TCP/IP services. For our purposes, the pertinent service is ECI. The ECI service has, defined in it, the TCP/IP port number through which the CICS region listens to the ECI. By default, IBM predefines the TCP/IP port number as "1435". If this port is already reserved for another CICS region, you may have to define a different port number in the ECI service. For more information, see your IBM documentation.

You must specify `SOCKETCLOSE(NO)` on the `TCPIPService`. If you need to specify a timeout for a task initiated using ECI over TCP/IP, specify an `RTIMOUT` value on the mirror transaction. Note that the standard mirror, `CPMI`, is defined with profile `DFHCICSA`, which specifies `RTIMOUT(NO)`. This means that long running mirrors will wait indefinitely for data, unless you specify a different `RTIMOUT` for the mirror transaction.

### ▶ To define an ECI service without security

- 1 Use `CEDA ALTER` to supply the `ECI TCPIPService` with a unique TCP/IP port number.
- 2 Use `CEDA ALTER` to set the `ECI Attachsec` to "LOCAL"

### ▶ To define an ECI service with security

- 1 Copy the `ECI TCPIPService` to an `ECIS TCPIPService`.
- 2 Use `CEDA ALTER` to supply the `ECIS TCPIPService` with a unique TCP/IP port number.
- 3 Use `CEDA ALTER` to set the `ECIS Attachsec` to "VERIFY".

## Installation Verification

---

A successful installation should pass the following verification tests:

1. `CEMT INQUIRE TCPIPService(*)` should now display your services with status OPE. A status of CLO might indicate an already used (not unique) TCP/IP port number.
2. `CEMT I TCPIPService(ECI)` to verify `TCPIPService` in CICS.
3. `CEMT I TRA(CIEP)` to verify Transaction CIEP in CICS.

4. CEMT I PROGRAM(DFHI EP) to verify Program DFHI EP in CICS.
5. CEMT I TRAN(CPMI) to verify Transaction CPMI in CICS.
6. CEMT I PROGRAM(DFHMIRS) to verify Program DFHMIRS in CICS.
7. CEMT I TD(CIEO) to verify Program TQ Queue CIEO.
8. Verify that the groups DFHISC DFHDCTG and DFHIPECI are added to the active autoinstall



**Tip:** You can check the mentioned programs and transactions and TD queues by using CEMT VERIFY TCP.

## Error Handling

This section describes the handling of errors in the CICS ECI connection or the CICS ECI RPC server.

Problem	Handling
A CICS program sends abend code in response.	The CICS session is closed and the next call opens a different session.
The TCP/IP connection is lost with a <code>SocketTimeoutException</code> .	The CICS session is closed and the next call opens a different session.
The TCP/IP connection is lost with an <code>EOFException</code> .	<ul style="list-style-type: none"> <li>■ The TCP/IP socket is closed and the next call opens a different session.</li> <li>■ There are no further attempts to send bytes on the TCP/IP connection which received the <code>EOFException</code>.</li> </ul>



# 18

## Preparing for IMS

---

▪ Extracting from COBOL Source .....	100
▪ Extracting from Message Format Service (MFS) .....	100
▪ Troubleshooting .....	100

This chapter describes how to prepare for connections to IMS.

 **Important:** If the terms and concepts in this chapter are unfamiliar to you, please work with the appropriate IMS system programmer. Only authorized personnel should make changes to mainframe computer systems.

## Extracting from COBOL Source

---

Use the IDL Extractor for COBOL. See the *EntireX Workbench* documentation for more information.

## Extracting from Message Format Service (MFS)

---

To extract interface definitions from Message Format Service (MFS) with MID and MOD definitions, use a command line extractor. This extractor is run with the following command line:

```
java -classpath <suite installation ↵
folder>\IntegrationServer\packages\WmEntireX\code\jars\entirex.jar ↵
com.softwareag.entirex.ims.extractor.MFSExtractor <inputfile>
```

The input file has to be an MFS source with MID and MOD definitions. The output is an IDL file with the same name as the input file, except for the suffix ".idl" which is appended. The IDL file can be used to generate connections and adapter services with the webMethods Integration Server Wrapper (see the *EntireX Workbench* documentation).

## Troubleshooting

---

This section describes how to fix errors in the IMS Connect connection or the IMS Connect RPC server.

Problem	Solution
If the IMS Connect connection uses a port which is not related to IMS but to some other application, a call may result in the following message: Unable to invoke adapter service <service name>. [ADA.800.500] WmEntireX: exception while executing service: 2011 0303 java.io.EOFException	Correct the configuration of the port.
If the IMS Connect RPC server uses a port which is not related to IMS but to some other application, a call may result in the following message: exception while executing service: 2011 0303 java.io.EOFException	Correct the configuration of the port.