

webMethods EntireX

EntireX RPC Server for z/OS CICS®

Version 10.1

October 2017

This document applies to webMethods EntireX Version 10.1 and all subsequent releases.

Specifications contained herein are subject to change and these changes will be reported in subsequent release notes or new editions.

Copyright © 1997-2017 Software AG, Darmstadt, Germany and/or Software AG USA, Inc., Reston, VA, USA, and/or its subsidiaries and/or its affiliates and/or their licensors.

The name Software AG and all Software AG product names are either trademarks or registered trademarks of Software AG and/or Software AG USA, Inc. and/or its subsidiaries and/or its affiliates and/or their licensors. Other company and product names mentioned herein may be trademarks of their respective owners.

Detailed information on trademarks and patents owned by Software AG and/or its subsidiaries is located at <http://softwareag.com/licenses>.

Use of this software is subject to adherence to Software AG's licensing conditions and terms. These terms are part of the product documentation, located at <http://softwareag.com/licenses/> and/or in the root installation directory of the licensed product(s).

This software may include portions of third-party products. For third-party copyright notices, license terms, additional rights or restrictions, please refer to "License Texts, Copyright Notices and Disclaimers of Third-Party Products". For certain specific third-party license restrictions, please refer to section E of the Legal Notices available under "License Terms and Conditions for Use of Software AG Products / Copyright and Trademark Notices of Software AG Products". These documents are part of the product documentation, located at <http://softwareag.com/licenses> and/or in the root installation directory of the licensed product(s).

Use, reproduction, transfer, publication or disclosure is prohibited except as specifically provided for in your License Agreement with Software AG.

Document ID: EXX-CICSRPC-101-20191129

Table of Contents

EntireX RPC Server for z/OS CICS®	v
1 About this Documentation	1
Document Conventions	2
Online Information and Support	2
Data Protection	3
2 Introduction to the RPC Server for CICS	5
Worker Models	6
Inbuilt Services	7
User Exit COBUEx02	9
Impersonation	10
Usage of Server Mapping Files	11
Supported Interface Types	12
3 Administering the RPC Server for CICS	13
Customizing the RPC Server	14
Configuring the RPC Server	16
Locating and Calling the Target Server	27
Using SSL/TLS with the RPC Server	28
User Exit COBUEx02	30
Autostart/Stop during CICS Start/Shutdown	35
Multiple RPC Servers in the same CICS	36
4 RPC Online Maintenance Facility	37
Monitoring the RPC Server for CICS	38
Starting the RPC Server for CICS	40
Pinging the RPC Server for CICS	41
Stopping the RPC Server for CICS	41
Modifying Parameters of the RPC Server for CICS	41
Activating Tracing for the RPC Server for CICS	42
Console Commands for the RPC Server for CICS	42
5 Deployment Service	45
Introduction	46
Scope	47
Enabling the Deployment Service	47
Disabling the Deployment Service	48
6 Server-side Mapping Files	49
Server-side Mapping Files in the RPC Server	50
Deploying Server-side Mapping Files to the RPC Server	51
Undeploying Server-side Mapping Files from the RPC Server	52
Change Management of Server-side Mapping Files	53
List Deployed Server-side Mapping Files	53
Check if a Server-side Mapping File Revision has been Deployed	54
Access Control: Secure Server Mapping File Deployment	54
Ensure that Deployed Server-side Mapping Files are not Overwritten	54
Is There a Way to Smoothly Introduce Server-side Mapping Files?	54

7 Scenarios and Programmer Information	55
COBOL Scenarios	56
PL/I Scenarios	57
Aborting RPC Server Customer Code and Returning Error to RPC Client	58
Automatic Syncpoint Handling	63
RPC Server Support of CICS with Large Buffer Interface	63

EntireX RPC Server for z/OS CICS®

The EntireX RPC Server for z/OS CICS® allows standard RPC clients to communicate with RPC servers on the operating system z/OS under CICS. It supports the programming languages COBOL and PL/I.

- For COBOL, it works together with the COBOL Wrapper and IDL Extractor for COBOL.
- For PL/I, it works together with the PL/I Wrapper and IDL Extractor for PL/I.

Supported compilers are listed under *z/OS Prerequisites* in the EntireX Release Notes.

1 About this Documentation

- Document Conventions 2
- Online Information and Support 2
- Data Protection 3

Document Conventions

Convention	Description
Bold	Identifies elements on a screen.
Monospace font	Identifies service names and locations in the format <i>folder.subfolder.service</i> , APIs, Java classes, methods, properties.
<i>Italic</i>	Identifies: Variables for which you must supply values specific to your own situation or environment. New terms the first time they occur in the text. References to other documentation sources.
Monospace font	Identifies: Text you must type in. Messages displayed by the system. Program code.
{ }	Indicates a set of choices from which you must choose one. Type only the information inside the curly braces. Do not type the { } symbols.
	Separates two mutually exclusive choices in a syntax line. Type one of these choices. Do not type the symbol.
[]	Indicates one or more options. Type only the information inside the square brackets. Do not type the [] symbols.
...	Indicates that you can type multiple options of the same type. Type only the information. Do not type the ellipsis (...).

Online Information and Support

Software AG Documentation Website

You can find documentation on the Software AG Documentation website at <http://documentation.softwareag.com>. The site requires credentials for Software AG's Product Support site Empower. If you do not have Empower credentials, you must use the TECHcommunity website.

Software AG Empower Product Support Website

If you do not yet have an account for Empower, send an email to empower@softwareag.com with your name, company, and company email address and request an account.

Once you have an account, you can open Support Incidents online via the eService section of Empower at <https://empower.softwareag.com/>.

You can find product information on the Software AG Empower Product Support website at <https://empower.softwareag.com>.

To submit feature/enhancement requests, get information about product availability, and download products, go to [Products](#).

To get information about fixes and to read early warnings, technical papers, and knowledge base articles, go to the [Knowledge Center](#).

If you have any questions, you can find a local or toll-free number for your country in our Global Support Contact Directory at https://empower.softwareag.com/public_directory.asp and give us a call.

Software AG TECHcommunity

You can find documentation and other technical information on the Software AG TECHcommunity website at <http://techcommunity.softwareag.com>. You can:

- Access product documentation, if you have TECHcommunity credentials. If you do not, you will need to register and specify "Documentation" as an area of interest.
- Access articles, code samples, demos, and tutorials.
- Use the online discussion forums, moderated by Software AG professionals, to ask questions, discuss best practices, and learn how other customers are using Software AG technology.
- Link to external websites that discuss open standards and web technology.

Data Protection


Software AG products provide functionality with respect to processing of personal data according to the EU General Data Protection Regulation (GDPR). Where applicable, appropriate steps are documented in the respective administration documentation.

2 Introduction to the RPC Server for CICS

▪ Worker Models	6
▪ Inbuilt Services	7
▪ User Exit COBUEX02	9
▪ Impersonation	10
▪ Usage of Server Mapping Files	11
▪ Supported Interface Types	12

The EntireX RPC Server for z/OS CICS® allows standard RPC clients to communicate with RPC servers on the operating system z/OS under CICS. It supports the programming languages COBOL and PL/I.

Worker Models



RPC requests are worked off inside the RPC server in worker threads, which are controlled by a main thread. Every RPC request occupies during its processing a worker thread. If you are using RPC conversations, each RPC conversation requires its own thread during the lifetime of the conversation. The RPC Server for CICS provides two worker models:

- **FIXED**
The *fixed* model creates a fixed number of worker threads. The number of worker threads does not increase or decrease during the lifetime of an RPC server instance.
- **DYNAMIC**
The *dynamic* model creates worker threads depending on the incoming load of RPC requests.


For configuration and technical details, see [ERXMAIN macro](#) parameter [ENDW](#) under *Administering the RPC Server for CICS*.

Inbuilt Services

RPC Server for CICS provides the following service for ease-of-use:

Deployment Service

The Deployment Service allows you to deploy server-side mapping files (EntireX Workbench files with extension .svm) interactively using the *Server Mapping Deployment Wizard*. On the RPC server side, the server-side mapping files are stored in a server-side mapping container (VSAM file). See [Server-side Mapping Files in the RPC Server](#) and [Deployment Service](#) for configuration information.




User Exit COBUEX02

The RPC Server for CICS provides a user exit COBUEX02 to influence/control the RPC logic. The exit is called on the events START-WORKER, START-USER, CALL-START and CALL-END. The following tasks can be performed:


- 1 WHICH-VERSION event. Tells the RPC Server for CICS the version to use.
- 3 START-WORKER event. Allows you to set the CICS transaction ID.
- 5 START-USER event. Apply user ID, CICS transaction ID and CICS terminal ID to impersonated user tasks. See *Impersonation*.
- 7 CALL-START event. Inspect, modify or terminate the RPC request (payload) from the RPC client.
- 8 CALL-END event. Inspect or modify the RPC reply (payload) or give an error to the RPC client.

The numbers in the graphic correspond to the event numbers in the user exit.



See also [User Exit COBUEX02](#) under *Administering the RPC Server for CICS*.

Impersonation



The RPC Server for CICS can be configured to execute the RPC request impersonated under the RPC client user ID. For this, worker tasks start additional impersonated user tasks. This can be useful, for example for accounting. Impersonation is controlled by the `ERXMAIN` macro parameter `IMPS`.

- For `IMPS` value `AUTO`, the RPC Server for CICS does not validate RPC passwords, so you have to take care the RPC client is correctly authenticated, either by using a secure EntireX Broker (validation must be against the correct mainframe security repository where CICS user IDs are defined) or with your own security implementation.
- For `IMPS` value `YES`, the RPC Server for CICS uses the RPC user ID and password supplied by the RPC client for authentication and impersonation of the client. This means that the RPC server validates the password.

The picture above shows the configuration `IMPS=YES`.


The lifetime of an impersonated user task starts when an open request for an RPC conversation or a non-conversational RPC request is received. It ends when the RPC conversation stops (after a commit operation or timeout) or when the non-conversational RPC request has been performed.

For worker threads, the slow-shrinking worker model `DYNAMIC` is used - value `TIMEOUT` is forced internally - any value given in the `ERXMAIN` macro parameter `ENDW` is ignored. The lifetime of worker threads can be controlled with `ERXMAIN` macro parameter `TOUT` as well as the number of workers with macro parameters `MINW` and `MAXW`.

Usage of Server Mapping Files

There are many situations where the RPC Server for CICS requires a server mapping file to correctly support special COBOL syntax such as `REDEFINES`, `SIGN LEADING` and `OCCURS DEPENDING ON` clauses, `LEVEL-88` fields, etc.

Server mapping files contain COBOL-specific mapping information that is not included in the IDL file, but is needed to successfully call the COBOL server program.



The RPC server marshals the data in a two-step process: the RPC request coming from the RPC client (Step 1) is completed with COBOL-specific mapping information taken from the server mapping file (Step 2). In this way the COBOL server can be called as expected.

The server mapping files are retrieved as a result of the IDL Extractor for COBOL extraction process and the COBOL Wrapper if a COBOL server is generated. See *When is a Server Mapping File Required?*

There are *server-side* mapping files (*EntireX Workbench* files with extension `.svm`) and *client-side* mapping files (*Workbench* files with extension `.cvm`). See *Server Mapping Files for COBOL* and *How to Set the Type of Server Mapping Files*.

If you are using server-side mapping files, you need to customize the server-side mapping container with `ERXMAIN` macro parameter `SVM`. See *Configuring the RPC Server*.



Note: Server mapping files are used for COBOL only.

Supported Interface Types

The interface types supported by the RPC Server for CICS vary depending on the target programming language. See also [Locating and Calling the Target Server](#).

COBOL

- *CICS with DFHCOMMAREA Calling Convention* (COBOL Wrapper | Extractor)
- *CICS with Channel Container Calling Convention* (COBOL Wrapper | Extractor)
- *CICS with DFHCOMMAREA Large Buffer Interface* (COBOL Wrapper | Extractor)

PL/I

- *CICS with DFHCOMMAREA Calling Convention* (PL/I Wrapper | Extractor)

3 Administering the RPC Server for CICS

- Customizing the RPC Server 14
- Configuring the RPC Server 16
- Locating and Calling the Target Server 27
- Using SSL/TLS with the RPC Server 28
- User Exit COBUEX02 30
- Autostart/Stop during CICS Start/Shutdown 35
- Multiple RPC Servers in the same CICS 36

The EntireX RPC Server for z/OS CICS® allows standard RPC clients to communicate with RPC servers on the operating system z/OS under CICS. It supports the programming languages COBOL and PL/I.

Customizing the RPC Server

By default, the RPC Server for CICS runs as CICS transaction `ESRV`. This can be changed with parameter `REPL`. The following elements are used for setting up the RPC Server for CICS:

- [ERXMAIN Control Block](#)
- [ERXMAIN Macro](#)
- [RPC Online Maintenance Facility](#)
- [IBM LE Runtime Options](#)
- [CICS Settings](#)

ERXMAIN Control Block

- defines a setup of the RPC Server for CICS that is persistent over CICS restarts
- is defined with parameters of the [ERXMAIN Macro](#); see column 1 in the table under *Configuring the RPC Server*
- contains the following important settings:
 - connection information such as broker ID, see [BKRN](#), server address, see [CLZN](#), [SRVN](#) and [SVCN](#)
 - location and usage of server-side mapping container; see [SVM](#) and [Usage of Server Mapping Files](#)
 - scalability parameters such as `endworker`, `minworker` and `maxworker`, see [ENDW](#), [MINW](#) and [MAXW](#)
 - etc.
- the default name for the control block is `ERXMAIN`, but any meaningful name can be chosen. Using this name as input parameter `memory` for the [RPC Online Maintenance Facility](#) means that multiple RPC Servers for CICS can be started and monitored in parallel. See *Installing Multiple EntireX RPC Servers in the same CICS (Optional)* under *Installing the RPC Server for CICS* in the z/OS Installation documentation.

ERXMAIN Macro

- creates an *ERXMAIN Control Block*, a persistent setup of the RPC Server for CICS
- needs to be assembled to define a setup
- is defined in Assembler program `EMAINGEN` (in `EXP101.SRCE`) - use this for assembling; see *Build the ERXMAIN Control Block* under *Installing the RPC Server for CICS* in the z/OS installation documentation

RPC Online Maintenance Facility

- provides commands (see column 2 in the table below) to vary most of the permanently defined parameters in the *ERXMAIN Control Block* currently in use. All modifications are lost if CICS is restarted. Use *ERXMAIN Macro* for permanent modifications
- allows you to try out new setups of the RPC Server for CICS easily without the need to reassemble the `ERXMAIN` Control Block.
- runs as CICS transaction `ERXM`
- supports
 - starting
 - stopping
 - pinging
 - monitoring
 - activating trace

of the RPC Server for CICS. See [RPC Online Maintenance Facility](#).

IBM LE Runtime Options

Depending on the feature the RPC Server for CICS needs to support (see table below) additional runtime options for IBM's Language Environment need to be set. For a full description of LE runtime options, see [z/OS V1R4.0 Lang Env Prog Guide](#).

Feature	LE Runtime Options	Description
Trap abends of called RPC server programs	<code>ABTERMENC(RETCODE)</code> ⁽¹⁾	Required to also trap the LE abends within a server program.
Level of information if called RPC server program terminates by unhandled condition	<code>TERMTHDACT(UADUMP)</code> ⁽¹⁾	Forces a U4039 system dump for abends not trapped by the server.
Force <code>HANDLE ABEND LABEL</code> getting control for COBOL runtime error and others	<code>USRHDLR=(CEEWUCHA)</code> ⁽¹⁾	The server traps abends using <code>CICS HANDLE ABEND</code> . With Enterprise COBOL for z/OS, errors resulting from the COBOL runtime (table overflow, for

Feature	LE Runtime Options	Description
		example) bypass the CICS abend handler. Setting CEEWUCHA enables the CICS abend handler to also trap the COBOL runtime errors.
Call RPC server programs with AMODE 24 as well	ALL31(OFF), STACK(, , BELOW)	If not specified, AMODE 31 is supported.



Note: ⁽¹⁾ Set internally by the RPC Server for CICS using application-specific CSECT CEEUOPT. The options can be changed if CEEUOPT is replaced on RPC Server for CICS load module RPCSRVC with IBM Linkage Editor.

There are various ways of specifying LE runtime options, for example installation-specific, region-specific (CEEROPT available in the DFHRPL concatenation) or application-specific (linked CSECT CEEUOPT) etc.

CICS Settings

CICS Parameter	Description	Default	How to change?
TWASIZE	Transaction Work Area (TWA) size may be used by target RPC programs called by the RPC Server for CICS. If this is the case, the TWA size set for the RPC Server for CICS must match the largest TWA size required by all called target RPC programs.	TWASIZE(28) This corresponds to 'Adabas Parameter List' if transport method NET is used. See <i>Installing Adabas with TP Monitors for EntireX</i> .	<ul style="list-style-type: none"> Use resource definition online (RDO), CICS transaction CEDA. See member DFHERX in EXP101.SRCE data set. See <i>Updating the CICS Tables</i>.

Configuring the RPC Server

The following rules apply for the *ERXMAIN Macro* syntax (column 1 in table below):

- keywords are given in uppercase
- there are no abbreviations for keywords

The following rules apply for the RPC Online Maintenance Facility commands (column 2 in table below):

- Underscored letters in a command indicate the minimum number of letters that can be used for abbreviation.

For example, in `brokerid=localhost`, `brok` is the minimum number of letters that can be used as an abbreviation, that is, the commands `brokerid=localhost` and `brok=localhost` are equivalents.

ERXMAIN Macro Syntax	RPC Online Maintenance Facility Commands	Default	Values	Req/Opt
BKRN	<code>brokerid</code>	ETB001	<p>Broker ID used by the server. See <i>Using the Broker ID in Applications</i>.</p> <p>Example: BKRN=myhost.com:1971</p>	R
CLZN	<code>class</code>	RPC	<p>Server class part of the server address used by the server. The server address must be defined as a service in the broker attribute file (see <i>Service-specific Attributes</i>). Case-sensitive, up to 32 characters. Corresponds to CLASS attribute of the broker attribute file.</p> <p>Example: CLZN=MyRPC</p>	R
SRVN	<code>servername</code>	SRV1	<p>Server name part of the server address used by the server. The server address must be defined as a service in the broker attribute file. See <i>Service-specific Attributes</i>. Case-sensitive, up to 32 characters. Corresponds to SERVER of the broker attribute file.</p> <p>Example: SRVN=mySrv</p>	R
SVCN	<code>service</code>	CALLNAT	<p>Service part of the server address used by the server. The server address must be defined as a service in the broker attribute file. See <i>Service-specific Attributes</i>. Case-sensitive, up to 32 characters. Corresponds to SERVICE attribute of the broker attribute file.</p> <p>Example: SVCN=MYSERVICE</p>	R
CODE	<code>codepage</code>	no codepage transferred	<p>The codepage tells the broker the encoding of the data. The application must ensure the encoding of the data matches the codepage. The RPC server itself does not convert your application data. The application's data is shipped and received as given. Often, the codepage must also match the encoding used in the RPC server environment for file and terminal IO, otherwise unpredictable results may occur.</p> <p>By default, no codepage is transferred to the broker. It is assumed the broker's locale string defaults match. See</p>	O

ERXMAIN Macro Syntax	RPC Online Maintenance Facility Commands	Default	Values	Req/ Opt
			<p><i>Locale String Mapping</i> If they do not match, provide the codepage here. Example:</p> <pre>CODE=ibm-273</pre> <p>Enable character conversion in the broker by setting the service-specific attribute <code>CONVERSION</code> to "SAGTRPC". See also <i>Configuring ICU Conversion</i> under <i>Configuring Broker for Internationalization</i> in the platform-specific Administration documentation. More information can be found under <i>Internationalization with EntireX</i>.</p>	
COMP	<code>compresslevel</code>	N	<p>Enforce compression when data is transferred between broker and server. See <i>Data Compression in EntireX Broker</i>.</p> <pre>compresslevel= 0 1 2 3 4 5 6 7 8 9 Y N</pre> <p>0-9 0=no compression 9=max. compression</p> <p>N No compression. Y Compression level 6.</p> <p>Example: COMP=6</p>	O
CYCL	<code>restartcycles</code>	15	<p>Number of restart attempts if the broker is not available. This can be used to keep the RPC Server for CICS running while the broker is down for a short time. A restart cycle will be repeated every 60 seconds.</p> <p>Note: Internally, the server waits in periods of 10 seconds (performing six times more cycles), which you can see in the server output.</p> <p>When the number of specified cycles is reached and a connection to the broker is not possible, the RPC Server for CICS stops.</p> <p>Example: CYCL=30</p> <p>The server waits up to 30 minutes (30*6*10 seconds) before it terminates due to a missing broker connection.</p>	O
DPLY	<code>deployment</code>	NO	<p>Activates the deployment service, see Deployment Service. Required to use the Server Mapping Deployment Wizard.</p>	O

ERXMAIN Macro Syntax	RPC Online Maintenance Facility Commands	Default	Values	Req/ Opt
			<p>See <i>Server Mapping Deployment Wizard</i> in the EntireX Workbench documentation.</p> <p>YES Activates the deployment service. The RPC server registers the deployment service in the broker.</p> <p>NO The deployment service is deactivated. The RPC server does not register the deployment service in the broker.</p> <p>Example: DPLY=YES</p>	
ENDW	<u>endworker</u>	TIMEOUT	<p>NEVER Defines worker model FIXED with a fixed number of worker threads. The number of worker threads is defined with ERXMAIN macro parameter MINW. It does not increase or decrease during the lifetime of an RPC server instance.</p> <p>TIMEOUT Defines slow-shrinking worker model DYNAMIC, where the number of worker threads is adjusted to the current number of client requests. With value TIMEOUT, all worker threads not used are stopped in the time specified by the ERXMAIN macro parameter TOUT, except for the minimum number of active workers specified with ERXMAIN macro parameter MINW. The upper limit of workers parallel active is restricted with ERXMAIN macro parameter MAXW.</p> <p>IMMEDIATE Defines fast-shrinking worker model DYNAMIC, where the number of worker threads is adjusted to the current number of client requests. With value IMMEDIATE, worker threads not used are stopped immediately as soon as they have finished their conversation, except for the minimum number of active workers defined with ERXMAIN macro parameter MINW. The upper limit of workers active in parallel is restricted with ERXMAIN macro parameter MAXW.</p>	O

ERXMAIN Macro Syntax	RPC Online Maintenance Facility Commands	Default	Values	Req/Opt
			<p>This parameter is forced to value TIMEOUT if impersonation is switched on, see <i>Impersonation</i> and ERXMAIN macro parameter IMPS.</p> <p>Example: ENDW=IMMEDIATE,MINW=2,MAXW=6</p>	
MINW	<u>minworker</u>	1	<p>Minimum limit of worker threads.</p> <ul style="list-style-type: none"> ■ For worker model DYNAMIC: minimum number of active worker threads, even if no RPC client requests have to be processed. This allows you to define a certain number of worker threads - not used by the currently executing RPC request - to wait for new RPC client requests to process. In this way the RPC server is ready to handle many RPC client requests arriving at the same time. Do not set a value higher than ERXMAIN macro parameter MAXW. ■ For worker model FIXED: number of active worker threads. Do not set a value higher than 31 without adjusting ERXMAIN macro parameter SIZE. <p>See also ERXMAIN macro parameter ENDW.</p> <p>Example: MINW=2</p>	O
MAXW	<u>maxworker</u>	10	<p>Upper limit of worker threads and impersonated user tasks.</p> <ul style="list-style-type: none"> ■ For worker model DYNAMIC: used to restrict the system load. Do not set a value higher than 31 without adjusting ERXMAIN macro parameter SIZE. See also ERXMAIN macro parameter ENDW. ■ For Impersonation: worker threads and impersonated user tasks active in parallel. Do not set a value higher than 15 without adjusting ERXMAIN macro parameter SIZE. See also ERXMAIN macro parameter IMPS <p>Example: MAXW=2</p>	O
ETBL	<u>etblnk</u>	CICSETB	<p>Define the broker stub to be used. See <i>Administering Broker Stubs</i> for available stubs.</p> <p>Example: ETBL=CICSETB</p>	O

ERXMAIN Macro Syntax	RPC Online Maintenance Facility Commands	Default	Values	Req/ Opt						
EXIT	n/a		At startup, the RPC Server for CICS will call the user exit to synchronize its version. If successful, the RPC Server for CICS will continue and call the user exit for the implemented events. See User Exit COBUEX02 .	O						
IMPS	<u>impersonation</u>	NO	<p>Defines if RPC requests are executed under the user ID of the RPC client. Depending on settings, different levels of checks are done prior to RPC server execution. See also Impersonation.</p> <p>impersonation= NO YES AUTO [, <u>sameuser</u> , anyuser]</p> <table border="1"> <tbody> <tr> <td>NO</td> <td>The RPC request is executed anonymously, which means the user ID of the RPC client is not used. RPC requests are executed under the user ID of the RPC server.</td> </tr> <tr> <td>YES</td> <td>The RPC request runs impersonated under the supplied <i>RPC client user ID</i>. For execution of the RPC request, the RPC Server for CICS starts a separate impersonated user task, that is, the client must be known to CICS and the supplied password is validated against CICS. The worker model DYNAMIC is forced; for details see Impersonation.</td> </tr> <tr> <td>AUTO</td> <td> <p>Same as option YES above, except that no password validation is performed, that is, the client is treated as already authenticated. For this setting, make sure the RPC client is correctly authenticated; use either</p> <ul style="list-style-type: none"> ■ a secure broker (validation must be against the correct mainframe security repository where the user IDs are defined) and option <code>sameuser</code> or ■ your own security implementation (option <code>anyuser</code> is supported for compatibility reasons if you need different broker and server user IDs - the customer-written security implementation must validate the RPC client using the <i>RPC client user ID</i>) </td> </tr> </tbody> </table>	NO	The RPC request is executed anonymously, which means the user ID of the RPC client is not used. RPC requests are executed under the user ID of the RPC server.	YES	The RPC request runs impersonated under the supplied <i>RPC client user ID</i> . For execution of the RPC request, the RPC Server for CICS starts a separate impersonated user task, that is, the client must be known to CICS and the supplied password is validated against CICS. The worker model DYNAMIC is forced; for details see Impersonation .	AUTO	<p>Same as option YES above, except that no password validation is performed, that is, the client is treated as already authenticated. For this setting, make sure the RPC client is correctly authenticated; use either</p> <ul style="list-style-type: none"> ■ a secure broker (validation must be against the correct mainframe security repository where the user IDs are defined) and option <code>sameuser</code> or ■ your own security implementation (option <code>anyuser</code> is supported for compatibility reasons if you need different broker and server user IDs - the customer-written security implementation must validate the RPC client using the <i>RPC client user ID</i>) 	O
NO	The RPC request is executed anonymously, which means the user ID of the RPC client is not used. RPC requests are executed under the user ID of the RPC server.									
YES	The RPC request runs impersonated under the supplied <i>RPC client user ID</i> . For execution of the RPC request, the RPC Server for CICS starts a separate impersonated user task, that is, the client must be known to CICS and the supplied password is validated against CICS. The worker model DYNAMIC is forced; for details see Impersonation .									
AUTO	<p>Same as option YES above, except that no password validation is performed, that is, the client is treated as already authenticated. For this setting, make sure the RPC client is correctly authenticated; use either</p> <ul style="list-style-type: none"> ■ a secure broker (validation must be against the correct mainframe security repository where the user IDs are defined) and option <code>sameuser</code> or ■ your own security implementation (option <code>anyuser</code> is supported for compatibility reasons if you need different broker and server user IDs - the customer-written security implementation must validate the RPC client using the <i>RPC client user ID</i>) 									

ERXMAIN Macro Syntax	RPC Online Maintenance Facility Commands	Default	Values		Req/ Opt	
				sameuser	The RPC Server for CICS checks whether the <i>broker client user ID</i> matches the <i>RPC client user ID</i> . This is the default if AUTO is used.	
				anyuser	The <i>RPC client user ID</i> is used for impersonation. The <i>broker client user ID</i> is ignored.	
			<p>Note:</p> <ol style="list-style-type: none"> EntireX supports two user ID/password pairs: a <i>broker client user ID/password</i> pair and an (optional) <i>RPC user ID/password</i> pair sent from RPC clients to the RPC server. With EntireX Security, the <i>broker client user ID/password</i> pair is checked. The <i>RPC user ID/password</i> pair is designed to be checked by the target RPC server. Thus it is possible to use different user IDs in the broker and target RPC server. RPC clients send the (optional) <i>RPC user ID/password</i> pair in the same way as specifying the Natural user ID/password pair for a Natural RPC Server. See for example <i>Using Natural Security</i> in the respective section of the documentation. If the RPC client does not specify the optional <i>RPC user ID/password</i> pair, the <i>broker client user ID</i> is inherited to the <i>RPC user ID</i> and thus used for impersonation by the RPC Server for CICS. <p>Example: IMPS=auto</p>			
LOGN	<u>logon</u>	YES	<p>Execute broker functions LOGON/LOGOFF in worker threads. Must match the setting of the broker attribute AUTOLOGON. Reliable RPC requires logon set to YES. See <i>Reliable RPC</i>.</p> <p>NO No logon/logoff functions are executed. <u>YES</u> Logon/logoff functions are executed.</p>		O	

ERXMAIN Macro Syntax	RPC Online Maintenance Facility Commands	Default	Values	Req/Opt
			Example: LOGN=no	
n/a	<u>mapname</u>		Alias for command memory .	O
n/a	<u>memory</u>		Command to load an <i>ERXMAIN Control Block</i> . See Modifying Parameters of the RPC Server for CICS .	O
OPTS	<u>runoption</u>	0	This parameter is for special purposes. It provides the RPC Server for CICS with additional information. The runoptions are normally set to meet the platform's requirements. Set this parameter only if a support representative provides you with an option and asks you to do so. Syntax: OPTS=(<u><option-list></u>) <u><option-list></u> = [<u><option-list></u> ,] <u><option></u> Example: OPTS=(RUNOPT1, RUNOPT2)	O
PSWD	<u>password</u>		Password for broker logon. Case-sensitive, up to 32 characters. For more information see broker ACI control block field PASSWORD. Example: PSWD=MyPwd	O
PRELOAD	<u>preload</u>	YES	Enable to call RPC Server for CICS with AMODE=24 YES Enable to call RPC server with AMODE 24 or 31. Internally the RPC Server for CICS preloads the called RPC server before execution to check the AMODE and releases the RPC server after this. The disadvantage of this approach is the CICS USECOUNT of the called RPC server program is increased by 2 for every executed RPC call. NO The RPC Server for CICS does not preload the called RPC server to check its AMODE. All RPC servers are called as running in AMODE 31. This option is useful for customers who require the CICS USECOUNT in their accounting (increased by 1 for every executed RPC call) but prevents usage of calling RPC Server with AMODE 24.	O
REPL	<u>replicatename</u>	ESRV	CICS transaction ID (uppercase, up to 4 characters) assigned to worker tasks and as default for user tasks if Impersonation is set. In the START-USER event of the user exit (see User Exit COBUEX02) the CICS transaction ID for	O

ERXMAIN Macro Syntax	RPC Online Maintenance Facility Commands	Default	Values	Req/ Opt
			user tasks can be overridden. See also Introduction to the RPC Server for CICS .	
SIZE	n/a	32768	<p>Size in bytes to hold work memory for worker tasks and impersonated user tasks if impersonation is used. Each task (worker and user) requires the same amount of memory. The following rules apply when calculating the ERXMAIN macro parameter MAXW:</p> <ol style="list-style-type: none"> 1. The theoretical maximum number of tasks can be calculated using the formula: maximum = integer part of $((SIZE-2036)/864-1)$. 2. For tasks in intermediate states (starting or ending), the theoretical maximum number must be reduced. We recommend reserving at least 10% for this purpose. 3. If impersonation is used, the theoretical maximum number must be halved. <p>This means:</p> <ul style="list-style-type: none"> ■ For the default SIZE value of 32768, the theoretical maximum number of tasks (see rule 1 above) is 34 $((32768-2036)/864-1)$. ■ Reducing this value by at least 10% (see rule 2 above) gives 31 for MAXW if no impersonation is used. ■ If impersonation is used, MAXW should be no more than 15 (see rule 3 above). 	O
SVM	svmfile		<p>Usage and location of server-side mapping files. See Server-side Mapping Files in the RPC Server. If no SVM parameter is given, the RPC server tries to open the server-side mapping container, using CICS file with name ERXSVM. If this CICS file is not available, no server-side mapping files are used. If you use server-side mapping files, the server-side mapping container must be installed and configured; see <i>Installing the Server-side Mapping Container for an RPC Server for CICS (Optional)</i> under <i>Installing the EntireX RPC Servers under z/OS</i>. There are also client-side mapping files that do not require configuration here; see <i>Server Mapping Files for COBOL</i>.</p> <p>Syntax: SVM=NO <i>cicsname</i></p>	O

ERXMAIN Macro Syntax	RPC Online Maintenance Facility Commands	Default	Values	Req/ Opt
			<p><i>cicsname</i> The RPC server tries to open the server-side mapping container using the CICS file with name <i>cicsname</i>.</p> <p>no No server-side mapping files are used.</p> <p>Example: SVM=MYSVM</p> <p>See also Usage of Server Mapping Files.</p>	
SYNC		Y	<p>Determines whether a CICS SYNCPOINT COMMIT command is issued.</p> <p>YES Execute CICS SYNCPOINT COMMIT. If running <i>without Impersonation</i>, the server issues a SYNCPOINT COMMIT command after a successful non-conversational request or an end-of-conversation.</p> <p>NO Do not execute CICS SYNCPOINT COMMIT. If running <i>with Impersonation</i>, a SYNCPOINT COMMIT command is issued by CICS when the user task ends. This cannot be disabled.</p> <p>See also Automatic Syncpoint Handling.</p>	O
TOUT	<u>timeout</u>	600	<p>Timeout in seconds, used by the server to wait for broker requests. See broker ACI control block field WAIT for more information. Also influences restartcycles and worker model DYNAMIC.</p> <p>Example: TOUT=300</p>	O
TRC1	<u>tracedestination</u>	CSSL	<p>Name of the destination for trace output. A valid CICS transient data queue. See also Activating Tracing for the RPC Server for CICS.</p>	O
TRLV	<u>tracelevel</u>	0	<p>Trace level for the server. See also Activating Tracing for the RPC Server for CICS.</p> <p>Syntax: TRLV= <u>None</u> Standard Advanced Support</p> <p>None No trace output. Standard For minimal trace output. Advanced For detailed trace output.</p>	O

ERXMAIN Macro Syntax	RPC Online Maintenance Facility Commands	Default	Values	Req/ Opt
			<p>Support This trace level is for support diagnostics and should only be switched on when requested by Software AG support.</p> <p>Example: TRLV=standard</p>	
TROP	<u>traceoption</u>	none	<p>Additional trace option if trace is active. See also Activating Tracing for the RPC Server for CICS.</p> <p>None No additional trace options.</p> <p>STUBLOG If <code>tracellevel</code> is Advanced or Support, the trace additionally activates the broker stub log.</p> <p>NOTRUNC Normally if a data buffer larger than 8 KB is traced, the buffer trace is truncated. Set this option to write the full amount of data without truncation.</p> <p>Note: This can increase the amount of trace output data dramatically if you transfer large data buffers.</p> <p>Example: TROP=(STUBLOG , NOTRUNC)</p>	O
USER	<u>userid</u>	ERXSRV1	<p>Used to identify the server to the broker. See broker ACI control block field <code>USER-ID</code>. Case-sensitive, up to 32 characters.</p> <p>Example: USER=MyUid</p>	O

Locating and Calling the Target Server

The IDL library and IDL program names that come from the RPC client are used to locate the RPC server. See `library-definition` and `program-definition` under *Software AG IDL Grammar* in the IDL Editor documentation. This two-level concept (library and program) has to be mapped to the RPC Server for CICS environment. Different mechanisms are used depending on the language:

- COBOL
- PL/I

COBOL

The approach used to derive the CICS program name for the RPC server depends on whether server mapping is used or not. See [Usage of Server Mapping Files](#) for an introduction.

1. If the RPC client sends a client-side type of server mapping with the RPC request, this server mapping is used first.
2. If no server mapping is available from step 1 above, and if server-side type of server mapping is used, the IDL library and IDL program names are used to form a key to locate the server mapping in the server-side mapping container. If a server mapping is found, this is then used.
3. If a server mapping is available from step 1 or 2 above, the CICS program name of the RPC server is derived from this mapping. In this case the IDL program name can be different to the CICS program name if it is renamed during wrapping process (see *Customize Automatically Generated Server Names*) or during the extraction process in the *COBOL Mapping Editor*.
4. If no server mapping is used at all, the IDL program name is used as the CICS program name of the RPC server (the IDL library name is ignored).

➤ To use the RPC Server for CICS with COBOL

- 1 Make sure that all CICS programs called as RPC servers
 - use an interface type supported by the RPC Server for CICS for target language COBOL; see [Supported Interface Types](#).
 - can be called with an `EXEC CICS LINK PROGRAM`
 - are accessible through the CICS RPL chain or accessible remotely using CICS DPL
- 2 Configure the `ERXMAIN` macro parameter `SVM` depending on whether server-side mapping files are used or not. See also [Usage of Server Mapping Files](#).

See also [Scenario I: Calling an Existing COBOL Server](#) or [Scenario II: Writing a New COBOL Server](#).

PL/I

There is a simple mechanism to derive the RPC server CICS program name:

- The IDL program name is used as the CICS program name.
- The IDL library name is not used.

» To use the RPC Server for CICS with PL/I

- Make sure that all CICS programs called as RPC servers
 - use an interface type supported by the RPC Server for CICS for target language PL/I; see [Supported Interface Types](#).
 - can be called with an `EXEC CICS LINK PROGRAM`
 - are accessible through the CICS RPL chain or accessible remotely using CICS DPL

See also [Scenario III: Calling an Existing PL/I Server](#) or [Scenario IV: Writing a New PL/I Server](#).

Using SSL/TLS with the RPC Server

RPC servers can use Secure Sockets Layer/Transport Layer Security (SSL/TLS) as the transport medium. The term “SSL” in this section refers to both SSL and TLS. RPC-based servers are always SSL clients. The SSL server can be either the EntireX Broker, Broker SSL Agent, or Direct RPC in webMethods Integration Server (IS inbound). For an introduction see *SSL/TLS and Certificates with EntireX* in the EntireX Security documentation.


SSL delivered on a z/OS mainframe will typically use the Resource Access Control Facility (RACF) as the certificate authority (CA). Certificates managed by RACF can only be accessed through the RACF keyring container. A keyring is a collection of certificates that identify a networking trust relationship (also called a trust policy). In an SSL client/server network environment, entities identify themselves using digital certificates called through a keyring. Server applications on z/OS that wish to establish network connections to other entities can use keyrings and their certificate contents to determine the trustworthiness of the client or peer entity. Note that certificates can belong to more than one keyring, and you can assign different users to the same keyring. Because of the way RACF internally references certificates, they must be uniquely identifiable by owner and label, and also unique by serial number plus data set name (DSN).

For establishing an SSL connection on z/OS, IBM's Application Transparent Transport Layer Security (AT-TLS) can be used, where the establishment of the SSL connection is pushed down the stack into the TCP layer.

With the RPC Server for CICS you can use IBM's Application Transparent Transport Layer Security (AT-TLS), where the establishment of the SSL connection is pushed down the stack into the TCP layer.

Using IBM's Application Transparent Transport Layer Security (AT-TLS)

Configure the AT-TLS rules for the policy agent (PAGENT) ⁴ using an appropriate client ¹ and the z/OS Management Facility (z/OSMF) ². Together with SSL parameters (to provide certificates stored in z/OS as RACF keyrings) define AT-TLS rules, for example by using the application ⁵ job name and remote TCP port number. If the rules match, the TCP connection is turned into an SSL connection ⁶. Refer to your IBM documentation for more information, for example the IBM Redbook *Communications Server for z/OS VxRy TCP/IP Implementation Volume 4: Security and Policy-Based Networking*.



- ¹ Client to interact with z/OS Management Facility (z/OSMF).
- ² AT-TLS rules are defined with z/OSMF policy management.
- ³ Policy Repository with AT-TLS rules stored as z/OS files.
- ⁴ Policy Agent, MVS task PAGENT, provides AT-TLS rules through a policy enforcement point (PEP) to TCP/IP stack.
- ⁵ Application using TCP connection.
- ⁶ If AT-TLS rules match, the TCP connection is turned into an SSL connection.

Notes:

1. The client ¹ may vary per operating system, for example a Web browser for z/OS 2.1.

2. z/OSMF [2](#) includes other administration and management tasks in addition to policy management.
3. Policy Management [3](#) includes other rules, such as IP filtering, network address translation etc.

➤ **To set up SSL with AT-TLS**

- 1 To operate with SSL, certificates need to be provided and maintained. Depending on the platform, Software AG provides default certificates, but we strongly recommend that you create your own. See *SSL/TLS Sample Certificates Delivered with EntireX* in the EntireX Security documentation.
- 2 Set up the RPC Server for CICS for a TCP/IP connection. On mainframe platforms, use *Transport-method-style Broker ID*. Example:

```
ETB024:1699:TCP
```

- 3 Configure AT-TLS to turn the TCP/IP connection to an SSL connection, see above.
- 4 Make sure the SSL server to which the RPC Server for CICS connects is prepared for SSL connections as well. The SSL server can be EntireX Broker, Broker SSL Agent, or Direct RPC in webMethods Integration Server (IS inbound). See:
 - *Running Broker with SSL/TLS Transport* in the platform-specific Administration documentation
 - *Setting up and Administering the EntireX Broker SSL Agent* in the UNIX and Windows Administration documentation
 - *Support for SSL/TLS* in the EntireX Adapter documentation (for Direct RPC)

User Exit COBUEX02


The RPC Server for CICS provides a user exit COBUEX02 to influence/control the RPC logic. This section covers the following topics:

- [User Exit Events](#)
- [Writing the User Exit](#)

- Configuring the User Exit

User Exit Events

The user exit is called on the following events:



The numbers in the graphic correspond to the event numbers in the user exit.

Step	Event	Called	Description	Note
1	WHICH-VERSION	During startup of RPC server.	The RPC Server for CICS and the exit decide on the version to use. See field VERSION .	
3	START-WORKER	Before starting a worker task.	This allows you to set the CICS transaction ID of the worker task. See field CICS-TRANSID .	1
5	START-USER	Before starting a user task.	Requires <i>Impersonation</i> . Before an impersonated CICS transaction (user task) is started, the user exit may change the user ID, CICS transaction ID and CICS terminal ID of the new impersonated user task. See fields USERID , CICS-TRANSID and CICS-TERMINID .	1
7	CALL-START	Before calling the target CICS program.	See field RPC-SERVER . You can inspect and modify the RPC request (payload data from the RPC client to the RPC server).	1
8	CALL-END	After calling the target CICS program.	See field RPC-SERVER . You can inspect and modify the RPC reply (payload data from the RPC server to the RPC client).	2

 **Notes:**

1. An RPC request can be terminated if an error is given in the fields `ERROR-CODE` and `ERROR-TEXT`. The RPC request is already executed.
2. If an error is given in the fields `ERROR-CODE` and `ERROR-TEXT`, this error is returned to the RPC client. The RPC request is already executed.

Writing the User Exit

EntireX provides the following resources for COBOL:

- User exit skeleton `COBUEX02` in data set `EXP101.SRCE`. Copy this skeleton so you have your own user exit source for modifications. The user exit program must comply with the `EXEC CICS LINK PROGRAM COMMAREA` conventions.
- Copybook `COBUEX02` in data set `EXP101.INCL`. Please add `EXP101.INCL` to your COBOL compiler `SYSLIB DD` chain. The copybook also contains further description and usage comments.

The parameters of `COBUEX02` are described below.

Parameter	Format	I/O	Description
<code>EXIT-FUNCTION</code>	<code>PIC 9(4) BINARY</code>	I	Signals the event. See User Exit Events .
<code>VERSION</code>	<code>PIC 9(4) BINARY</code>	I/O	For event <code>WHICH-VERSION</code> , see User Exit Events . On input, the RPC Server for CICS provides the maximum supported version; on output, the exit returns the version to be used. Values 1-2 may be supplied. Some of the fields require a minimum version.
<code>TRACE-LEVEL</code>	<code>PIC 9(4) BINARY</code>	I	Informational. Value is 0 - n. Corresponds to parameter <code>tracelevel</code> .
<code>ERROR-CODE</code>	<code>PIC 9(4) BINARY</code>	O	Must be set on output. Possible values: 0 Success. Continue this RPC request. 1..9999 Stop the RPC request. Reply with error class 1022 together with field <code>ERROR-TEXT</code> to the calling RPC client. Example: Error code value <code>nnnn</code> results in the following error message: <code>1022nnnn error-text</code> . See Message Class 1022 - RPC Server for CICS User Exit Messages .
<code>ERROR-TEXT</code>	<code>PIC X(256)</code>	O	Error text returned to RPC client if an error is supplied in field <code>ERROR-CODE</code> . Up to 256 characters.
<code>CICS-TRANSID</code>	<code>PIC X(4)</code>	I/O	Input defined by macro <code>EMAINGEN</code> . Default is <code>ESRV</code> . Can be modified on output. Available for the following events: <code>START-WORKER</code> Transaction ID to start the <code>WORKER-TASK</code> . <code>START-USER</code> Transaction ID to start the <code>USER-TASK</code> . Requires <i>Impersonation</i> .

Parameter	Format	I/O	Description
CICS-TERMID	PIC X(4)	O	Available for the following event: START-USER If applied on output, starts the USER-TASK with the supplied terminal ID. Requires <i>Impersonation</i> .
USERID	PIC X(32)	I/O	Input supplied by RPC client. Available for the following event: START-USER If applied on output, starts the USER-TASK with the supplied user ID. Requires <i>Impersonation</i> .
RPC-LIBRARY	PIC X(128)	I	IDL library name. Informational. Availability depends on event and VERSION : START-USER If field VERSION >=2 has been set on WHICH-VERSION. CALL-START All supported field VERSIONs. CALL-END All supported field VERSIONs.
RPC-PROGRAM	PIC X(128)	I	IDL program name. Informational. Availability depends on event and VERSION : START-USER If field VERSION >=2 has been set on WHICH-VERSION. CALL-START All supported field VERSIONs. CALL-END All supported field VERSIONs.
INTERFACE-TYPE	PIC X	I	Type of interface. Informational. Available for events CALL-START and CALL-END. Possible values: D DFHCOMMAREA C Channel Container W Large Buffer
RPC-SERVER	PIC X(8)	I	Target CICS program to call. Informational. Available for the following events: CALL-START All supported field VERSIONs. CALL-END All supported field VERSIONs.
CHANNEL-NAME	PIC X(16)	I	Name of CICS Channel. Informational. Applicable if field INTERFACE-TYPE is 'C' (Channel Container). Available for the following events: CALL-START All supported field VERSIONs. CALL-END All supported field VERSIONs.

Parameter	Format	I/O	Description																					
CHAIN-COUNTER	PIC S9(9) BINARY	I	<table border="1"> <thead> <tr> <th>Event</th> <th>Interface Type</th> <th>Chain Counter</th> </tr> </thead> <tbody> <tr> <td>CALL-START</td> <td>DFHCOMMAREA</td> <td>1</td> </tr> <tr> <td>CALL-END</td> <td>DFHCOMMAREA</td> <td>1</td> </tr> <tr> <td>CALL-START</td> <td>Channel Container</td> <td><i>number-input-containers</i></td> </tr> <tr> <td>CALL-END</td> <td>Channel Container</td> <td><i>number-output-containers</i></td> </tr> <tr> <td>CALL-START</td> <td>Large Buffer</td> <td>1</td> </tr> <tr> <td>CALL-END</td> <td>Large Buffer</td> <td>1</td> </tr> </tbody> </table>	Event	Interface Type	Chain Counter	CALL-START	DFHCOMMAREA	1	CALL-END	DFHCOMMAREA	1	CALL-START	Channel Container	<i>number-input-containers</i>	CALL-END	Channel Container	<i>number-output-containers</i>	CALL-START	Large Buffer	1	CALL-END	Large Buffer	1
			Event	Interface Type	Chain Counter																			
			CALL-START	DFHCOMMAREA	1																			
			CALL-END	DFHCOMMAREA	1																			
			CALL-START	Channel Container	<i>number-input-containers</i>																			
			CALL-END	Channel Container	<i>number-output-containers</i>																			
			CALL-START	Large Buffer	1																			
CALL-END	Large Buffer	1																						
CHAIN-POINTER	POINTER	I	<p>Informational. Pointer to first element of a table (or chain of elements) describing payload data. See structure DATA-ENTRY. Available for the following events:</p> <p>CALL-START The table or chain of elements (structure DATA-ENTRY) contains descriptions of input payload data.</p> <p>CALL-END The table or chain of elements (structure DATA-ENTRY) contains descriptions of output payload data.</p>																					
CHAIN-COUNTER-OUT	PIC S9(9) BINARY	I	<table border="1"> <thead> <tr> <th>Event</th> <th>Interface Type</th> <th>Chain Counter</th> </tr> </thead> <tbody> <tr> <td>CALL-START</td> <td>DFHCOMMAREA</td> <td>1</td> </tr> <tr> <td>CALL-START</td> <td>Channel Container</td> <td><i>number-output-containers</i></td> </tr> <tr> <td>CALL-START</td> <td>Large Buffer</td> <td>1</td> </tr> </tbody> </table>	Event	Interface Type	Chain Counter	CALL-START	DFHCOMMAREA	1	CALL-START	Channel Container	<i>number-output-containers</i>	CALL-START	Large Buffer	1									
			Event	Interface Type	Chain Counter																			
			CALL-START	DFHCOMMAREA	1																			
CALL-START	Channel Container	<i>number-output-containers</i>																						
CALL-START	Large Buffer	1																						
CHAIN-POINTER-OUT	POINTER	I	<p>Similar to CHAIN-POINTER. Informational. See structure DATA-ENTRY. Available for the following event:</p> <p>CALL-START If field <code>VERSION >=2</code> has been set on <code>WHICH-VERSION</code>. The table or chain of elements (structure DATA-ENTRY) contains descriptions of expected output payload data with maximum length for variable length data, for example <code>OCCURS DEPENDING ON ...</code></p>																					
RPC-RETCODE	PIC 9(9) BINARY	I	<p>RPC error code. Informational.</p> <p>1001 0045 CICS abend code.</p> <p>1002 <i>nnnn</i> User-definable server message.</p> <p>...</p> <p>See <i>Error Messages and Codes</i>.</p>																					
CICS-ABCODE	PIC X(4)	I	CICS abend code. Informational.																					
DATA-ENTRY		I	Structure. Informational. Consists of: <code>DATA-NAME</code> , <code>DATA-LENGTH</code> , <code>DATA-POINTER</code> .																					

Parameter	Format	I/O	Description																					
DATA-NAME	PIC X(16)	I	<table border="1"> <thead> <tr> <th>Event</th> <th>Interface Type</th> <th>Container Name</th> </tr> </thead> <tbody> <tr> <td>CALL-START</td> <td>DFHCOMMAREA</td> <td>'DFHCOMMAREA'</td> </tr> <tr> <td>CALL-END</td> <td>DFHCOMMAREA</td> <td>'DFHCOMMAREA'</td> </tr> <tr> <td>CALL-START</td> <td>Channel Container</td> <td><i>input-container-name</i> or <i>output-container-name</i></td> </tr> <tr> <td>CALL-END</td> <td>Channel Container</td> <td><i>output-container-name</i></td> </tr> <tr> <td>CALL-START</td> <td>Large Buffer</td> <td>'WM-LCB-INPUT'</td> </tr> <tr> <td>CALL-END</td> <td>Large Buffer</td> <td>'WM-LCB-OUTPUT'</td> </tr> </tbody> </table>	Event	Interface Type	Container Name	CALL-START	DFHCOMMAREA	'DFHCOMMAREA'	CALL-END	DFHCOMMAREA	'DFHCOMMAREA'	CALL-START	Channel Container	<i>input-container-name</i> or <i>output-container-name</i>	CALL-END	Channel Container	<i>output-container-name</i>	CALL-START	Large Buffer	'WM-LCB-INPUT'	CALL-END	Large Buffer	'WM-LCB-OUTPUT'
			Event	Interface Type	Container Name																			
			CALL-START	DFHCOMMAREA	'DFHCOMMAREA'																			
			CALL-END	DFHCOMMAREA	'DFHCOMMAREA'																			
			CALL-START	Channel Container	<i>input-container-name</i> or <i>output-container-name</i>																			
			CALL-END	Channel Container	<i>output-container-name</i>																			
			CALL-START	Large Buffer	'WM-LCB-INPUT'																			
CALL-END	Large Buffer	'WM-LCB-OUTPUT'																						
DATA-LENGTH	PIC 9(9) BINARY	I	Length or maximum expected length: With event CALL-START and CHAIN-POINTER-OUT : the maximum length of payload data. For all other cases, the actual length of the payload data.																					
DATA-POINTER	POINTER	I	Pointer to payload for this element.																					

Configuring the User Exit

Apply the name of your exit routine to the EntireX RPC server [ERXMAIN macro](#) parameter [EXIT](#). See *Configuring the RPC Server*.

At startup, the RPC Server for CICS will call the named user exit to synchronize its version. If successful, the [RPC Online Maintenance Facility](#) will display the user exit as map field "parameter opts". See *To display the Server parameters (PF06) under RPC Online Maintenance Facility*. The RPC Server for CICS will continue and call the user exit for the implemented events.

Autostart/Stop during CICS Start/Shutdown

The RPC Server for CICS can be started and stopped automatically during start and stop of the CICS region. For manual start/stop, see [Starting the RPC Server for CICS](#) and [Stopping the RPC Server for CICS](#) under *RPC Online Maintenance Facility*.

» To start the RPC Server for CICS during the initialization of CICS

- 1 If the COBOL source ERXSTART of the EntireX installation library EXP101.SRCE has not been defined in the CICS CSD data sets by the installation job \$INSTALL, define it.
- 2 Customize and compile ERXSTART if necessary.
- 3 Add the following entry to your CICS PLTPI table (second phase PLT program):

```
DFHPLT TYPE=ENTRY , PROGRAM=ERXSTART
```

See also *Starting the EntireX RPC Server Automatically on CICS Startup (Optional)* under *Installing the RPC Server for CICS* in the z/OS Installation documentation.

➤ **To stop the RPC Server for CICS during the shutdown of CICS**

- 1 If the COBOL source ERXSTOP of the EntireX installation library EXP101.SRCE has not been defined in the CICS CSD data sets by the installation job \$INSTALL, define it.
- 2 Customize and compile ERXSTOP if necessary.
- 3 Add the following entry to your CICS PLTSD table (first phase PLT program):

```
DFHPLT TYPE=ENTRY , PROGRAM=ERXSTOP
```

See also *Stopping the EntireX RPC Server Automatically on CICS Shutdown (Optional)* under *Installing the RPC Server for CICS* in the z/OS Installation documentation.

Multiple RPC Servers in the same CICS

If you need to install multiple instances in the same CICS region, see *Installing Multiple EntireX RPC Servers in the same CICS (Optional)* under *Installing the RPC Server for CICS* in the z/OS Installation documentation.

4 **RPC Online Maintenance Facility**

- Monitoring the RPC Server for CICS 38
- Starting the RPC Server for CICS 40
- Pinging the RPC Server for CICS 41
- Stopping the RPC Server for CICS 41
- Modifying Parameters of the RPC Server for CICS 41
- Activating Tracing for the RPC Server for CICS 42
- Console Commands for the RPC Server for CICS 42

Monitoring the RPC Server for CICS

The parameters in the following screens are described under [Configuring the RPC Server](#).

➤ **To call the RPC Online Maintenance Facility and display the RPC Broker Parameters**

- Start the CICS transaction

```
ERXM [MEM=erxmain-control-block]
```

where *erxmain-control-block* is the name of the ERXMAIN control block. See [ERXMAIN Control Block](#) under *Customizing the RPC Server*.

The RPC Broker Parameter map is displayed:

```

11:56:56          --- ERX CICS OnLine utility  V101.0 ---          12/11/2015
                    RPC Broker Parameter

Broker parameter
Broker name      = ETB001
Class name       = RPC
Server name      = SRV2
Service name     = CALLNAT

User ID          = ERXSRV1
Logon            = Yes

Code page        =
Server timeout   = 60
Compress level   = N
ETBLNK           = CICSETB

COMMAND ==>
=====
PF01=Help  03=Exit  04=Control  05=Broker parms  06=Server parms
           08=Start server  09=Ping server  10=Stop server
    
```

Press **PF05** from any map to return to the RPC Broker Parameter map.

➤ **To display the RPC Server Parameters**

- Press **PF06** from any map and the RPC Server Parameters will be displayed:

```

12:03:05          --- ERX CICS Online utility  V101.0 ---          06/02/2014
                    RPC Server Parameter

Server parameter
# Min. Workers =      2              Trace Level   = 0
# Max. Workers =      2              Trace Dest.(TD)= CSSL
Ending Workers = Never
Impersonation  = No
Deployment     = Yes
Restart Cycles =      3

Server options = SVM      AutoSYNC
Marshal options=

CICS parameter                Mapping file = ERXSVM   (Preferred)
Memory name   = ERXMAIN   (V900)  Dsn(ENTIREX.SVMDEV.KSDS)
Transaction ID = ESRV           Opn Add Rea Upd Del

COMMAND ===>
=====
PF01=Help   03=Exit   04=Control  05=Broker parms  06=Server parms
              08=Start server  09=Ping server  10=Stop server

```

> **To display the RPC Server Control map**

■ **Press PF04.**

```

12:07:18          --- ERX CICS Online utility  V101.0 ---          06/02/2014
                    RPC Server Control

MAIN Task
Status      Running

WORKER Tasks
Registered      2
Busy            0
Maximum busy    2

USER Tasks
Active          0
Max. active     0

BrokerId in use:  ETB001
Class in use:     RPC
Server Name in use:  SRV1
Service in use:   CALLNAT

COMMAND ===>
=====

```

PF01=Help	03=Exit	04=Control	05=Broker parms	06=Server parms
		08=Start server	09=Ping server	10=Stop server

➤ **To display help for the RPC Online Maintenance Facility**

- Enter `Help` or press **PF01**.

➤ **To stop the RPC Online Maintenance Facility**

- Enter `Exit` or press **PF03**.

Starting the RPC Server for CICS

➤ **To start the RPC Server for CICS using the RPC Online Maintenance Facility**

- 1 Start the CICS transaction `ERXM` to call the RPC Online Maintenance Facility. See also [Monitoring the RPC Server for CICS](#).
- 2 Start the server with the **PF08** key or with the command `start`.
The status of the `MAIN` task (see RPC server control panel) changes to “is running”. The defined number (see `ERXMAIN` macro parameter `MINW`) of worker tasks that are registered is displayed.

If an error occurred and the RPC Server for CICS is not correctly registered in the broker, but the number of currently active worker tasks is not zero:

- Check with CICS command `CEMT INQUIRE TASK` whether server instances are already running. If yes, stop them using native CICS commands.
- Verify the server parameters matching your system requirements. See column 2 of table under [Configuring the RPC Server](#).
- Then issue command `start` or use **PF08**.

Alternatively, you can use the `start` command from the console. See [Console Commands for the RPC Server for CICS](#).

Pinging the RPC Server for CICS

➤ To ping the RPC Server for CICS using the RPC Online Maintenance Facility

- 1 Start the CICS transaction ERXM to call the EntireX RPC Online Maintenance Facility. See [Monitoring the RPC Server for CICS](#).
- 2 Issue the command ping or use PF09.

Alternatively you can use the ping command from the console. See [Console Commands for the RPC Server for CICS](#).

Stopping the RPC Server for CICS

➤ To stop the RPC Server for CICS using the RPC Online Maintenance Facility

- 1 Start the CICS transaction ERXM to call the RPC Online Maintenance Facility. See [Monitoring the RPC Server for CICS](#).
- 2 Issue the stop command or use PF10. This ensures correct deregistration from broker and all worker threads are shut down.

Alternatively, you can use the stop command from the console. See [Console Commands for the RPC Server for CICS](#).

Modifying Parameters of the RPC Server for CICS

With RPC Online Maintenance Facility commands, RPC Server for CICS parameters can be temporarily modified. Modifications are lost if CICS is restarted. The purpose of the commands is to try out easily new configurations. For persistent modifications (setup) of the RPC Server for CICS, reassemble the **ERXMAIN Control Block** using the **ERXMAIN Macro**.

➤ To modify the RPC Server for CICS parameters using the RPC Online Maintenance Facility

- 1 Start the CICS transaction ERXM to call the RPC Online Maintenance Facility. See [Monitoring the RPC Server for CICS](#).
- 2 Use the appropriate RPC Online Maintenance Facility command to modify the parameters. See the column 2 of table under [Configuring the RPC Server](#).

Activating Tracing for the RPC Server for CICS

➤ To switch on tracing for the RPC Server for CICS using the RPC Online Maintenance Facility

A prerequisite to switch on tracing is a valid defined trace destination. We recommend defining it permanently, see [ERXMAIN macro](#) parameter [TRC1](#).

- 1 Start the CICS transaction `ERXM` to call the RPC Online Maintenance Facility. See [Monitoring the RPC Server for CICS](#).
- 2 Temporarily change the trace level with the command `tracellevel=tracelevel`, where `tracelevel` is one of `None`, `Standard`, `Advanced` or `Support`. See [ERXMAIN macro](#) parameter [TRLV](#).

Example: `tracellevel=Standard`

- 3 Dynamically change the trace option with the command `traceoption=traceoption`, where `traceoption` is one of `None`, `STUBLOG` or `NOTRUNC`. See [ERXMAIN macro](#) parameter [TROP](#).

Example: `traceoption=NOTRUNC`

To evaluate RPC Server for CICS return codes, see [EntireX RPC Server Return Codes](#).

Alternatively, you can issue the command from the console. See [Console Commands for the RPC Server for CICS](#).

Console Commands for the RPC Server for CICS

The RPC Online Maintenance Facility `ERXM` can be used directly from a z/OS console using the z/OS command `MODIFY /F`. In the command syntax below:

- `cics-name` is the name of the CICS job
- `erxmain-control-block` is the name of the [ERXMAIN Control Block](#). It can be omitted if the default name `ERXMAIN` is used.
- No blanks are allowed in the string provided to `ERXM`, for example
`MEM=erxmain-control-block,CMD=...`

➤ To start the RPC Server for CICS from a z/OS console

- Use the following z/OS `MODIFY` command:

```
F cics-name,ERXM [MEM=erxmain-control-block,]CMD=START
```

➤ **To ping the RPC Server for CICS from a z/OS console**

- Use the following z/OS MODIFY command:

```
F cics-name,ERXM [MEM=erxmain-control-block,]CMD=PING
```

➤ **To stop the RPC Server for CICS from a z/OS console**

- Use the following z/OS MODIFY command:

```
F cics-name,ERXM [MEM=erxmain-control-block,]CMD=STOP
```

➤ **To switch on tracing for the RPC Server for CICS from a z/OS console**

- Use the following z/OS MODIFY command:

```
F cics-name,ERXM [MEM=erxmain-control-block,]CMD=TRACELEVEL=tracelevel
```

For *tracelevel*, see [Activating Tracing for the RPC Server for CICS](#).

5 Deployment Service


- Introduction 46
- Scope 47
- Enabling the Deployment Service 47
- Disabling the Deployment Service 48

Introduction

The deployment service is the (server-side) counterpart to the deployment wizard; see *Server Mapping Deployment Wizard*. It is a built-in service of the EntireX RPC server, which can be enabled/disabled by EntireX RPC server configuration settings.

Usage can be restricted to certain users or group of users, using EntireX Security; see *Authorization of Client and Server* in the EntireX Security documentation.

You need to configure the deployment service only when server-side mapping files are used. There are also client-side server mapping files that do not need configuration here; see *Server Mapping Files for COBOL* in the EntireX Workbench documentation.



Scope

The deployment service is used in conjunction with the

- IDL Extractor for COBOL to deploy server-side mapping files with the deployment wizard;
- COBOL Wrapper for RPC server generation to deploy server-side mapping files with the deployment wizard.

See also [Deploying Server-side Mapping Files to the RPC Server](#).

The deployment service uses the same class and server names as defined for the EntireX RPC server, and `DEPLOYMENT` as the service name, resulting in `class/server/DEPLOYMENT` as the broker service. Please note `DEPLOYMENT` is a service name reserved by Software AG. See broker attribute `SERVICE`.

Enabling the Deployment Service

» To enable the deployment service

- 1 For an RPC Server for CICS, the server-side mapping container (VSAM file) must be installed and configured. See *Installing the Server-side Mapping Container for an RPC Server for CICS (Optional)* under *Installing the EntireX RPC Servers under z/OS*.
- 2 Set `ERXMAIN Macro` parameter `DPLY=YES`. See `DPLY` under [Configuring the RPC Server](#).
- 3 Define in the broker attribute file, under the RPC service, an additional broker service with `DEPLOYMENT` as the service name and values for class and server identical to those used for the RPC service. For example, if your RPC service is named

```
CLASS = RPC    SERVER = SRV1    SERVICE = CALLNAT
```

the deployment service requires the following additional service definition in the broker attribute file:

```
CLASS = RPC    SERVER = SRV1    SERVICE = DEPLOYMENT
```

- 4 Optional. If you need to restrict the use of the deployment service to a selected group of users, use EntireX Security and define security rules for the `class/server/DEPLOYMENT` broker service. The service name `DEPLOYMENT` is a constant.
 - For a z/OS broker, see *Resource Profiles in EntireX Security*.
 - For a UNIX or Windows broker, see *Authorization Rules*.

- Not applicable to a BS2000 or z/VSE broker.

Disabling the Deployment Service

> To disable the deployment service

- Set *ERXMAIN Macro* parameter `DPLY=NO`. See *ERXMAIN macro* parameter `DPLY`.

The RPC Server for CICS will not register the deployment service in the broker.

6 Server-side Mapping Files

- Server-side Mapping Files in the RPC Server 50
- Deploying Server-side Mapping Files to the RPC Server 51
- Undeploying Server-side Mapping Files from the RPC Server 52
- Change Management of Server-side Mapping Files 53
- List Deployed Server-side Mapping Files 53
- Check if a Server-side Mapping File Revision has been Deployed 54
- Access Control: Secure Server Mapping File Deployment 54
- Ensure that Deployed Server-side Mapping Files are not Overwritten 54
- Is There a Way to Smoothly Introduce Server-side Mapping Files? 54

Server mapping enables the RPC server to correctly support special COBOL syntax such as `REDEFINES`, `SIGN LEADING` and `OCCURS DEPENDING ON` clauses, `LEVEL-88` fields, etc. If one of these elements is used, the IDL Extractor for COBOL automatically extracts a server mapping file in addition to the IDL file (interface definition language). Also, the COBOL Wrapper may generate a server mapping file for RPC server generation. The server mapping is used at runtime to marshal and unmarshal the RPC data stream. There are client-side mapping files (EntireX Workbench files with extension `.cvm`) and server-side mapping files (Workbench files with extension `.svm`). If you have not used server-side mapping, we recommend you use client-side mapping. See *Server Mapping Files for COBOL* in the EntireX Workbench documentation.

See also *Source Control of Server Mapping Files* | *Comparing Server Mapping Files* | *When is a Server Mapping File Required?* | *Migrating Server Mapping Files* in the EntireX Workbench documentation.

Server-side Mapping Files in the RPC Server

Under z/OS, server-side mapping corresponds to lines of EntireX Workbench files with extension `.svm`. See *Server Mapping Files for COBOL*. The mapping information is stored as records within one VSAM file, the server-side mapping container. This container contains all server-side mapping entries from all EntireX Workbench files with extension `.svm`. The unique key of the VSAM file consists of the first 255 bytes of the record: for the type (1 byte), for the IDL library (127 bytes) and for the IDL program (127 bytes).

If *one* server requires a server-side mapping file, you need to provide this to the RPC server:

- Development environments: to deploy new server-side mapping files, see [Deploying Server-side Mapping Files to the RPC Server](#).
- Production environments: provide a server-side mapping container (VSAM file) containing all required server-side mapping files to the RPC server. See `ERXMAIN` macro parameter `SVM`.

If *no* server requires server-side mapping, you can execute the RPC server without server mapping files:

- Development environments: you can disable the deployment service. See [Disabling the Deployment Service](#).
- Production environments: there is no need to provide a server-side mapping container (VSAM file) to the RPC server. See `ERXMAIN` macro parameter `SVM`.

Deploying Server-side Mapping Files to the RPC Server


The following approaches are available to deploy a server-side mapping file (EntireX Workbench file with extension .svm; see *Server Mapping Files for COBOL*):

- Server Mapping Deployment Wizard
- FTP and IDCAMS

➤ To deploy a server-side mapping file with the Server Mapping Deployment Wizard

- 1 Make sure your RPC server is active and that the Deployment Service of the RPC server is properly configured. See [Deployment Service](#).
- 2 From the context menu of your IDL file, choose **COBOL > Deploy/Synchronize Server Mapping** and call the Server Mapping Deployment Wizard. See *Server Mapping Deployment Wizard* in the EntireX Workbench documentation.

➤ To deploy a server-side mapping file using FTP and IDCAMS



- 1 Make sure the server-side mapping container (VSAM file) is installed. See *Installing the Server-side Mapping Container for an RPC Server for CICS (Optional)* under *Installing the EntireX RPC Servers under z/OS*.
- 2 Allocate a target sequential file on your mainframe.
- 3 Allow write access to the VSAM file mentioned above and usage of IDCAMS tools.
- 4 Transfer the server-side mapping file to the target host, using FTP. You have to switch to text mode and the codepage of the FTP service must be the same as the codepage (locale string) of the RPC server used.
- 5 Install the server mapping contained in the server-side mapping file into the server-side mapping container (VSAM file) with an appropriate IDCAMS job.

```
//EXPSVMR JOB ( , , , 999), ENTIREX, NOTIFY=&SYSUID, MSGLEVEL=(1,1),
//          CLASS=K, MSGCLASS=X, REGION=0M, COND=(0,LT)
//*-----*
//* FILL THE SVM VSAM CLUSTER *
//*-----*
//IMPORT EXEC PGM=IDCAMS
//RECORDS DD DISP=SHR, DSN=EXP.SVM.TARGET.SEQ.RECORDS
//SVM DD DISP=SHR, DSN=EXP.SVM.KSDS
//SYSPRINT DD SYSOUT=*
//SYSIN DD *
  REPRO -
  REPLACE -
  INFILE(RECORDS) -
  OUTFILE(SVM)
```



Note: If you omit the keyword `REPLACE` or define `NOREPLACE` in the `SYSIN` data stream of `IDCAMS` instead, existing server mapping information is not overwritten. This protects server-side mapping records from being overwritten by duplicates.

Undeploying Server-side Mapping Files from the RPC Server

Use the Server Mapping Deployment Wizard to undeploy a server-side mapping file (Workbench file with extension `.svm`). See *Server Mapping Files for COBOL*.

➤ To undeploy a server-side mapping file with the Server Mapping Deployment Wizard

- 1 Make sure your RPC server is active and that the Deployment Service of the RPC server is properly configured. See [Deployment Service](#).
- 2 Make sure your IDL file is within an EntireX Workbench directory (folder) without the related server-side mapping file (`.svm`).
- 3 From the context menu of your IDL file, choose **COBOL > Deploy/Synchronize Server Mapping** and call the Server Mapping Deployment Wizard. See *Server Mapping Deployment Wizard* in the EntireX Workbench documentation. Because there is no related server-side mapping file in the Workbench, all server mapping information related to the IDL file in the RPC server will be removed.

Change Management of Server-side Mapping Files

Under z/OS, change management for a VSAM file (server-side mapping container, see [Server-side Mapping Files in the RPC Server](#)) is similar to change management for a database. The complete VSAM file can be backed up at any time, for example by using IDCAMS. All updates to the VSAM file done after a backup must be kept.

All EntireX Workbench server-side mapping files (.svm) added since the last backup should be available. See *Server Mapping Files for COBOL* in the EntireX Workbench documentation.

List Deployed Server-side Mapping Files

Use IDCAMS to list the contents of the server-side mapping container. See [Server-side Mapping Files in the RPC Server](#).

```
//EXXPRINT JOB ( , , , 999 ), ENTIREX, NOTIFY=&SYSUID, MSGLEVEL=(1,1),
//          CLASS=K, MSGCLASS=X, REGION=0M
//*-----*
/* PRINT CONTENTS OF AN SVM VSAM CLUSTER          *
/*-----*
//SVMPRINT EXEC PGM=IDCAMS
//SYSPRINT DD SYSOUT=*
//IN      DD DISP=SHR, DSN=ETS.SVM.KSDS
//OUT     DD SYSOUT=*
//SYSIN   DD *
PRINT -
  INFILE(IN) -
  DUMP | HEX | CHAR -
  OUTFILE(OUT)
/*
//
```

Use `DUMP` or `CHAR` format to print the server-side mapping records of the VSAM file.

Check if a Server-side Mapping File Revision has been Deployed

Server-side mapping records in the server-side mapping container correspond to lines of EntireX Workbench files with extension .svm. See *Server Mapping Files for COBOL* in the EntireX Workbench documentation. The records contain a creation timestamp at offset 276 (decimal) in the format *YYYYMMDDHHIISST*. Precision is 1/10 of a second. The creation timestamp can be checked.

The timestamp can be found on the same offset in the records in the server-side mapping container (VSAM file). See *Server-side Mapping Files in the RPC Server*.

Access Control: Secure Server Mapping File Deployment

For deployment with the *Server Mapping Deployment Wizard*, use EntireX Security if the broker is running on platforms z/OS, UNIX, Windows or z/VSE. See *Enabling the Deployment Service*.

For IBM deployment tool IDCAMS, use RACF to secure deployment.

Ensure that Deployed Server-side Mapping Files are not Overwritten

For IDCAMS, use the `NOREPLACE` option to disallow overwriting of duplicate server-side mapping records in the server-side mapping container (VSAM file); see *Server-side Mapping Files in the RPC Server*. See also *Deploying Server-side Mapping Files to the RPC Server*.

Is There a Way to Smoothly Introduce Server-side Mapping Files?

All EntireX RPC servers can be executed without server-side mapping files. See *Server-side Mapping Files in the RPC Server*. There is no need to install the server-side mapping container if the following conditions are met:

- You do not use features that require server mapping; see *When is a Server Mapping File Required?*
- Server-side type of COBOL mapping is switched on in the EntireX Workbench. If you have not used server-side mapping, we recommend you use client-side mapping. See *Server Mapping Files for COBOL*.

You can also call COBOL servers generated or extracted with previous versions of EntireX mixed with a COBOL server that requires server-side mapping. All EntireX RPC servers are backward compatible.

7 Scenarios and Programmer Information

▪ COBOL Scenarios	56
▪ PL/I Scenarios	57
▪ Aborting RPC Server Customer Code and Returning Error to RPC Client	58
▪ Automatic Syncpoint Handling	63
▪ RPC Server Support of CICS with Large Buffer Interface	63

COBOL Scenarios

- [Scenario I: Calling an Existing COBOL Server](#)
- [Scenario II: Writing a New COBOL Server](#)

Scenario I: Calling an Existing COBOL Server

➤ To call an existing COBOL server

- 1 Use the IDL Extractor for COBOL to extract the Software AG IDL and, depending on the complexity, also a server mapping file. See *When is a Server Mapping File Required?* in the EntireX Workbench documentation.
- 2 Build an EntireX RPC client using any EntireX wrapper. For a quick test you can:
 - use the IDL Tester; see *EntireX IDL Tester* in the EntireX Workbench documentation
 - generate an XML mapping file (XMM) and use the XML Tester for verification; see *EntireX XML Tester* in the XML/SOAP Wrapper documentation

See *Client and Server Examples for z/OS CICS* in the COBOL Wrapper documentation for COBOL RPC Server examples.

Scenario II: Writing a New COBOL Server

➤ To write a new COBOL server

- 1 Use the COBOL Wrapper to generate a COBOL server skeleton and, depending on the complexity, also a server mapping file. See *When is a Server Mapping File Required?* in the EntireX Workbench documentation. Write your COBOL server and proceed as described under *Using the COBOL Wrapper for the Server Side*.
- 2 Build an EntireX RPC client using any EntireX wrapper. For a quick test you can:
 - use the IDL Tester; see *EntireX IDL Tester* in the EntireX Workbench documentation
 - generate an XML mapping file (XMM) and use the XML Tester for verification; see *EntireX XML Tester* in the XML/SOAP Wrapper documentation

See *Client and Server Examples for z/OS CICS* in the COBOL Wrapper documentation for COBOL RPC Server examples.

PL/I Scenarios

- [Scenario III: Calling an Existing PL/I Server](#)
- [Scenario IV: Writing a New PL/I Server](#)

Scenario III: Calling an Existing PL/I Server

➤ **To call an existing PL/I server**

- 1 Use the IDL Extractor for PL/I to extract the Software AG IDL.
- 2 Build an EntireX RPC client using any EntireX wrapper. For a quick test you can:
 - use the IDL Tester; see *EntireX IDL Tester* in the EntireX Workbench documentation
 - generate an XML mapping file (XMM) and use the XML Tester for verification; see *EntireX XML Tester* in the XML/SOAP Wrapper documentation

See *Client and Server Examples for z/OS CICS* in the PL/I Wrapper documentation for PL/I RPC Server examples.

Scenario IV: Writing a New PL/I Server

➤ **To write a new PL/I server**

- 1 Use the PL/I Wrapper to generate a PL/I server skeleton. Write your PL/I server and proceed as described under *Using the PL/I Wrapper for the Server Side*.
- 2 Build an EntireX RPC client using any EntireX wrapper. For a quick test you can:
 - use the IDL Tester; see *EntireX IDL Tester* in the EntireX Workbench documentation
 - generate an XML mapping file (XMM) and use the XML Tester for verification; see *EntireX XML Tester* in the XML/SOAP Wrapper documentation

See *Client and Server Examples for z/OS CICS* in the PL/I Wrapper documentation for PL/I RPC Server examples.

Aborting RPC Server Customer Code and Returning Error to RPC Client

This section covers the following topics:

- [Using EXEC CICS ABEND ABCODE](#)
- [Using EXEC CICS ABEND CANCEL](#)
- [Using RETURN-CODE Special Register \(COBOL only\)](#)

Using EXEC CICS ABEND ABCODE

This approach applies to all CICS scenarios (all programming languages and all interface types); see [Supported Interface Types](#).

The CICS feature `EXEC CICS ABEND ABCODE(myabend)` may be used to indicate application error codes. According to IBM CICS standards, ABEND codes starting with the letter A are reserved for CICS itself and should not be used in your RPC server.

The RPC Server for CICS follows these IBM CICS standards and sends back the RPC protocol message

1. 10010018 Abnormal termination during program execution. This is returned when an ABEND code starting with the letter "A" is received from CICS, which is a CICS ABEND.
2. 10010045 CICS ABEND *myabend* was issued. This is returned when an ABEND code starting with a letter other than "A" is received from CICS, which is an application error situation forced by your RPC server.

Using EXEC CICS ABEND CANCEL

This approach applies to all CICS scenarios (all programming languages and all interface types) if impersonation is used (YES|AUTO). See [Supported Interface Types](#) and [Impersonation](#). If impersonation is not set, `EXEC CICS ABEND CANCEL` cannot be used.


If the customer server code uses the CICS feature `EXEC CICS ABEND CANCEL` to abort for particular error situations, the RPC server cannot trap the abort and is not able to send back an error to the RPC client. The RPC client gets a Broker timeout without any further information about the RPC server abort. In this case, to notify the RPC client you need to call `RPCUEX01` (immediately before `CICS ABEND CANCEL`) in the customer server code to inform the RPC Server for CICS that your program is about to abort with `CICS ABEND CANCEL`. EntireX does not recommend using `EXEC CICS ABEND CANCEL`. However, if you do need to call an existing COBOL program with `EXEC CICS ABEND CANCEL`, this can be done if the `RPCUEX01` call is added. Whenever possible use `EXEC CICS ABEND ABCODE` instead. See [Using EXEC CICS ABEND ABCODE](#).

- [Process Flow](#)
- [Usage](#)

- Installation

Process Flow

The server invokes the server program using `CICS LINK PROGRAM` and expects that the program returns with `CICS RETURN`. However, if the program uses `CICS ABEND CANCEL` to abort for particular error situations, the RPC server cannot trap the abort. If your server program uses `CICS ABEND CANCEL` you need to call the delivered `RPCUEX01` to inform the server that your program is about to abort with `CICS ABEND CANCEL`.



- 1 The customer server program is invoked within the user task.
- 2 The customer server program decides to abort using `CICS ABEND CANCEL`. Immediately before calling `CICS ABEND CANCEL` it calls the `RPCUEX01`. After returning from `RPCUEX01` it performs `CICS ABEND CANCEL` to abort. The `CICS ABEND CANCEL` terminates the user task.
- 3 `RPCUEX01` posts the worker task and informs it about the abort of its associated user task. The worker task sends back the abort information to the RPC client.

Usage

The server program calls `RPCUEX01` with:

```
EXEC CICS LINK PROGRAM('RPCUEX01')
      COMMAREA(rpcuex01-commarea)
```

After execution, the server program is responsible for aborting the task. If the server program ends without terminating the task, unpredictable results may occur.

Layout of `rpcuex01-commarea`:

- **Return code**

4-byte integer value. Value of -1 indicates failure.

- **Error text**

128-byte text field containing the error description.

If the call of `RPCUEX01` fails, the user program must not abort the task.

COBOL example for calling `RPCUEX01`:

```
01 UEX01-AREA.
   05 RETCODE          PIC S9(9) BINARY.
   05 ERRORTXT         PIC X(128).
...
   MOVE -1 TO RETCODE
   MOVE 'ERX: No Commarea access' TO ERRORTXT
   EXEC CICS LINK PROGRAM('RPCUEX01')
         COMMAREA(UEX01-AREA)
         RESP(RESP)
         RESP2(RESP2)
         END-EXEC
   IF RESP NOT = 0
       DISPLAY 'Error invoking RPCUEX01:'
       GO TO MAIN-EXIT
   END-IF
   IF RETCODE IS < 0
       DISPLAY 'Error from RPCUEX01:'
           ' ERRTXT = ' ERRORTXT
       GO TO MAIN-EXIT
   END-IF
* Now cancel the task...
EXEC CICS ABEND CANCEL END-EXEC
```

Installation

The program `RPCUEX01` must reside in the CICS load library concatenation. The following PPT entry is required:

```
DEFINE PROGRAM(RPCUEX01) GROUP(EXX)
  DESCRIPTION(RPC user exit to abort RPC programs)
  LANGUAGE(C)
```

Using RETURN-CODE Special Register (COBOL only)

This approach applies to the following CICS scenarios:

- *CICS with DFHCOMMAREA Calling Convention (COBOL Wrapper | Extractor)*
- *CICS with DFHCOMMAREA Large Buffer Interface (COBOL Wrapper | Extractor)*

CICS applications that use the DFHCOMMAREA as communication area (`EXEC CICS LINK` applications) may return error codes if the LINKed application has a C main entry and if this application is running in the same CICS (non-DPL program) as the RPC Server for CICS. Under these circumstances, IBM's Language Environment for C provides the application return code to `EIBRESP2`, where it can be detected by the RPC Server for CICS.

The following provided modules need to be linked to your application.

- `ERXRCSR`, a C main module that calls the intermediate COBOL subroutine `RCCALL` and catches the error from your RPC server and provides it to the RPC Server for CICS. This module is available as source in the source data set `EXP101.SRCE` as well as precompiled in the load data set `EXP101.LD00`, so a C compiler is not needed.
- `RCCALL`, a COBOL subroutine calling your RPC server. This module is available as source in the CICS example server data set `EXP101.DVCO`.

A step-by-step description is given below, but for ease of use we recommend using the job `RCIGY`. See below.

➤ To set up your server to be able to return application errors manually

- 1 Change the `CALL` statement of the `RCCALL` program below which your RPC server is called instead of "MyCobol" below

```

IDENTIFICATION DIVISION.
PROGRAM-ID.      RCCALL.

*****
*
* CICS RPC Server
*
* Returning Application Errors from RPC Server to RPC Client
*
* This program calls your target COBOL Server.
*
* For further information and explanation refer to
* - "Writing Applications with the COBOL Wrapper"
* in the delivered documentation.
*
* $Revision: n.n $
*
* Copyright (C) 1997 - 20nn Software AG, Darmstadt, Germany
* and/or Software AG USA, Inc., Reston, VA, United States of
* America, and/or their licensors.
*
*****

ENVIRONMENT DIVISION.

DATA DIVISION.
WORKING-STORAGE SECTION.

LINKAGE SECTION.

01 DFHCOMMAREA.
   10 DFHCOMM-DUMMY          PIC X.

PROCEDURE DIVISION USING DFHCOMMAREA.

MAIN SECTION.
   CALL "my-cobol" USING DFHEIBLK DFHCOMMAREA.

MAIN-EXIT.
   EXIT PROGRAM.

END PROGRAM RCCALL.

```

- 2 In your RPC server, do not use EXEC CICS RETURN, because this prevents the return of the application error code to the RPC Server for CICS. If you are using a COBOL RPC server generated with the COBOL Wrapper, comment out or remove this line.
- 3 Compile the RCCALL program with a COBOL compiler supported by the COBOL Wrapper.

- 4 Link the compiled `RCCALL` program, the delivered `ERXRCSR` module and your RPC server together to a CICS program to be called by the RPC Server for CICS. See also *Using the COBOL Wrapper for the Server Side* for supported CICS scenarios.

➤ **To set up your server to be able to return application errors using job `RCIGY`**

- Execute `RCIGY` as provided in the CICS example source data set `EXP101.DVCO`.

This enhanced job will

1. modify `RCCALL` as needed (step 1 from the manual approach, see above),
2. add the modified `RCCALL` code to your COBOL input source (step 2 from the manual approach, see above),
3. link edit with `ERXRCSR` (step 3 from the manual approach, see above).

Automatic Syncpoint Handling

The RPC Server for CICS issues a `SYNCPPOINT` command under the following circumstances:

- If you are running under CICS *without Impersonation*, the server issues a `SYNCPPOINT COMMIT` command after a successful non-conversational request or an end-of-conversation. This can be disabled with the `SYNC` parameter.
- If you are running under CICS *with Impersonation*, this `SYNCPPOINT` command is not executed by the server, but by CICS when the user task is terminated.
- After abnormal termination of a non-conversational request or a conversation due to an error, the server performs a `SYNCPPOINT ROLLBACK` command to back out any pending database modifications.

RPC Server Support of CICS with Large Buffer Interface

This RPC Server for CICS supports the Large Buffer interface with the following methods:

- [In Same as Out](#)

- In Different to Out

In Same as Out

In this scenario, the input buffer is same as the output buffer. Normally the server application data has only one interface structure that is used for input as well as output.

```
LINKAGE SECTION.

01 DFHCOMMAREA.
  10 WM-LCB-MARKER          PIC X(4).
  10 WM-LCB-INPUT-BUFFER   POINTER.
  10 WM-LCB-INPUT-BUFFER-SIZE PIC S9(8) BINARY.
  10 WM-LCB-OUTPUT-BUFFER  POINTER.
  10 WM-LCB-OUTPUT-BUFFER-SIZE PIC S9(8) BINARY.
  10 WM-LCB-FLAGS          PIC X(1).
  88 WM-LCB-FREE-OUTPUT-BUFFER VALUE 'F'.
  10 WM-LCB-RESERVED       PIC X(3).
01 INOUT-BUFFER.
  02 OPERATION             PIC X(1).
  02 OPERAND-1             PIC S9(9) BINARY.
  02 OPERAND-2             PIC S9(9) BINARY.
  02 FUNCTION-RESULT       PIC S9(9) BINARY.
. . .
PROCEDURE DIVISION USING DFHCOMMAREA.
. . .
  SET ADDRESS OF INOUT-BUFFER TO WM-LCB-INPUT-BUFFER.
```

Variable	Description
WM-LCM-MARKER	Has eye-catcher "XXXX".
WM-LCB-INPUT-BUFFER	Has pointer to server application data.
WM-LCB-INPUT-BUFFER-SIZE	Contains size of application data.
WM-LCB-OUTPUT-BUFFER	Same as WM-LCB-INPUT-BUFFER.
WM-LCB-OUTPUT-BUFFER-SIZE	Same as WM-LCB-INPUT-BUFFER-SIZE.

WM-LCB-OUTPUT-BUFFER, WM-LCB-OUTPUT-BUFFER-SIZE and WM-LCB-FREE-OUTPUT-BUFFER are normally not used in this scenario. Nevertheless, if WM-LCB-FREE-OUTPUT-BUFFER and WM-LCB-OUTPUT-BUFFER are changed, the RPC server will use the reply data from this WM-LCB-OUTPUT-BUFFER. Afterwards this buffer will be freed (EXEC CICS FREEMAIN).

In Different to Out

In this scenario, the input buffer is different to the output buffer. Normally the server application data has at least two application structures: one for the input, the other for the output.

```
LINKAGE SECTION.
01 DFHCOMMAREA.
  10 WM-LCB-MARKER          PIC X(4).
  10 WM-LCB-INPUT-BUFFER   POINTER.
  10 WM-LCB-INPUT-BUFFER-SIZE PIC S9(8) BINARY.
  10 WM-LCB-OUTPUT-BUFFER  POINTER.
  10 WM-LCB-OUTPUT-BUFFER-SIZE PIC S9(8) BINARY.
  10 WM-LCB-FLAGS          PIC X(1).
    88 WM-LCB-FREE-OUTPUT-BUFFER VALUE 'F'.
  10 WM-LCB-RESERVED       PIC X(3).
01 IN-BUFFER.
  02 OPERATION             PIC X(1).
  02 OPERAND-1             PIC S9(9) BINARY.
  02 OPERAND-2             PIC S9(9) BINARY.
01 OUT-BUFFER.
  02 FUNCTION-RESULT      PIC S9(9) BINARY.
. . .
PROCEDURE DIVISION USING DFHCOMMAREA.
. . .
  SET ADDRESS OF IN-BUFFER TO WM-LCB-INPUT-BUFFER.
  SET ADDRESS OF OUT-BUFFER TO WM-LCB-OUTPUT-BUFFER.
```

Variable	Description
WM-LCM-MARKER	Has eye-catcher "XXXX".
WM-LCB-INPUT-BUFFER	Has pointer to server input application data.
WM-LCB-INPUT-BUFFER-SIZE	Contains size of input application data.
WM-LCB-OUTPUT-BUFFER	Has buffer for server output application data.
WM-LCB-OUTPUT-BUFFER-SIZE	Size of WM-LCB-OUTPUT-BUFFER.

Normally, the output data can be written to the WM-LCB-OUTPUT-BUFFER provided. Nevertheless, if WM-LCB-FREE-OUTPUT-BUFFER and WM-LCB-OUTPUT-BUFFER are changed, the RPC server will use the reply data from this WM-LCB-OUTPUT-BUFFER. Afterwards this buffer will be freed (EXEC CICS FREEMAIN).

