

webMethods EntireX

RPC-ACI Bridge

Innovation Release

Version 9.9

October 2015

This document applies to webMethods EntireX Version 9.9 and all subsequent releases.

Specifications contained herein are subject to change and these changes will be reported in subsequent release notes or new editions.

Copyright © 1997-2015 Software AG, Darmstadt, Germany and/or Software AG USA, Inc., Reston, VA, USA, and/or its subsidiaries and/or its affiliates and/or their licensors.

The name Software AG and all Software AG product names are either trademarks or registered trademarks of Software AG and/or Software AG USA, Inc. and/or its subsidiaries and/or its affiliates and/or their licensors. Other company and product names mentioned herein may be trademarks of their respective owners.

Detailed information on trademarks and patents owned by Software AG and/or its subsidiaries is located at <http://softwareag.com/licenses>.

Use of this software is subject to adherence to Software AG's licensing conditions and terms. These terms are part of the product documentation, located at <http://softwareag.com/licenses/> and/or in the root installation directory of the licensed product(s).

This software may include portions of third-party products. For third-party copyright notices, license terms, additional rights or restrictions, please refer to "License Texts, Copyright Notices and Disclaimers of Third-Party Products". For certain specific third-party license restrictions, please refer to section E of the Legal Notices available under "License Terms and Conditions for Use of Software AG Products / Copyright and Trademark Notices of Software AG Products". These documents are part of the product documentation, located at <http://softwareag.com/licenses> and/or in the root installation directory of the licensed product(s).

Use, reproduction, transfer, publication or disclosure is prohibited except as specifically provided for in your License Agreement with Software AG.

Document ID: EXX-ACI-99-20171128BRIDGE

Table of Contents


EntireX RPC-ACI Bridge	v
1 Introduction to the EntireX RPC-ACI Bridge	1
2 Administering EntireX RPC-ACI Bridge	3
Customizing the RPC-ACI Bridge	4
Configuring the RPC Server Side	6
Configuring the ACI Client Side	9
Starting the RPC-ACI Bridge	10
Stopping the RPC-ACI Bridge	11
Using SSL/TLS	11
Application Identification	13
3 Writing ACI Servers for the RPC-ACI Bridge in COBOL	15
Tasks	16
Data Types	17
Declaring the Variables for the Data Types	18
4 Writing ACI Servers for the RPC-ACI Bridge in Natural	21
Tasks	22
Data Types	23
Declaring the Variables for the Data Types	24
5 Writing RPC Clients for the RPC-ACI Bridge with the C Wrapper	27
6 Writing RPC Clients for the RPC-ACI Bridge in Java	29

EntireX RPC-ACI Bridge

- Introduction*** The RPC-ACI Bridge enables RPC-based client applications to be used with ACI servers.
- Administration*** Customizing the RPC-ACI Bridge; configuring the RPC server side and ACI client side.
- Writing ACI Servers in COBOL*** Overview of tasks and supported data types when writing server applications in COBOL for the RPC-ACI Bridge.
- Writing ACI Servers in Natural*** Overview of tasks and supported data types when writing server applications in Natural for the RPC-ACI Bridge.

1 Introduction to the EntireX RPC-ACI Bridge

The EntireX RPC-ACI Bridge allows standard RPC clients to communicate with an ACI server. The RPC-ACI Bridge transforms the RPCs from the clients into ACI messages. The RPC-ACI Bridge acts on one side as an RPC server and on the other side as an ACI client. In this documentation we distinguish between the Broker for RPC, which sends the RPCs from the client to the server side of the RPC-ACI Bridge and the Broker for ACI, which sends the messages to the ACI server. These two brokers can be the same instance. Use distinct services for the RPCs and ACI.



The RPC-ACI Bridge can connect to ACI servers in any language. We describe the use of Natural and COBOL ACI servers. For existing COBOL programs you can use the COBOL IDL Generator to generate the IDL file for the RPC clients.

The RPC-ACI Bridge supports RPC clients in different programming languages.

2 Administering EntireX RPC-ACI Bridge

▪ Customizing the RPC-ACI Bridge	4
▪ Configuring the RPC Server Side	6
▪ Configuring the ACI Client Side	9
▪ Starting the RPC-ACI Bridge	10
▪ Stopping the RPC-ACI Bridge	11
▪ Using SSL/TLS	11
▪ Application Identification	13

The RPC-ACI Bridge enables RPC-based client applications to be used with ACI servers.

Customizing the RPC-ACI Bridge

For the setup of the RPC-ACI Bridge there are

- a configuration file and
- scripts to start the RPC-ACI Bridge.

Location of the RPC-ACI Bridge


The RPC-ACI Bridge is contained in the file *entirex.jar*.

The Configuration File

The default name of the configuration file is *entirex.rpcacibrIDGE.properties*. The RPC-ACI Bridge searches for this file in the current working directory.

You can set the name of the configuration file with `-Dentirex.server.properties=<your file name>` with `"/"` as file separator.

The configuration file contains the configuration for both parts of the RPC-ACI Bridge.



➤ To set up the RPC-ACI Bridge

- 1 Use the RPC server agent of the System Management Hub.
- 2 Add the RPC-ACI Bridge as an RPC server.

See *Administering the EntireX RPC Servers using System Management Hub* in the UNIX and Windows administration documentation for details.

Or:

Use the scripts to start the RPC-ACI Bridge.

Under Windows use *jrpcacibridge.bat* in the folder *bin* to start the RPC-ACI Bridge. You may customize this file.

Under UNIX use *jrpcacibridge.bsh* in the folder *bin* to start the RPC-ACI Bridge. You may customize this file.

Both scripts use the configuration file *entirex.rpcacibridge.properties* in the folder *etc*.

Configuring more than one RPC-ACI Bridge

If you configure more than one RPC-ACI Bridge that connect to the same EntireX Broker, the following items must be distinct:

- The user for the ACI client side (property `entirex.rpcacibridge.userid`).
- The trace output file (property `entirex.server.logfile`).
- The monitor port for SMH (property `entirex.server.monitorport`).
- The log for the Windows Service (property `entirex.server.serverlog`).
- The trace output file of the SMH agent for RPC servers.

Configuring the RPC Server Side

The RPC server side of the RPC-ACI Bridge is configured like the Java RPC Server. The RPC-ACI Bridge uses the properties that start with “entirex.server”.

The RPC server side can adjust the number of worker threads to the number of parallel requests. Use the properties `entirex.server.fixedservers`, `entirex.server.maxservers`, `entirex.server.minservers` to configure this scalability. If `entirex.server.fixedservers=yes`, the number of `entirex.server.minservers` is started and the server can process this number of parallel requests. If `entirex.server.fixedservers=no`, the number of worker threads balances between `entirex.server.minservers` and `entirex.server.maxservers`. This is done by a so-called attach server thread. On startup, the number of worker threads is `entirex.server.minservers`. If more than `entirex.server.minservers` are waiting for requests, a worker thread stops if its receive call times out. The timeout period is configured with `entirex.server.waitserver`.

Alternatively to the properties, you can use the command-line option. The command-line options have a higher priority than the properties set as Java system properties and these have higher priority than the properties in the configuration file.

Name	Command-line Option	Default Value	Explanation														
<code>entirex.server.brokerid</code>	<code>-broker</code>	<code>localhost : 1971</code>	Broker ID. See <i>URL-style Broker ID</i> .														
<code>entirex.server.codepage</code>	<code>-codepage</code>		The codepage the server uses. Permitted values are the name of the codepages the JVM supports. Use the value <code>LOCAL</code> when the default codepage of the JVM should be used. See <i>Internationalization with EntireX</i> for details.														
<code>entirex.server.compresslevel</code>	<code>-compresslevel</code>	0 (no compression)	<table border="1"> <tr> <td><code>BEST_COMPRESSION</code></td> <td>9</td> </tr> <tr> <td><code>BEST_SPEED</code></td> <td>1</td> </tr> <tr> <td><code>DEFAULT_COMPRESSION</code></td> <td>-1, mapped to 6</td> </tr> <tr> <td><code>DEFLATED</code></td> <td>8</td> </tr> <tr> <td><code>NO_COMPRESSION</code></td> <td>0</td> </tr> <tr> <td><code>N</code></td> <td>0</td> </tr> <tr> <td><code>Y</code></td> <td>8</td> </tr> </table>	<code>BEST_COMPRESSION</code>	9	<code>BEST_SPEED</code>	1	<code>DEFAULT_COMPRESSION</code>	-1, mapped to 6	<code>DEFLATED</code>	8	<code>NO_COMPRESSION</code>	0	<code>N</code>	0	<code>Y</code>	8
<code>BEST_COMPRESSION</code>	9																
<code>BEST_SPEED</code>	1																
<code>DEFAULT_COMPRESSION</code>	-1, mapped to 6																
<code>DEFLATED</code>	8																
<code>NO_COMPRESSION</code>	0																
<code>N</code>	0																
<code>Y</code>	8																
<code>entirex.server.encryptionlevel</code>	<code>-encryption</code>	0	Deprecated. For encrypted transport we strongly recommend using the Secure Sockets Layer/Transport Layer Security														

Name	Command-line Option	Default Value	Explanation
			protocol. See <i>SSL/TLS and Certificate</i> in the <i>EntireX</i> documentation.
entirex.server.environment			Can be used in a user-written trace listener at the exit of the broker. See BrokerService, setEnvironment(java.lang.String) in the Javadoc documentation of the Java ACI.
entirex.server.fixedservers		no	If "no", use an attach server thread to manage worker threads, otherwise use a fixed number of server threads. Minimum number of server threads is defined by the properties entirex.server.maxservers and entirex.server.minservers.
entirex.server.logfile	-logfile		Path and name of the trace output file.
entirex.server.maxservers		32	Maximum number of worker threads.
entirex.server.minservers		1	Minimum number of server threads.
entirex.server.monitorport	-smhport	0	The port where the server listens for commands from the System Management Hub (SMH). If this port is 0, no port is used and the management by the SMH is disabled.
entirex.server.name			The name of the server.
entirex.server.password	-password		The password for secured access to the Broker. The password is encrypted and written to the property entirex.server.password.encrypt. To change the password, set the password in the properties file (entirex.rpcacibridge.properties). To disable password encryption, set the property entirex.server.passwordencrypt to "no". Default for this property is "yes".
entirex.server.properties	-propertyfile	entirex.rpcacibridge.properties	The file name of the property file.
entirex.server.restartcycles	-restartcycles	15	Number of restart attempts if the broker is not available. This can be used to restart the Java RPC Server running while the broker is down for a short time.
entirex.server.security	-security	no	no/yes/auto/Name of BrokerSecurity

Name	Command-line Option	Default Value	Explanation
entirex.server.serveraddress	-server	RPC/SRV1/CALLNAT	Server address
entirex.server.serverlog	-serverlog		Name of the file where start and stop of worker threads is logged. Used by the Windows RPC Service.
entirex.server.userid	-user	JavaServer	The user ID of the Broker for RPC. See <code>entirex.server.password</code> .
entirex.server.verbose	-verbose	no	Verbose output to standard output yes/no
entirex.server.waitattach		600S	Wait timeout for the attach server thread
entirex.server.waitserver		300S	Wait timeout for the worker threads.
entirex.timeout		20	TCP/IP transport timeout. See <i>Setting the Transport Timeout</i> under <i>Writing Advanced Applications - EntireX Java ACI</i> .
entirex.trace	-trace	0	Trace level (1,2,3).

Configuring the ACI Client Side

These properties are used to configure the connection to the Broker for ACI.

Alternatively, you can use the command-line option. The command-line options have a higher priority than the properties set as Java system properties and these have higher priority than the properties in the configuration file

Name	Command-line Option	Default Value	Explanation												
entirex.rpcacibridge.brokerid	-acibroker	localhost	Broker ID of the Broker for ACI. See <i>URL-style Broker ID</i> .												
entirex.rpcacibridge.compresslevel	-acicompresslevel	0 (no compression)	<p>Permitted values (you can enter the text or the numeric value):</p> <table border="1"> <tr> <td>BEST_COMPRESSION</td> <td>9</td> </tr> <tr> <td>BEST_SPEED</td> <td>1</td> </tr> <tr> <td>DEFAULT_COMPRESSION</td> <td>-1, mapped to 6</td> </tr> <tr> <td>DEFLATED</td> <td>8</td> </tr> <tr> <td>NO_COMPRESSION</td> <td>0</td> </tr> <tr> <td>Y</td> <td>8</td> </tr> </table>	BEST_COMPRESSION	9	BEST_SPEED	1	DEFAULT_COMPRESSION	-1, mapped to 6	DEFLATED	8	NO_COMPRESSION	0	Y	8
BEST_COMPRESSION	9														
BEST_SPEED	1														
DEFAULT_COMPRESSION	-1, mapped to 6														
DEFLATED	8														
NO_COMPRESSION	0														
Y	8														
entirex.rpcacibridge.encryptionlevel	-aciencryption	0	Deprecated. For encrypted transport we strongly recommend using the Secure Sockets Layer/Transport Layer Security protocol. See <i>SSL/TLS and Certificates with EntireX</i> .												
entirex.rpcacibridge.marshalling	-acimarshalling		This is for arrays of groups. Set this property to "cobol" if the ACI server is a COBOL program. Set this property to "natural" if the ACI server is a Natural program. Default is "", which lets the RPC client determine the marshalling.												
entirex.rpcacibridge.password	-acipassword		The password of the Broker for ACI. The password is encrypted and written to the property entirex.server.password.e. To change the password, set the new password in the properties file (default is <i>entirex.rpcacibridge.properties</i>). To disable password encryption set <code>entirex.server.passwordencrypt=no</code> . Default for this property is "yes".												

Name	Command-line Option	Default Value	Explanation
entirex.rpcacibridge.security	-acisecurity	no	no/yes/auto/Name of BrokerSecurity object.
entirex.rpcacibridge.serveraddress	-aciserver	AClass/AServer/ASERVICE	Server Address for the Broker for ACI.
entirex.rpcacibridge.trace	-acitrace	No	If set to "yes", additional trace output (exception stack-traces and request and reply buffers) is generated.
entirex.rpcacibridge.userid	-aciuser	Value of system property user.name	The user ID of the Broker for ACI. Use different user IDs for different RPC-ACI Bridges on the same Broker.
entirex.rpcacibridge.waittime		0S	The wait time for receive requests. Permitted values are $nS nM nH$, where n is the number of seconds or minutes or hours.

Starting the RPC-ACI Bridge

➤ To start the RPC-ACI Bridge

- Use the script `jrpcacibridge` in the folder `bin` to start the RPC-ACI Bridge. You may customize this file.

Or:

Use the RPC server agent in the System Management Hub to configure and start the RPC-ACI Bridge.

See *Administering the EntireX RPC Servers using System Management Hub* in the UNIX and Windows administration documentation for details.

On Windows you can start the RPC-ACI Bridge as a Windows Service. The installation of the service is similar to the installation of the Java RPC Server. See *Running the Java RPC Server as a Windows Service* under *Administering the EntireX Java RPC Server* in the Windows administration documentation in the Windows administration documentation.

Stopping the RPC-ACI Bridge

➤ To stop the RPC-ACI Bridge

- Use the RPC server agent in the SMH to stop the RPC-ACI Bridge.

Or:

Use the agent for the Broker. Use `Deregister` on the service, specified with the property `entirex.server.serveraddress`.

Using SSL/TLS

To use SSL with RPC-ACI Bridge, you need to configure two sides, the RPC server side and the ACI client side.

- **For the ACI client side**

ACI applications can use Secure Sockets Layer/Transport Layer Security (SSL/TLS) as the transport medium. The term “SSL” in this section refers to both SSL and TLS. ACI-based clients or servers are always SSL clients. The SSL server can be either the EntireX Broker or the Broker SSL Agent. For an introduction see *SSL/TLS and Certificates* in the Security documentation.

- **For the RPC server side**

The same is true for the RPC server side. Additionally, Direct RPC in webMethods Integration Server (IS inbound) can be used as the SSL server.

➤ To set up SSL

- 1 To operate with SSL, certificates need to be provided and maintained. Depending on the platform, Software AG provides default certificates, but we strongly recommend that you create your own. See *Default Certificates Delivered with EntireX*.
- 2 Set up the ACI side and RPC side for an SSL connection.

For both sides, use the *URL-style Broker ID* with protocol `ssl://` for the Broker ID. If no port number is specified, port 1958 is used as default. Example:

```
ssl://localhost:22101?trust_store=C:\SoftwareAG\EntireX\etc\ExxCACert.jks&verify_server=no
```

If the SSL client checks the validity of the SSL server only, this is known as *one-way SSL*. The mandatory `trust_store` parameter specifies the file name of a keystore that must contain the list of trusted certificate authorities for the certificate of the SSL server. By default a check is made that the certificate of the SSL server is issued for the hostname specified in the Broker ID. The common name of the subject entry in the server's certificate is checked against the hostname. If they do not match, the connection will be refused. You can disable this check with SSL parameter `verify_server=no`.

If the SSL server additionally checks the identity of the SSL client, this is known as *two-way SSL*. In this case the SSL server requests a client certificate (the parameter `verify_client=yes` is defined in the configuration of the SSL server). Two additional SSL parameters must be specified on the SSL client side: `key_store` and `key_passwd`. This keystore must contain the private key of the SSL client. The password that protects the private key is specified with `key_passwd`.

The ampersand (&) character cannot appear in the password.

SSL parameters are separated by ampersand (&). See also *SSL/TLS Parameters for EntireX Clients and Servers*.

- 3 Make sure the SSL server to which the ACI side connects is prepared for SSL connections as well. The SSL server can be EntireX Broker or Broker SSL Agent. See:
 - *Running Broker with SSL/TLS Transport* in the platform-specific administration documentation
 - *Setting up and Administering the EntireX Broker SSL Agent* in the UNIX and Windows administration documentation

- 4 Make sure the SSL server to which the RPC side connects is prepared for SSL connections as well. The SSL server can be EntireX Broker, Broker SSL Agent, or Direct RPC in webMethods Integration Server (IS inbound). See:
 - *Running Broker with SSL/TLS Transport* in the platform-specific administration documentation
 - *Setting up and Administering the EntireX Broker SSL Agent* in the UNIX and Windows administration documentation
 - *Support for SSL/TLS* in the EntireX Adapter documentation (for Direct RPC)

Application Identification

The application identification is sent from the RPC-ACI Bridge to the Broker. It is visible with Broker Command and Info Services.

The identification consists of four parts: name, node, type, and version. These four parts are sent with each Broker call and are visible in the trace information.

For the RPC-ACI Bridge these values are:

Application name:	ANAME=RPC-ACI Bridge
Node name:	ANODE=< <i>host name</i> >
Application type:	ATYPE=Java
Version:	AVERS=9.0.0.0

3 Writing ACI Servers for the RPC-ACI Bridge in COBOL

- Tasks 16
- Data Types 17
- Declaring the Variables for the Data Types 18

The RPC-ACI Bridge is prepared for ACI servers written in COBOL.

Tasks

Writing an ACI server consists of two tasks:

- implement the Broker calls
- implement the processing of the received buffer and the response for the send buffer

Using Arrays of Groups

If your programs use arrays of groups, you have to adjust the marshalling.

» To adjust the marshalling for arrays of groups

- 1 Use the property `entirex.rpcacibridge.marshalling` for the configuration.
- 2 Set the property to "cobol".

If your programs do not use arrays of groups, you do not need to set `entirex.rpcacibridge.marshalling`.

Data Types

Data Type	Description	Format	Note
<i>A</i> <i>number</i>	Alphanumeric	<i>number</i> bytes, encoding the characters.	
AV	Alphanumeric variable length	Bytes up to the end of the buffer.	1
AV[<i>number</i>]	Alphanumeric variable length with maximum length	Bytes up to the end of the buffer, maximal length <i>number</i> .	1
<i>K</i> <i>number</i>	Kanji	Same as data type A.	
KV	Kanji variable length	Same as data type AV.	1
KV[<i>number</i>]	Kanji variable length with maximum length	Same as data type AV[<i>number</i>].	1
I1	Integer (small)	<i>sign</i> (+, -) and 3 bytes (digits).	
I2	Integer (medium)	<i>sign</i> (+, -) and 5 bytes (digits).	
I4	Integer (large)	<i>sign</i> (+, -) and 10 bytes (digits).	
N <i>number1</i> [. <i>number2</i>]	Unpacked decimal	<i>sign</i> (+, -), <i>number1</i> bytes (digits) [<i>number2</i>] bytes (digits), no decimal point.	
NU <i>number1</i> [. <i>number2</i>]	Unpacked decimal unsigned	<i>number1</i> bytes (digits) [<i>number2</i>] bytes (digits), no decimal point.	
P <i>number1</i> [. <i>number2</i>]	Packed decimal	<i>sign</i> (+, -), <i>number1</i> bytes (digits) [<i>number2</i>] bytes (digits), no decimal point.	
PU <i>number1</i> [. <i>number2</i>]	Packed decimal unsigned	<i>number1</i> bytes (digits) [<i>number2</i>] bytes (digits), no decimal point.	
L	Logical	1 byte: X for true, all other false.	
D	Date	YYYYMMDD.	2
T	Time	YYYYMMDDhhmmss.S.	3



Notes:

1. Only as last value.
2. YYYY year, MM month, DD day.
3. YYYY year, MM month, DD day, hh hour, mm minute, ss second, S tenth of a second.

Data Types not supported:

- Binary (B[*n*], BV, BV[*n*])
- Floating point (F4, F8)

Declaring the Variables for the Data Types

This section describes how to declare the variables for the data types. Use these declarations to map the receive buffer and the send buffer to variables.

Data Type	Description	Declaration and Marshalling
<i>A</i> number	Alphanumeric	Declaration for receive and send buffer: PIC X(<i>n</i>)
AV	Alphanumeric variable length	Declaration for receive and send buffer: PIC X(<i>n</i>)
AV[<i>number</i>]	Alphanumeric variable length with maximum length	Declaration for receive and send buffer: PIC X(<i>n</i>)
<i>K</i> number	Kanji	Declaration for receive and send buffer: PIC X(<i>n</i>)
KV	Kanji variable length	Declaration for receive and send buffer: PIC X(<i>n</i>)
KV[<i>number</i>]	Kanji variable length with maximum length	Declaration for receive and send buffer: PIC X(<i>n</i>)
I1	Integer (small)	Declaration for receive and send buffer: PIC S9(3)
I2	Integer (medium)	Declaration for receive and send buffer: PIC S9(5)
I4	Integer (large)	Declaration for receive and send buffer: PIC S9(10)
<i>N</i> number1[. <i>number</i> 2]	Unpacked decimal	Declaration for receive and send buffer: PIC S9(<i>number</i> 1)V(<i>number</i> 2) SIGN LEADING SEPARATE
NU <i>number</i> 1[. <i>number</i> 2]	Unpacked decimal unsigned	Declaration for receive and send buffer: PIC 9(<i>number</i> 1)V(<i>number</i> 2)
<i>P</i> number1[. <i>number</i> 2]	Packed decimal	Declaration for receive and send buffer: PIC S9(<i>number</i> 1)V(<i>number</i> 2) SIGN LEADING SEPARATE Declare local variable PIC S9(<i>number</i> 1)V(<i>number</i> 2) PACKED DECIMAL Move from receive buffer to local variable before computation and from local variable to send buffer afterwards.
PU <i>number</i> 1[. <i>number</i> 2]	Packed decimal unsigned	Declaration for receive and send buffer: PIC 9(<i>number</i> 1)V(<i>number</i> 2) Declare local variable PIC 9(<i>number</i> 1)V(<i>number</i> 2)PACKED DECIMAL Move from receive buffer to local variable before computation and from local variable to send buffer afterwards.
L	Logical	Declaration for receive and send buffer: PIC X(1)
D	Date	Declaration for receive and send buffer: PIC X(8)

Data Type	Description	Declaration and Marshalling
T	Time	Declaration for receive and send buffer: PIC X(15)

4 Writing ACI Servers for the RPC-ACI Bridge in Natural

- Tasks 22
- Data Types 23
- Declaring the Variables for the Data Types 24

The RPC-ACI Bridge is prepared for ACI servers written in Natural.

Tasks

Writing an ACI server consists of two tasks:

- implement the Broker calls
- implement the processing of the received buffer and the response for the send buffer

Using Arrays of Groups

If your programs use arrays of groups, you have to adjust the marshalling.

» To adjust the marshalling for arrays of groups

- 1 Use the property `entirex.rpcacibridge.marshalling` for the configuration.
- 2 Set the property to "natural".

If your programs do not use arrays of groups, you do not need to set `entirex.rpcacibridge.marshalling`.

Data Types

Data Type	Description	Format	Note
<i>A</i> <i>number</i>	Alphanumeric	<i>number</i> bytes, encoding the characters.	
AV	Alphanumeric variable length	Bytes up to the end of the buffer.	1
AV[<i>number</i>]	Alphanumeric variable length with maximum length	Bytes up to the end of the buffer, maximal length <i>number</i> .	1
<i>K</i> <i>number</i>	Kanji	Same as data type A.	
KV	Kanji variable length	Same as data type AV.	1
KV[<i>number</i>]	Kanji variable length with maximum length	Same as data type AV[<i>number</i>].	1
I1	Integer (small)	<i>sign</i> (+, -) and 3 bytes (digits).	
I2	Integer (medium)	<i>sign</i> (+, -) and 5 bytes (digits).	
I4	Integer (large)	<i>sign</i> (+, -) and 10 bytes (digits).	
<i>N</i> <i>number1</i> [. <i>number2</i>]	Unpacked decimal	<i>sign</i> (+, -), <i>number1</i> bytes (digits) [<i>number2</i>] bytes (digits), no decimal point.	
<i>P</i> <i>number1</i> [. <i>number2</i>]	Packed decimal	<i>sign</i> (+, -), <i>number1</i> bytes (digits) [<i>number2</i>] bytes (digits), no decimal point.	
L	Logical	1 byte: X for true, all other false.	
D	Date	YYYYMMDD.	2
T	Time	YYYYMMDDhhmmss.S.	3



Notes:

1. Only as last value.
2. YYYY year, MM month, DD day.
3. YYYY year, MM month, DD day, hh hour, mm minute, ss second, S tenth of a second.

Data Types not supported:

- Binary (B[*n*], BV, BV[*n*])
- Floating point (F4, F8)

Declaring the Variables for the Data Types

This section describes how to declare the variables for the data types. Use these declarations to map the receive buffer and the send buffer to variables. For some data types, the values have to be moved to a local variable before computation.

Example:

```
* Declaration
DEFINE DATA LOCAL
1 PNUMERIC (A012)
1 #NUMERIC (N8.3)
1 REDEFINE #NUMERIC
2 #NUMERIC1 (N11)
* Computation
MOVE EDITED RCVE-DATA.PNUMERIC TO #NUMERIC1 (EM=S9(11))
#NUMERIC := #NUMERIC + 1
MOVE EDITED #NUMERIC1 (EM=S9(11)) TO SEND-DATA.PNUMERIC
```

Data Type	Description	Declaration and Marshalling
<i>A</i> number	Alphanumeric	Declaration for receive and send buffer: (A <i>n</i>)
AV	Alphanumeric variable length	Declaration for receive and send buffer: (A) DYNAMIC
AV[<i>number</i>]	Alphanumeric variable length with maximum length	Declaration for receive and send buffer: (A) DYNAMIC
<i>K</i> number	Kanji	Declaration for receive and send buffer: (A <i>n</i>)
KV	Kanji variable length	Declaration for receive and send buffer: (A) DYNAMIC
KV[<i>number</i>]	Kanji variable length with maximum length	Declaration for receive and send buffer: (A) DYNAMIC
I1	Integer (small)	Declaration for receive and send buffer: (A4)MOVE EDITED to I1 variable with (EM=S9(3))
I2	Integer (medium)	Declaration for receive and send buffer: (A6)MOVE EDITED to I2 variable with (EM=S9(5))
I4	Integer (large)	Declaration for receive and send buffer: (A11)MOVE EDITED to I4 variable with (EM=S9(10))
N <i>number1</i> [. <i>number2</i>]	Unpacked decimal	Declaration for receive and send buffer: (A <i>n</i>), where $n = \text{number1} + \text{number2} + 1$ (one byte for the sign). Redefine N <i>number1+number2</i> variable as N <i>number1.number2</i> variable. MOVE EDITED to N <i>number1+number2</i> variable with (EM=S9($\text{number1} + \text{number2}$))

Data Type	Description	Declaration and Marshalling
<i>Pnumber1</i> [. <i>number2</i>]	Packed decimal	Declaration for receive and send buffer: (<i>An</i>), where $n = \textit{number1} + \textit{number2} + 1$ (one byte for the sign). Redefine <i>Pnumber1+number2</i> variable as <i>Pnumber1.number2</i> variable. MOVE EDITED to <i>Pnumber1+number2</i> variable with (EM=S9(<i>number1</i> + <i>number2</i>))
L	Logical	Declaration for receive and send buffer: (A1)
D	Date	Declaration for receive and send buffer: (A8)MOVE EDITED to Date variable with (EM=YYYYMMDD)
T	Time	Declaration for receive and send buffer: (A15)MOVE EDITED to Time variable with (EM=YYYYMMDDHHIISST)

5 Writing RPC Clients for the RPC-ACI Bridge with the C Wrapper

The RPC-ACI Bridge enables RPC-based client applications to be used with ACI servers.

» To write a C client

- Follow the instructions under *Using the C Wrapper for the Client Side*.

The RPC-ACI Bridge reports errors from the RPC server side and the ACI side to the RPC clients. Errors from the ACI side include errors by the Broker for ACI.

The RPC-ACI Bridge reports the same error classes and error codes for the RPC server side as the Java RPC Server. The RPC-ACI Bridge reports errors of the ACI side in a client-specific way as error 10010007 (internal error of the RPC protocol). The detailed message of the error has the form `RPCACIBridge: < text >`, where *text* indicates the cause of the error. See *Message Class 1018 - EntireX RPC-ACI Bridge* under *Error Messages and Codes* for additional information.

6 Writing RPC Clients for the RPC-ACI Bridge in Java

The RPC-ACI Bridge enables RPC-based client applications to be used with ACI servers.

The EntireX RPC-ACI Bridge reports errors from the RPC server side and the ACI side to the RPC clients. Errors from the ACI side include errors by the Broker for ACI. The RPC-ACI Bridge reports the same error classes and error codes for the RPC server side as the XML/SOAP RPC Server. The RPC-ACI Bridge reports errors of the ACI side in a client-specific way as described below.

➤ To write a Java client

- 1 Generate the Java RPC client stub from the IDL file as described in *Using the Java Wrapper*.
- 2 Implement the client with this stub.

All errors are reported as `BrokerExceptions`. Errors on the ACI side of the RPC-ACI Bridge are `BrokerExceptions` in class 1018. See *Message Class 1018 - EntireX RPC-ACI Bridge* under *Error Messages and Codes*.

