

# **Adabas Manager**

## **Installation**

Version 8.6

October 2021

This document applies to Adabas Manager Version 8.6 and all subsequent releases.

Specifications contained herein are subject to change and these changes will be reported in subsequent release notes or new editions.

Copyright © 2014-2021 Software AG, Darmstadt, Germany and/or Software AG USA, Inc., Reston, VA, USA, and/or its subsidiaries and/or its affiliates and/or their licensors.

The name Software AG and all Software AG product names are either trademarks or registered trademarks of Software AG and/or Software AG USA, Inc. and/or its subsidiaries and/or its affiliates and/or their licensors. Other company and product names mentioned herein may be trademarks of their respective owners.

Detailed information on trademarks and patents owned by Software AG and/or its subsidiaries is located at <http://softwareag.com/licenses>.

Use of this software is subject to adherence to Software AG's licensing conditions and terms. These terms are part of the product documentation, located at <http://softwareag.com/licenses/> and/or in the root installation directory of the licensed product(s).

This software may include portions of third-party products. For third-party copyright notices, license terms, additional rights or restrictions, please refer to "License Texts, Copyright Notices and Disclaimers of Third-Party Products". For certain specific third-party license restrictions, please refer to section E of the Legal Notices available under "License Terms and Conditions for Use of Software AG Products / Copyright and Trademark Notices of Software AG Products". These documents are part of the product documentation, located at <http://softwareag.com/licenses> and/or in the root installation directory of the licensed product(s).

Use, reproduction, transfer, publication or disclosure is prohibited except as specifically provided for in your License Agreement with Software AG.

**Document ID: AMN-INSTALL-86-20210929**

## Table of Contents

Preface .....	v
1 About this Documentation .....	1
Document Conventions .....	2
Online Information and Support .....	2
Data Protection .....	3
2 System Requirements .....	5
Supported Operating System Platforms .....	6
Memory Space Requirements .....	6
Disk Space Requirements .....	6
Software Requirements .....	6
Supported Browsers .....	8
License File .....	8
3 Important Information .....	9
Administrator Status .....	10
Installation Directory .....	10
Side-by-Side Installations .....	10
Data Protection .....	11
Opening Ports for Remote Connections .....	12
AMNPAM Service for Linux Operating System User ID Login .....	12
Software AG Common Runtime .....	13
4 Installing Adabas Manager .....	15
5 Uninstalling Adabas Manager .....	17
6 Migrating from System Management Hub (SMH) to Adabas Manager (AMN) .....	19
Preparing for Migration .....	20
Performing the Migration .....	21



---

## Preface

---

This documentation describes the installation of Adabas Manager on Windows and UNIX/Linux.

Adabas Manager is installed using the Software AG Installer, which you download from the Software AG Empower website at <https://empower.softwareag.com/>.

This documentation provides product-specific instructions for installing Adabas Manager. It is intended for use with *Using the Software AG Installer*. That guide explains how to prepare your machine to use the Software AG Installer, and how to use the Software AG Installer and Software AG Uninstaller to install and uninstall your products. The most up-to-date version of *Using the Software AG Installer* is always available at <http://documentation.softwareag.com/> (Empower login required).

This documentation is organized under the following headings:

<a href="#">System Requirements</a>	Supported operating system platforms and prerequisites.
<a href="#">Important Information</a>	Important information that you should be aware of before you start the installation.
<a href="#">Installing Adabas Manager</a>	How to install Adabas Manager with the Software AG Installer.
<a href="#">Uninstalling Adabas Manager</a>	How to uninstall Adabas Manager.
<a href="#">Migrating from System Management Hub (SMH) to Adabas Manager (AMN)</a>	How to migrate the administration of existing Net-Work components from SMH to AMN.

For important last-minute information, see the readme file that is provided with Adabas Manager. You can find it in the Adabas Manager product documentation at <http://documentation.softwareag.com/> (Empower login required).

---

# 1 About this Documentation

---

▪ Document Conventions .....	2
▪ Online Information and Support .....	2
▪ Data Protection .....	3

## Document Conventions

---

Convention	Description
<b>Bold</b>	Identifies elements on a screen.
Monospace font	Identifies service names and locations in the format <i>folder.subfolder.service</i> , APIs, Java classes, methods, properties.
<i>Italic</i>	Identifies:  Variables for which you must supply values specific to your own situation or environment. New terms the first time they occur in the text. References to other documentation sources.
Monospace font	Identifies:  Text you must type in. Messages displayed by the system. Program code.
{ }	Indicates a set of choices from which you must choose one. Type only the information inside the curly braces. Do not type the { } symbols.
	Separates two mutually exclusive choices in a syntax line. Type one of these choices. Do not type the   symbol.
[ ]	Indicates one or more options. Type only the information inside the square brackets. Do not type the [ ] symbols.
...	Indicates that you can type multiple options of the same type. Type only the information. Do not type the ellipsis (...).

## Online Information and Support

---

### Software AG Documentation Website

You can find documentation on the Software AG Documentation website at <https://documentation.softwareag.com>.

### Software AG Empower Product Support Website

If you do not yet have an account for Empower, send an email to [empower@softwareag.com](mailto:empower@softwareag.com) with your name, company, and company email address and request an account.

Once you have an account, you can open Support Incidents online via the eService section of Empower at <https://empower.softwareag.com/>.

You can find product information on the Software AG Empower Product Support website at <https://empower.softwareag.com>.

To submit feature/enhancement requests, get information about product availability, and download products, go to [Products](#).

To get information about fixes and to read early warnings, technical papers, and knowledge base articles, go to the [Knowledge Center](#).

If you have any questions, you can find a local or toll-free number for your country in our Global Support Contact Directory at [https://empower.softwareag.com/public\\_directory.aspx](https://empower.softwareag.com/public_directory.aspx) and give us a call.

### **Software AG Tech Community**

You can find documentation and other technical information on the Software AG Tech Community website at <https://techcommunity.softwareag.com>. You can:

- Access product documentation, if you have Tech Community credentials. If you do not, you will need to register and specify "Documentation" as an area of interest.
- Access articles, code samples, demos, and tutorials.
- Use the online discussion forums, moderated by Software AG professionals, to ask questions, discuss best practices, and learn how other customers are using Software AG technology.
- Link to external websites that discuss open standards and web technology.

## **Data Protection**

---

Software AG products provide functionality with respect to processing of personal data according to the EU General Data Protection Regulation (GDPR). Where applicable, appropriate steps are documented in the respective administration documentation.

---

# 2 System Requirements

---

- Supported Operating System Platforms ..... 6
- Memory Space Requirements ..... 6
- Disk Space Requirements ..... 6
- Software Requirements ..... 6
- Supported Browsers ..... 8
- License File ..... 8

## Supported Operating System Platforms

---

Adabas Manager supports the following operating system platforms:

- Windows Server 2012 (Datacenter and Standard Edition, x86-64)
- Windows Server 2016 (Datacenter and Standard Edition, x86-64)
- Windows Server 2019 (Datacenter and Standard Edition, x86-64)
- Windows 10 (Pro and Enterprise Edition, x86-64)
- CentOS Linux 7 (x86-64)
- SUSE Linux Enterprise Server 12 (x86-64)
- Red Hat Enterprise Linux AS 7 (x86-64)

Home Editions of Microsoft Windows are not supported.



**Note:** We suggest that you install all of the manufacturer's recommended patches before you start the installation.

## Memory Space Requirements

---

The memory space required by Adabas Manager largely depends on the number of users. It is recommended to use a system with a memory of at least 4 GB.

## Disk Space Requirements

---

Approximately 2 GB of hard-disk space is required for Adabas Manager (including all preselected Adabas and Software AG Installer packages). This value depends on the installation hardware.

## Software Requirements

---

Adabas Manager supports the administration of Adabas environments Version 6.6 and above, as well as the administration of Entire Net-Work LUW. Installing and running Adabas Manager requires no additional components to be installed on the node where it is running.


In order to administer Adabas databases, the Adabas Manager needs to be connected to the Adabas RESTful Administration Server of the Adabas installations.

In order to administer Entire Net-Work, the Adabas Manager needs to be connected to the Adabas Manager Communicator.

In order to exploit the full capability of Adabas Manager, the following component versions are required:

- Adabas 6.7 SP1 – 6.7.1.0
- Adabas Directory Server 5.9 – 5.9.0.0
- Adabas Manager 8.5 – 8.5.0.0
- Adabas Manager Communicator 2.1 – 2.1.0.0
- Adabas Restful Administration 6.7 SP1 – 6.7.1.0
- Entire Net-Work Client 1.8 – 1.8.0.0
- Entire Net-Work Server 7.9 – 7.9.0.0

The following architecture overview shows an example of a possible installation scenario:





**Note:** Fixes in hand with the release must be applied.

## Supported Browsers

---

Supported browsers in this version are:

Microsoft Edge

Mozilla Firefox Extended Support Release 68 <sup>(1)</sup>

Google Chrome <sup>(2)</sup>

### Notes:

<sup>(1)</sup> Only the Extended Support Releases of Mozilla Firefox are explicitly supported. Due to frequent upgrades of the Mozilla Firefox consumer release, the compatibility of Adabas Manager with future versions of Mozilla Firefox cannot be fully guaranteed. Possible incompatibilities will be removed during the regular maintenance process of Adabas Manager.

<sup>(2)</sup> The Google Chrome support is based on Google Chrome Version 74. Due to frequent version upgrades of Google Chrome, compatibility of Adabas Manager with future versions of Google Chrome cannot be fully guaranteed. Possible incompatibilities will be removed during the regular maintenance process of Adabas Manager.



**Important:** Cookies and JavaScript must be enabled in the browser.

## License File

---

The installation and usage of Adabas Manager does not require a license file.

# 3 Important Information

---

- Administrator Status ..... 10
- Installation Directory ..... 10
- Side-by-Side Installations ..... 10
- Data Protection ..... 11
- Opening Ports for Remote Connections ..... 12
- AMNPAM Service for Linux Operating System User ID Login ..... 12
- Software AG Common Runtime ..... 13

## Administrator Status

---

The person performing the installation must have Windows system administrator privileges (Windows platforms).

During the installation, the **Sudo** panel may appear. When you enter the sudo password in this panel, the installer will execute the scripts which require sudoers privileges. For you to use sudo in the installer, the user that you are using to install must be in the sudoers configuration. (Unix/Linux).

## Installation Directory

---

During the installation, you are asked to specify an installation directory. Specify the installation directory in which to install your Software AG products. The user that you are using to install must have full read and write permissions to this directory.

The default installation directory under Windows is *SoftwareAG* and under Unix/Linux is */opt/softwareag*, but any other directory is also possible. In the following description the placeholder *<install-dir>* is used to represent the installation directory.

You can only install Adabas Manager on a local hard drive on a Windows/Linux system. You cannot install Adabas Manager on a network-mounted drive or a SUBST drive (Windows only).

## Side-by-Side Installations

---

You can install the same Adabas Manager version more than once on the same machine. And you can also install several different versions of Adabas Manager on the same machine. This may be necessary to test a new Adabas Manager version before it is taken over into a production environment. Each version, however, must be installed in a separate directory and on Windows you must specify a separate Start menu group name. That is, when Adabas Manager is already installed, for example, in the directory *SoftwareAG* or */opt/softwareag*, you can install a second instance of Adabas Manager, for example, in a directory named *SoftwareAG2* or */opt/softwareag2*.

Since Software AG Empower only offers the latest version of Adabas Manager and other products, it is recommended that you create and keep an image of installed Adabas Manager versions for possible later use. Installing from an image rather than downloading it from Empower will usually be faster, too. For further information, see *Using the Software AG Installer*.

While Adabas Manager is being installed, it is not possible for another user to install Adabas Manager on the same machine. A message with the following information will then be shown:

the name of the user who is currently installing Adabas Manager, when this installation has been started, and into which directory Adabas Manager is currently being installed.

## Data Protection

Before you start Adabas Manager for the first time, you should be aware that Adabas Manager stores user-related data, such as user IDs, in configuration files and log files.

### Configuration File

File Path	Windows:  <code>&lt;install-dir&gt;\AdabasManager\config\host_&lt;uid&gt;.config</code>  Unix/Linux:  <code>&lt;install-dir&gt;/AdabasManager/config/host_&lt;uid&gt;.config</code>
Content	<ul style="list-style-type: none"> <li>■ The file name contains the user ID</li> <li>■ The file content may contain user IDs</li> </ul>
Administration	<p>User IDs in the entries can be managed (created, modified, deleted) by the owner of the configuration file from within the Adabas Manager.</p> <p>If a user ID is deleted, there is no longer access to the respective Adabas REST administration server with this user ID.</p>
Access	Access to the configuration file and its directory can be secured, based on operating system file permissions.
Deletion	<p>Single entries in the file: see Administration above.</p> <p>File: manually or automatically by operating system means or scripts.</p>



**Important:** for existing users of Adabas Manager 8.5, who are upgrading to Adabas Manager 8.6, Adabas Manager will automatically combine the 2 old files `adaHost_<uid>.config` and `netHost_<uid>.config` into the new file `host_<uid>.config`. The user can then manually remove the files `adaHost_<uid>.config` and `netHost_<uid>.config` after `host_<uid>.config` has been created. Users who only install Adabas Manager 8.6 (without having previously installed Adabas Manager 8.5), only have 1 file (`host_<uid>.config`) for each login UserID. (where <uid> stands for <User-ID>)

## Log File

File Path	<p>Windows:</p> <pre>&lt;install-dir&gt;\AdabasManager\log\amn_yyyymmdd.log &lt;install-dir&gt;\AdabasManager\log\amnserver_yyyymmdd.log</pre> <p>Unix/Linux:</p> <pre>&lt;install-dir&gt;/AdabasManager/log/amn_yyyymmdd.log &lt;install-dir&gt;/AdabasManager/log/amnserver_yyyymmdd.log</pre>
Content	Contains user IDs.
Administration	Not possible via Adabas Manager.
Access	Access to the configuration file and its directory can be secured, based on operating system file permissions.
Deletion	<p>Single entries in the file: manually or automatically by operating system means or scripts.</p> <p>File: manually or automatically by operating system means or scripts.</p>

## Opening Ports for Remote Connections

In order to access Adabas Manager and Adabas databases (on Linux and Windows) that are installed on a remote host (e.g. on machine 1) from an internet browser (e.g. on machine 2), it is necessary to open the ports on machine 1, for example the default Adabas Manager port (8083) and the Adabas REST server administration port (8190). Similarly, in order to use Adabas Manager Communicator (AMC) installed remotely, it is necessary to open the port (default 4980), to allow incoming requests.



**Important:** the following known restriction applies - in order to use the HTTPS port (default 8084) on Adabas Manager, the Adabas Administration Server needs to be connected via an HTTPS port (default 8191). Currently, it is not possible to use HTTPS on Adabas Manager together with Adabas Manager Communicator (AMC) to administer Entire Net-Work.

## AMNPAM Service for Linux Operating System User ID Login

After installation, a `sag<n>amnpam service` (where `<n>` is the number of the installed instance) and various shell scripts for use with the `amnpam` service are available in the `$SAG/AdabasManager/bin/` directory.

The purpose of the Adabas Manager PAM server is to communicate with the Pluggable Authentication Module (PAM) in Unix, which in turn allows users to login to Adabas Manager using the Linux Operating System ID (i.e. those IDs created into the `\etc\passwd` file).

The Adabas Manager PAM server will be started after the user has executed the *AfterInstallAsRoot.sh* script.

In the event that the `sag<n>amnpam` service is not running properly, please execute the script *amnpam\_rc.sh stop*, followed by an execution of the script *amnpam\_rc.sh start* with `sudo`, to restart the amnpam service.

## Software AG Common Runtime

---

The Adabas Manager web pages are rendered by the Software AG Common Runtime. Adabas Manager uses the HTTP port (default port 8083) that it provides. For further information, please refer to the *Software AG Infrastructure Administrator's Guide*.



# 4 Installing Adabas Manager

---

This installation documentation provides just a brief description on how to install Adabas Manager directly on the target machine using the Software AG Installer GUI. For detailed information on the Software AG Installer, see *Using the Software AG Installer*.

 **Important:** Make sure all ports you specify on panels or in response to prompts are not already being used by other products on your machine. For a list of default ports used by Software AG products, see "List of Used TCP/IP Ports" in [Empower](#) (go to **Products & Documentation > Download Components > TCP/IP Ports**).

## > To install Adabas Manager

- 1 Start the Software AG Installer GUI as described in *Using the Software AG Installer*.
- 2 When the first page of the Software AG Installer GUI (the so-called Welcome panel) is shown, choose the **Next** button repeatedly (and specify all required information on the shown panels as described in *Using the Software AG Installer*) until the panel containing the product selection tree appears. This tree lists the products you have licensed and which can be installed on the operating system of the machine on which you are installing.
- 3 To install Adabas Manager, expand the **Adabas Products** node and select **Adabas Manager**.



**Note:** Products or product versions which are already installed in the selected installation directory are shown as disabled.

- 4 Choose the **Next** button.
- 5 Read the license agreement, select the check box to agree to the terms of the license agreement, and choose the **Next** button.



**Note:** If you are installing other products together with Adabas Manager, several panels may appear that are not explained in this documentation. See the documentation for these products for more information.

6 A panel to enter a sudo password appears (Unix/Linux). If you do not provide a sudo password, you must manually run the script *afterInstallAsRoot.sh* with sudo rights once the installation is complete.

7 A panel for the Platform Manager appears.

The Platform Manager is an agent that allows remote administration of one or more selected products in this installation from Command Central. The Platform Manager is not supported by Adabas Manager; if you do not want to use it, deselect **Plan to use Command Central**.

Choose the **Next** button to proceed to the next panel.

8 A panel for Adabas Manager Runtime Service appears.

Adabas Manager Runtime Service allows Adabas Manager to administer the Adabas Audit Server. The default port is 4990. If you do not plan to administer the Adabas Audit Server, you can unselect the checkbox.

9 On the last panel, review the list of products you have selected for installation. If the list is correct, choose the **Next** button to complete the installation process.

### > To invoke Adabas Manager after installation (Windows platforms)

■ Start Adabas Manager from the Windows **Start** menu:

**All Programs > <start menu group> > Administration > Adabas Manager *n.n***, where *n.n* is the version number.

### > To invoke Adabas Manager after installation (Unix/Linux platforms)

■ Start Adabas Manager with the script *amn.sh* in *<install-dir>/AdabasManager/bin*.

# 5

## Uninstalling Adabas Manager

---

You uninstall Adabas Manager using the Software AG Uninstaller. For detailed information on how to use the uninstaller, see the *Using the Software AG Installer* guide.

Under Windows, you uninstall Adabas Manager using the standard uninstall functionality of Windows. The Control Panel offers the following entry: **Software AG Products: <installation-directory>**. When you choose to uninstall this entry, the Software AG Uninstaller is invoked.

Under Unix/Linux, you uninstall Adabas Manager as follows:

1. Open a command window and go to the *bin* directory of your main installation directory.
2. Execute the script *beforeUninstallAsRoot.sh* with root privileges.
3. Run the command `uninstall`. This starts the Software AG Uninstaller.

The following files are not removed:

- All files created by the user.
- All configuration files that have been created during the installation.
- Scripts in the *Adabas/INSTALL* directory which may be needed to stop services or daemons (Unix/Linux)

---

# 6 Migrating from System Management Hub (SMH) to Adabas

## Manager (AMN)

---

- Preparing for Migration ..... 20
- Performing the Migration ..... 21

Adabas Manager Version 8.5 and above can be used to administer the Entire Net-Work suite of products (Entire Net-work Server, Entire Net-work Client and Directory Server). As there will be no further development or fixes for System Management Hub, it is highly recommended to upgrade to Adabas Manager as a replacement.

The following chapter will provide you with the information that you need in order to migrate the administration of the Entire Net-Work suite of products from System Management Hub to Adabas Manager.

## Preparing for Migration

---

Adabas Manager is the user interface component that connects to the Adabas Management Communicator (AMC) Server, which in turn connects to the Software AG Directory Server (ADI). From ADI, you can administer components registered to the ADI that you connect to.

You will need two pieces of information before you can start the migration:

- The host name/IP address and port number of the AMC;
- The host name/IP address and port number of the ADI.

The details for AMC are available during the installation. The default port number is 4980, but this can be changed during the installation.

The details for ADI are also available during its installation. The default port number is 4952, but this can be changed during the installation. However, if you are migrating from SMH, you will probably already have an ADI installed, the following steps explain how you can obtain the required information.

### ➤ To obtain the host name/IP address and port number of the Adabas Directory Server

- 1 Login to your SMH. Expand the Directory Server menu until you see the list of available Directory Servers.
- 2 Right click on the Directory Server that you want to check, and select **Modify Directory Server Settings**. Take note of the contents of the fields **Directory Server Host Name** and **Port** - you will need this information when you set up your AMC server in Adabas Manager. If the value in the field **Directory Server Host Name** is a valid host name or IP address, you can use it as it is. Otherwise proceed to the next step.
- 3 If the field **Directory Server Host Name** contains the value `localhost`, it means that ADI is installed on the same machine as SMH. You can find the name of the localhost by entering the command `hostname` at the command prompt. Alternatively, you can find the IP address by entering the command `ipconfig` at the command prompt.

## Performing the Migration

---

### ➤ To migrate the administration of Entire Net-Work products to Adabas Manager

- 1 Enter your login information (local or domain user ID and password) on the Adabas Manager login page and click the **Log In** button. The Adabas Manager home page is displayed.
- 2 Click on the icon **Administer Entire Net-Work** on the Adabas Manager home page.

The Entire Net-Work Administration start page is displayed.

- 3 Click on the configuration icon  on the top right of the page. The Add AMC Host page is displayed.
- 4 Specify the details of the AMC server that you want to use, then click on the button **Add AMC Host**. Either the host name or the IP address of the AMC server can be entered in the field **Hostname/IP**.
- 5 Click on the arrow button next to the name of the AMC server that you have just added. Now specify the details of the Directory Server that you want to use (see the section [Preparing for Migration](#) for information about how to obtain these details).
- 6 Click on the link Net-Work Connection in the header of the page to expand the list of available AMC servers, then click on the name of the AMC server that you have just added. The tree view network is displayed; you can now start with the administration of your Entire Net-Work product suite.



**Note:** By default, Adabas Manager uses the tree view to display the components in the form of a network tree. If preferred, you can switch to the list view, which resembles SMH.

