

# Natural System Error Messages 5951-6000

**NAT5960: Internal error - invalid function code (NOMPUT-N).**

**NAT5961: Internal error - report not opened.**

**NAT5962: Internal error - error during compression of print line.**

**NAT5963: Internal error - invalid CC type specification.**

**NAT5964: Internal error - invalid source type specification.**

**NAT5965: Internal error - invalid NAF DBID.**

**NAT5966: Internal error - invalid NAF FNR.**

**NAT5967: Internal error - invalid logical printer number (1-31).**

**NAT5968: Internal error - invalid User ID specification.**

**NAT5969: Internal error - invalid PROGRAM specification.**

**NAT5970: Internal error - invalid LIBRARY specification.**

**NAT5971: Internal error - invalid LPF specification.**

**NAT5972: Internal error - invalid function code (NOMPUTQN).**

**NAT5973: NOM control record missing.**

**NAT5974: FSPOOL not defined in the NOM monitor defaults.**

**NAT5975: Internal error - error during CMMPP call.**

**NAT5981: Invalid value specified (BLKCTRL/BLKSIZE/LRECL).**

Text	ESY5981 Invalid value specified (BLKCTRL/BLKSIZE/LRECL).
Expl.	Invalid value for BLOCK CONTROL, BLOCK SIZE or RECORD LENGTH specified.
Actn.	Please correct error.

**NAT5982: Error during use of ISAM-key.**

Text	ESY5982 Error during use of ISAM-key.
Expl.	Possible reasons: - duplicate key detected for DUPEKY=NO - key must be generated, but KEYLEN is greater than 8 bytes or no default KEYPOS - key length of file is greater than 253 bytes - key not found in ISAM-file - no key supplied for UPDATE-INPLACE=YES - invalid key sequence detected
Actn.	Please check parameters or file attributes.

**NAT5983: :1: not supported in :2:.**

Text	ESY5983 ... not supported in ....
Expl.	Some views or features are not supported under certain circumstances. Example: View EVENTING is not supported in Single User Mode on BS2000/OSD.
Actn.	No action possible.

**NAT5984: Server is not authorized to access.**

Text	ESY5984 Server is not authorized to access.
Expl.	ESY Server Task is not authorized to access various objects with protection attributes, which not allows access for \$TSOS.
Actn.	No action possible.

**NAT5985: Access to tape file not allowed.**

Text	ESY5985 Access to tape file not allowed.
Expl.	Access to tape file was requested, but parameter TAPES=NO is specified in ESY startup file.
Actn.	Please contact your ESY Administrator.

**NAT5986: No or not enough space for :1:.**

Text	ESY5986 No or not enough space for ....
Expl.	Various startup parameter sizes are exceeded. See variable text for details.
Actn.	Please contact your ESY Administrator.

**NAT5987: Job Variable already exists.**

Text	ESY5987 Job Variable already exists.
Expl.	An existing job variable cannot be allocated again.
Actn.	Please check your input values.

**NAT5988: Invalid task type detected.**

Text	ESY5988 Invalid task type detected.
Expl.	Task type must have a value between 1 and 7.
Actn.	Correct program.

**NAT5989: Invalid ELEMENT specification.**

Text	ESY5989 Invalid ELEMENT specification.
Expl.	Element name must be unique.
Actn.	Correct element name.

**NAT5990: Field RECORD not found in format buffer.**

Text	ESY5990 Field RECORD not found in format buffer.
Expl.	An attempt was made to read a record without specifying the "RECORD" field.
Actn.	Supply field RECORD in program.

**NAT5991: Unknown product.**

Text	ESY5991 Unknown product.
Expl.	An invalid "PRODUCT" value was specified.
Actn.	Specify valid product code.

**NAT5992: Requested job variable not found.**

Text	ESY5992 Requested job variable not found.
Expl.	The requested job variable is not catalogued.
Actn.	No action required.

**NAT5993: Cannot open file.**

Text	ESY5993 Cannot open file.
Expl.	An open request failed.
Actn.	No action required.

**NAT5994: File not on volume.**

Text	ESY5994 File not on volume.
Expl.	The requested data set is not on the specified volume.
Actn.	No action is required.

**NAT5995: File not in catalog.**

Text	ESY5995 File not in catalog.
Expl.	The data set is not catalogued.
Actn.	Specify VOLSER, or catalog data set.

**NAT5996: Volume not online.**

Text	ESY5996 Volume not online.
Expl.	The specified volume is currently not available.
Actn.	Contact Operator or system programmer.

**NAT5997: Data set is not PDS or sequential.**

Text	ESY5997 Data set is not PDS or sequential.
Actn.	No action is required.

**NAT5998: MEMBER not found.**

Text	ESY5998 MEMBER not found.
Expl.	The requested member was not found.
Actn.	No action is required.

**NAT5999: ENTIRE SYSTEM SERVER node :1: not active.**

Text	ESY5999 ENTIRE SYSTEM SERVER node ... not active.
Actn.	Contact Operator or system programmer.

**NAT6000: Error text not available.**

Text	Error text not available.
------	---------------------------