# Natural System Error Messages 5851-5900

## NAT5851: File not on volume.

| Text  | ESY5851 File not on volume.                                |
|-------|------------------------------------------------------------|
| Expl. | The requested file does not exist on the specified volume. |
| Actn. | No action is required.                                     |

# NAT5852: No password supplied / VSAM data space.

| Text  | ESY5852 No password supplied / VSAM data space.                                       |
|-------|---------------------------------------------------------------------------------------|
| Expl. | No password was specified before attempting to access a password protected VSAM file. |
| Actn. | Specify a password.                                                                   |

# NAT5853: Retention cycle unexpired / NEWNAME exists.

| Text  | ESY5853 Retention cycle unexpired / NEWNAME exists.                                                                   |
|-------|-----------------------------------------------------------------------------------------------------------------------|
| Expl. | A VTOC-UPDATE RENAME function was attempted; however, the retention cycle is unexpired, and the NEWNAME still exists. |
| Actn. | Specify a different NEWNAME, or wait until the retention cycle has expired.                                           |

# NAT5854: Permanent I/O error.

| Text  | ESY5854 Permanent I/O error.                                      |
|-------|-------------------------------------------------------------------|
| Expl. | A permanent I/O error was detected.                               |
| Actn. | This is probably a hardware error. Contact data center personell. |

# NAT5855: Volume not mounted.

| Text  | ESY5855 Volume not mounted.                                         |
|-------|---------------------------------------------------------------------|
| Expl. | The requested volume was not mounted.                               |
| Actn. | Make sure that the volume is mounted before re-issuing the request. |

# NAT5856: Operator unable to mount volume.

| Text  | ESY5856 Operator unable to mount volume.      |
|-------|-----------------------------------------------|
| Expl. | The operator is not able to mount the volume. |
| Actn. | No action is required.                        |

#### NAT5857: File in use.

| Text  | ESY5857 File in use. |
|-------|----------------------|
| Expl. | The file is in use.  |
| Actn. | Retry later.         |

## NAT5858: Not authorized.

| Text  | ESY5858 Not authorized.            |
|-------|------------------------------------|
| Expl. | A security violation was detected. |
| Actn. | No action is required.             |

# NAT5859: File definition not deleted by RACF.

| Text  | ESY5859 File definition not deleted by RACF.      |
|-------|---------------------------------------------------|
| Expl. | The file definition has not been deleted by RACF. |
| Actn. | Execute RACF file deletion.                       |

# NAT5860: Member under MSHP control or changed with MSHP bypass.

| Text  | ESY5860 Member under MSHP control or changed with MSHP bypass.                  |
|-------|---------------------------------------------------------------------------------|
| Expl. | Member to be overwritten is under MSHP control or was changed with MSHP bypass. |
| Actn. | Use MSHP=YES to indicate MSHP bypass required.                                  |

## NAT5861: Member contains SYSIPT data.

| Text  | ESY5861 Member contains SYSIPT data.                                                                          |
|-------|---------------------------------------------------------------------------------------------------------------|
| Expl. | Member to be overwritten contains SYSIPT data.                                                                |
| Actn. | Use INLINE-DATA=YES to confirm SYSIPT data required<br>or INLINE-DATA=OFF to switch off the SYSIPT indicator. |

## NAT5870: RECORD field not in search buffer.

| Text  | ESY5870 RECORD field not in search buffer. |
|-------|--------------------------------------------|
| Expl. | RECORD must be specified for WRITE-FILE.   |
| Actn. | Specify RECORD value.                      |

# NAT5871: MEMBER/MEMBER-TYPE not specified.

| Text  | ESY5871 MEMBER/MEMBER-TYPE not specified.      |
|-------|------------------------------------------------|
| Expl. | The member name and/or type was not specified. |
| Actn. | Specify a member name and/or type.             |

## NAT5872: Record format not supported.

| Text  | ESY5872 Record format not supported.                        |
|-------|-------------------------------------------------------------|
| Expl. | The record format of the desired data set is not supported. |
| Actn. | No action is required.                                      |

## NAT5873: RECORD-LENGTH missing.

| Text  | ESY5873 RECORD-LENGTH missing.      |
|-------|-------------------------------------|
| Expl. | The RECORD-LENGTH value is missing. |
| Actn. | Specify RECORD-LENGTH value.        |

# NAT5874: RECORD-LENGTH > LRECL.

| Text  | ESY5874 RECORD-LENGTH > LRECL.                                               |
|-------|------------------------------------------------------------------------------|
| Expl. | The specified RECORD-LENGTH value is greater than the LRECL of the data set. |
| Actn. | Specify valid RECORD-LENGTH value.                                           |

# NAT5875: Position of data field > RECORD-LENGTH.

| Text  | ESY5875 Position of data field > RECORD-LENGTH. |
|-------|-------------------------------------------------|
| Expl. | invalid parameter are given in this view-call.  |
| Actn. | check program and correct error.                |

# NAT5876: No NEW-field for CHANGE request.

| Text  | ESY5876 No "NEW-" field for CHANGE request                                             |
|-------|----------------------------------------------------------------------------------------|
| Expl. | No NEW-CLASS, NEW-DESTINATION or NEW-USERID field was supplied for the CHANGE request. |
| Actn. | Supply "NEW-" value                                                                    |

## NAT5877: VSAM (SHOWCAT) processing error.

| Text  | ESY5877 VSAM (SHOWCAT) processing error.                                                                                                                                                                                                                                               |
|-------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Expl. | A SHOWCAT error was detected when processing the requested VSAM<br>file. This generally indicates that the requested file is not a<br>a VSAM cluster or non-VSAM file, but rather a VSAM catalog or<br>other VSAM non-file object. Information cannot be displayed<br>about this file. |

#### NAT5878: Volume defined as DYNAM/D pool name.

| Text | ESY5878 Volume defined as DYNAM/D pool name.                                                                                             |
|------|------------------------------------------------------------------------------------------------------------------------------------------|
| -    | The requested volume is defined to Entire System Server as a DYNAM/D<br>"virtual" pool name. The requested function cannot be performed. |

#### NAT5881: Error occurred while opening file.

| Text  | ESY5881 Error occurred while opening file. |
|-------|--------------------------------------------|
| Expl. | An error occurred during OPEN.             |
| Actn. | Check the status of the data set.          |

## NAT5882: Error occurred while closing file.

| Text  | ESY5882 Error occurred while closing file. |
|-------|--------------------------------------------|
| Expl. | An error occurred during CLOSE.            |
| Actn. | Check the status of the data set.          |

#### NAT5883: Data set is full.

| Text  | ESY5883 Data set is full.                        |
|-------|--------------------------------------------------|
| Expl. | The data set is full.                            |
| Actn. | Compress the PDS, or increase the data set size. |

#### NAT5886: Event is in use.

| Text  | ESY5886 Event is in use.                                        |
|-------|-----------------------------------------------------------------|
| Expl. | An attempt was made to delete an event someone was waiting for. |
| Actn. | Issue "POST" request prior to delete an event.                  |

# NAT5887: Event is already defined.

| Text  | ESY5887 Event is already defined.                            |
|-------|--------------------------------------------------------------|
| Expl. | An attempt was made to define an event which already exists. |
| Actn. | No action is required.                                       |

#### NAT5888: Event name must be specified.

| Text  | ESY5888 Event name must be specified.                               |
|-------|---------------------------------------------------------------------|
| Expl. | An "EVENTING" request was issued without specifying the event name. |
| Actn. | Specify an event name.                                              |

# NAT5889: Permanent I/O error while writing data set.

| Text  | ESY5889 Permanent I/O error while writing data set.               |
|-------|-------------------------------------------------------------------|
| Expl. | An I/O error was detected during WRITE access.                    |
| Actn. | This is probably a hardware error. Contact data center personell. |

### NAT5890: Event does not exist.

| Text  | ESY5890 Event does not exist.       |
|-------|-------------------------------------|
| Expl. | The specified event does not exist. |
| Actn. | No action is required.              |

#### NAT5891: Timeout waiting for event.

| Text  | ESY5891 Timeout while waiting for event.        |
|-------|-------------------------------------------------|
| Expl. | A timeout happened before the event was posted. |
| Actn. | No action is required.                          |

#### NAT5893: Getmain failed.

| Text  | ESY5893 Getmain failed.                                                 |
|-------|-------------------------------------------------------------------------|
| Expl. | There was not sufficient storage available to proceed with the request. |
| Actn. | Notify system programmer.                                               |

## NAT5894: Enable Eventing failed.

| Text  | ESY5894 Enable Eventing failed.           |
|-------|-------------------------------------------|
| Expl. | internal eventing error occured.          |
| Actn. | contact technical support of Software AG. |

## NAT5895: :1: must be specified.

| Text  | ESY5895 :1: must be specified.        |
|-------|---------------------------------------|
| Expl. | Required value :1: was not specified. |
| Actn. | Provide required value.               |

# NAT5896: Error occurred when sending E-Mail.

| Text  | ESY5896 Error occurred when sending E-Mail.                                                                                                         |
|-------|-----------------------------------------------------------------------------------------------------------------------------------------------------|
| Expl. | Severe error occurred during E-MAIL processing. Further information are returned in field SYSTEM-MESSAGE to identify subfunction and response code. |
| Actn. | Please contact Software AG support.                                                                                                                 |

# NAT5897: Mailer response: :1:.

| Text  | ESY5897 Mailer response :1:.                                                                                                           |
|-------|----------------------------------------------------------------------------------------------------------------------------------------|
| Expl. | Error :1: occurred during E-MAIL processing in Mailer function.<br>E-MAIL was not delivered to recipient(s) if serious error occurred. |
| Actn. | Please contact Entire System Server Administrator. Mailer report may contain further error diagnostics.                                |

# NAT5899: Permanent I/O error while reading data set.

| Text  | ESY5899 Permanent I/O error while reading data set.               |
|-------|-------------------------------------------------------------------|
| Expl. | An I/O error was detected during READ access.                     |
| Actn. | This is probably a hardware error. Contact data center personell. |

# NAT5900: Cannot allocate SYSOUT data set.

| Text  | ESY5900 Cannot allocate SYSOUT data set.      |
|-------|-----------------------------------------------|
| Expl. | Dynamic allocation of SYSOUT data set failed. |
| Actn. | Contact the system programmer.                |