List All Environment Variables

Subroutine Name	Executable Example	Viewable Example
W3LIST-ENVIRONMENT W3LIST-ENVIRONMENT-TO-DYNAMIC	E3ENVLIS	E3ENVLIS

Description

List all variables sent by the HTTP server.

Parameters

1. W3LIST-ENVIRONMENT

```
1 W3START            (I4)        /* io/m : Offset to be started at
*                                /*        out: 0 no occurrences
*                                /*        out: >0 more occurrences
1 W3ARRAYCOUNTER     (A72/1:V)   /* io/m : Length of array returned values
1 W3ARRAYNAME        (A250/1:V)  /*  o/m : Name of variables
1 W3ARRAYVALUE       (I4/1:V)    /*  o/m : Value of variables
1 W3ARRAYVALUELENGTH (L/1:V)     /*  o/m : Length of variables
1 W3ARRAYVALUESERVER (I4)        /*  o/m : Variable belongs to
1 W3ARRAYMAXIMUM                 /*  o/m : Total number of variables
```

2. W3LIST-ENVIRONMENT-TO-DYNAMIC

```
1 W3START            (I4)            /* io/m : Offset to be started at
*                                    /*        out: 0 no occurrences
*                                    /*        out: >0 more occurrences
1 W3ARRAYCOUNTER     (A/1:V)dynamic  /* io/m : Length of array returned values
1 W3ARRAYNAME        (A/1:V)dynamic  /*  o/m : Name of variables
1 W3ARRAYVALUE       (I4/1:V)        /*  o/m : Value of variables
1 W3ARRAYVALUELENGTH (L/1:V)         /*  o/m : Length of variables
1 W3ARRAYVALUESERVER (I4)            /*  o/m : Variable belongs to
1 W3ARRAYMAXIMUM                     /*  o/m : Total number of variables
```

How To Invoke

```
PERFORM W3LIST-ENVIRONMENT W3START W3NAME W3ARRAYCOUNTER
        W3ARRAYNAME(*) W3ARRAYVALUE(*) W3ARRAYVALUELENGTH(*)
        W3ARRAYVALUESERVER(*) W3ARRAYMAXIMUM
```