

Compression/Decompression Error Messages

This section lists the error messages (NUS02nn) that may be issued by the Natural thread compression routine as a result of internal errors.

NUS0201 - INVALID OP.CODE OR FIRST ENTRY IS NOT THE COMPRESSION BUFFER

Expl.	Internal error.
Actn.	Send the corresponding dump to Software AG Support.

NUS0202 - NUMBER OF TABLE ELEMENTS IS ZERO

Expl.	Internal error.
Actn.	Send the corresponding dump to Software AG Support.

NUS0203 - NUMBER OF TABLE ELEMENTS IS GREATER MAX.

Expl.	Internal error.
Actn.	Send the corresponding dump to Software AG Support.

NUS0204 - TOTAL THREAD LENGTH LOWER COMPRESSED

Expl.	Internal error.
Actn.	Send the corresponding dump to Software AG Support.

NUS0205 - BUFFER TYPE MISSING

Expl.	Internal error.
Actn.	Send the corresponding dump to Software AG Support.

NUS0206 - COMPRESSED BUFFER GREATER TOTAL LENGTH

Expl.	Internal error.
Actn.	Send the corresponding dump to Software AG Support.

NUS0207 - TOTAL LENGTH GREATER UPPER LIMIT

Expl.	The Natural user thread is too small.
Actn.	Enlarge the Natural user thread (under UTM, change operand of parameter MAXSIZE in macro NTSWPRM).

NUS0208 - INCORRECT TOTAL BUFFER LENGTH

Expl.	Internal error.
Actn.	Send the corresponding dump to Software AG Support.

NUS0209 - INCORRECT USED BUFFER LENGTH

Expl.	Internal error.
Actn.	Send the corresponding dump to Software AG Support.

NUS0210 - THREAD TOO SMALL FOR DECOMPRESSION

Expl.	The Natural user thread is too small.
Actn.	Enlarge the Natural user thread (under UTM, change operand of parameter MAXSIZE in macro NTSWPRM).

NUS0211 - BUFFER OFFSET/ADDRESS NOT POSITIVE

Expl.	Internal error.
Actn.	Send the corresponding dump to Software AG Support.

NUS0212 - ERROR IN BUFFER SORT SEQUENCE

Expl.	Internal error.
Actn.	Send the corresponding dump to Software AG Support.

NUS0213 - INCORRECT BUFFER OVERLAPPING

Expl.	Internal error.
Actn.	Send the corresponding dump to Software AG Support.

NUS0214 - TOTAL OR USED BUFFER LENGTH IS INVALID

Expl.	Internal error.
Actn.	Send the corresponding dump to Software AG Support.

NUS0215 - INVALID THREAD STATUS FOR OPERATION

Expl.	Internal error.
Actn.	Send the corresponding dump to Software AG Support.

NUS0216 - INVALID BUFFER LENGTH IN PREFIX

Expl.	Internal error.
Actn.	Send the corresponding dump to Software AG Support.

NUS0217 - INVALID LENGTH LOW END IN PREFIX

Expl.	Internal error.
Actn.	Send the corresponding dump to Software AG Support.

NUS0218 - INVALID LENGTH HIGH END IN PREFIX

Expl.	Internal error.
Actn.	Send the corresponding dump to Software AG Support.

NUS0219 - INVALID LENGTH BEFORE COMPR. BUFFER

Expl.	Internal error.
Actn.	Send the corresponding dump to Software AG Support.

NUS0220 - CMCCBR CALLED WITH COMPRESSED THREAD

Expl.	Internal error.
Actn.	Send the corresponding dump to Software AG Support.

NUS0221 - CMCCBR THREAD STATUS IS UNDEFINED

Expl.	Internal error.
Actn.	Send the corresponding dump to Software AG Support.

NUS0222 - INVALID BUFFER ID OR EYE CATCHER DESTROYED

Expl.	Internal error.
Actn.	Send the corresponding dump to Software AG Support.

NUS0223 - ERROR FROM CMFREMP FOR OUTSIDE BUFFER

Expl.	Internal error.
Actn.	Send the corresponding dump to Software AG Support.

NUS0224 - PHYS.GETMAIN ERROR FOR A FIXED BUFFER BELOW

Expl.	Internal error.
Actn.	Send the corresponding dump to Software AG Support.

NUS0225 - PHYS.GETMAIN ERROR FOR A VAR.BUFFER BELOW

Expl.	Internal error.
Actn.	Send the corresponding dump to Software AG Support.

NUS0226 - FREE MAIN FOR WORKPOOLS NOT DONE

Expl.	Internal error.
Actn.	Send the corresponding dump to Software AG Support.

**NUS0227 - STORAGE OVERFLOW - yyy BYTES
GREATER zzz**

yyy	represents the number of bytes which exceed the value defined by the keyword parameters OVSIZE or WPSIZE.
zzz	represents the value defined for the operand of the keyword parameters OVSIZE or WPSIZE of the Natural parameter module NTPRM.

Expl.	During a physical GETMAIN, one of the maximum sizes defined in the keyword parameters OVSIZE or WPSIZE in the Natural parameter module NTPRM is exceeded.
Actn.	Increase the maximum size of OVSIZE or WPSIZE of the Natural parameter module.

NUS0228 - GETMAIN FOR BIT TABLE BUFFER FAILED

Expl.	Internal error.
Actn.	Send the corresponding dump to Software AG Support.