

FREEMAIN Error Numbers in NAT7546

This document describes the error numbers which are displayed in Error Message NAT7546 as a result of a failed FREEMAIN request:

NAT7546 freemain of :1: buffer failed (:2:/:3:)

where **:2:** contains one of the following error numbers and

:3: contains the response code from the operating system.

Error 100: Incorrect total buffer length in buffer prefix

Expl.	Internal error, the buffer prefix contains an invalid total buffer length.
Actn.	Contact Software AG Support.

Error 104 : Invalid freemain length for a fixed buffer type

Expl.	Internal error, invalid FREEMAIN length for a fixed buffer.
Actn.	Contact Software AG Support.

Error 108 : Invalid freemain length for a variable buffer

Expl.	Internal error, invalid FREEMAIN length for a variable buffer.
Actn.	Contact Software AG Support.

Error 112 : Used length greater freemain buffer length

Expl.	Internal error, the length of an existing variable buffer has been reduced, but the length used from high end plus the length used from low end is greater than the new (reduced) buffer length.
Actn.	Contact Software AG Support.

Error 116 : Freemain for a fixed buffer below the 16-MB line failed

:3:

Expl.	FREEMAIN error for a fixed buffer below the 16-MB line from the operating system.
Actn.	For details, see the reason code and response code from the operating system.

Error 120 : Eye catcher of physical buffer destroyed

Expl.	Internal error, the eye catcher of a physical buffer in a work pool has been destroyed.
Actn.	Contact Software AG Support.

Error 124 : Freemain for the physical buffer already done

Expl.	Internal error, the FREEMAIN for the physical buffer in a work pool has been done.
Actn.	Contact Software AG Support.

Error 128 : Invalid freemain length for a physical buffer

Expl.	Internal error, the FREEMAIN length for a physical buffer is invalid.
Actn.	Contact Software AG Support.

Error 132 : Freemain length greater than Work Pool size

Expl.	Internal error, the FREEMAIN length for a physical buffer is greater than the work pool size.
Actn.	Contact Software AG Support.

Error 136 : Freemain length greater total size of physical storage

Expl.	Internal error, the FREEMAIN length for a physical buffer is greater than the total size of the physical storage.
Actn.	Contact Software AG Support.

Error 140 : Invalid buffer address for freemain

Expl.	Internal error, the buffer address for a FREEMAIN is not valid.
Actn.	Contact Software AG Support.

Error 144 : Error from CMFREMP for a variable/fixed buffer

:3:

Expl.	FREEMAIN error for a variable or fixed buffer from the operating system.
Actn.	For details, see the reason code and response code from the operating system.

Error 148 : Error from CMFREMP for a Work Pool

:3:

Expl.	FREEMAIN error for a work pool from the operating system.
Actn.	For details, see the reason code and response code from the operating system.

Error 152 : Error from CMFREMP during freemain ALL

:3:

Expl.	FREEMAIN error from the operating system during FREEMAIN ALL.
Actn.	For details, see the reason code and response code from the operating system.

Error 156 : Error from CMFREMP for a buffer outside of thread

:3:

Expl.	FREEMAIN error from the operating system for a buffer which is allocated outside of the thread.
Actn.	For details, see the reason code and response code from the operating system.