# Natural System Error Messages 2751-2800

# NAT2751: Object replaced.

| Text  | Object replaced.  |
|-------|---|
| Expl. | During the load process an object description in Predict has been replaced. |

# NAT2752: File type for file changed to "S".

| Text  | File type for file changed to "S".   |
|-------|--|
| Expl. | If you load a VSAM file, which was stored in Predict Version 1, the file type is set to "S" in Predict Version 2, because some attributes of the VSAM file definition are missing. |
| Actn. | Change manually the SEQUENTIAL FILE in a VSAM FILE and add the required attributes.  |

#### NAT2753: Adabas field name missing.

| Text  | Adabas field name missing.   |
|-------|--|
| Expl. | During the load process a field without an Adabas short name<br>was laoded. This message is a warning. Some files require to all<br>fields an Adabas short name. The field was loaded, but the file<br>contains now incorrect data. Please define to those fields the<br>Adabas short names. |
| Actn. | Correct the invalid field.   |

## NAT2754: FDT incorporated.

| Text  | FDT incorporated.                           |
|-------|---|
| Expl. | The FDT has been incorporated successfully. |

#### NAT2755: Master field missing.

| Text  | Master field missing.   |
|-------|---|
| Expl. | If you load a userview and no related Adabas field in Predict<br>Exists, this message will be sent. |
| Actn. | Load first the related Adabas file.   |

## NAT2756: Natural Security not installed.

| Text  | Natural Security not installed.   |
|-------|---|
| Expl. | The Natural Security feature is not installed. No Security options are available. |
| Actn. | Either do not specify Security options or install the Natural Security System.    |

## NAT2757: First character of PREFIX not alpha.

| Text  | First character of PREFIX not alpha.           |
|-------|--|
| Expl. | The PREFIX must start with an alpha character. |
| Actn. | Check prefix and correct error.                |

## NAT2758: Only command VERSIONS allowed.

| Text  | Only command VERSIONS allowed.  |
|-------|---|
| Expl. | Message occurres, if you want to unload predict version 1 data with command "UNLOAD". |
| Actn. | Enter command VERSIONS.   |

## NAT2759: No related master file found. File not loaded.

| Text  | No related master file found. File not loaded.   |
|-------|--|
| Expl. | If you want to load a User view and no related Adabas file exists,<br>this message will be sent. |
| Actn. | Please load first the Adabas file.   |

# NAT2760: User exit program missing.

| Text  | User exit program missing.  |
|-------|---|
| Expl. | IF a USER EXIT should be activated via the Predict DDA SERVICES the USER EXIT program must exist. |
| Actn. | Catalog the user exit program.  |

# NAT2761: Enter "O", "N", "Y", or "F".

| Text  | Enter "O", "N", "Y", or "F".  |
|-------|---|
| Expl. | The possible values of general system default parameters EDIT<br>OWNER/DESCRPTION are O, N, Y or F. See documentation for further<br>information. |

#### NAT2762: File is not locked.

| Text  | File is not locked.  |
|-------|--|
| Expl. | If you use the RECOVER function for a file which is not locked, This message will be sent. |
| Actn. | Check FILE-ID.   |

#### NAT2763: USER VIEW not loaded, because related MASTER FILE was rejected.

| Text  | USER VIEW not loaded, because related MASTER FILE was rejected.   |
|-------|---|
| Expl. | A USER VIEW should be laoded, but the related MASTER FILE was rejected, because its file number was not unique. |
| Actn. | Check the used file numbers.  |

#### NAT2764: If pre-processor specified, no Natural data allowed.

| Text  | If pre-processor specified, no Natural data allowed.  |
|-------|---|
| Expl. | Natural parameter data may not be used when deleting active cross references using the Predict pre-processor. |
| Actn. | Do not specify Natural data.  |

## NAT2765: If PROGRAM-ID is specified, LIBRARY-ID must be specified too.

| Text  | f PROGRAM-ID is specified, LIBRARY-ID must be specified too.   |  |
|-------|--|--|
|       | If you want an evaluation by PROGRAM name, you must also specify the LIBRARY NAME. Its allowed to specify only a LIBRARY name. |  |
| Actn. | Specify library name.  |  |

#### NAT2766: Abend data of preprocessor deleted.

| Text  | Abend data of preprocessor deleted.   |  |
|-------|---|--|
| Expl. | Active references will also be stored in the data dictionary if the preprocessor terminates with condition code greater zero.<br>These abend data can be deleted by a special function of DDA SERVICES. |  |

#### NAT2767: More than 130 fields are undefined.

| Text  | More than 130 fields are undefined.   |
|-------|---|
| Expl. | Maximal 130 fields, which are used but not defined in Predict, are displayed. |
| Actn. | Define the used fields in Predict.  |

#### NAT2768: Xref data deleted.

| Text  | Xref data deleted.  |  |
|-------|---|--|
| Expl. | This message tells you that active crossreference records have been deleted successfully. |  |

#### NAT2769: Please enter User ID or ".".

| Text  | Please enter User ID or ".".  |
|-------|---|
| Expl. | When using the owner editor, you may enter the owners of an object.<br>If an owner has no users defined, it will be marked with a "?".<br>To define one or more users for such an owner,<br>enter .E in the respective editor line; then enter a User ID<br>for the new user description. |
| Actn. | Enter a new User ID or a ".".   |

## NAT2770: SUPER Natural only possible, if file has security definitions.

| Text  | SUPER Natural only possible, if file has security definitions.  |
|-------|---|
| Expl. | IF Natural Security is active, the generation of a SUPER Natural file<br>entry is only possible if also Security definitions for the file are<br>available. |
| Actn. | Generate also Security definition. Enter "Y" for Natural Security.  |

## NAT2771: Copy-field ID or Copy-file ID missing.

| Text  | Copy-field ID or Copy-file ID missing.   |
|-------|--|
| Expl. | An attempt was made to copy a field without having specified a<br>Copy-field ID. A field can be copied from one file to another<br>or into the same file by changing its name. |
| Actn. | Enter either a Field ID or a File ID.  |

#### NAT2772: Start-field ID not found.

| Text  | Start-field ID not found.  |
|-------|--|
| Expl. | The Start-field ID was not found in the file. A valid<br>Start-field ID must be entered in order to copy fields. |
| Actn. | Enter a valid Start-field ID.  |

## NAT2773: Start-field ID missing.

| Text  | Start-field ID missing.        |
|-------|--------------------------------|
| Expl. | No Start-field ID was entered. |
| Actn. | Enter a Start-field ID.        |

## NAT2774: Do not specify both Field ID and File ID for start field.

| Text  | Do not specify both Field ID and File ID for start field.   |
|-------|---|
| Expl. | The selection can be performed in two ways: either all fields from<br>one file are displayed for selection, or all files containing the<br>field entered are displayed. |
| Actn. | Enter either a Field ID or a File ID; do not enter both.  |

## NAT2775: No SUPER Natural possible if status private.

| Text  | No SUPER Natural possible if status private.  |
|-------|---|
| Expl. | If Natural Security is active and a file is declared as private<br>no generation of a SUPER Natural file entry is possible. |
| Actn. | Change status of the file, if necessary.  |

# NAT2776: SUPER Natural file added.

| Text  | SUPER Natural file added.  |
|-------|--|
| Expl. | At generation DDM for the file a SUPER Natural entry has been generated. |

## NAT2777: Hit enter to return to menu.

| Text  | Hit enter to return to menu.  |
|-------|---|
| Expl. | This message is issued when an error is encountered during the generation of a Data Definition Module; a specific error message is also returned with this message. |
| Actn. | Hit enter and the menu will be displayed.<br>Hit enter to go back to menu; correct error.   |

# NAT2778: Invalid offset or length of primary key.

| Text  | Invalid offset or length of primary key.   |
|-------|--|
| Expl. | This error message occurres at generation DDM of logical VSAM file.<br>Offset and length of the primary key in the logical VSAM file must be<br>equate to the offset and length of the primary key in the physical<br>VSAM file in consideration with the length of the Prefix.<br>If the VSAM prefix was not specified at maintenance logical VSAM file,<br>the standard VSAM prefix "file number" will be taken. |
| Actn. | Correct offset or length of the primary key in the logical or physical VSAM file.  |

## NAT2779: Incorrect length for primary key.

| Text  | Incorrect length for primary key.  |
|-------|------------------------------------|
| Expl. | Correct length of the primary key. |

#### NAT2780: Field moved successfully.

| Text  | Field moved successfully.                         |
|-------|---|
| Expl. | The field was moved successfully within the file. |

#### NAT2781: Object purge was not confirmed.

| Text  | Object purge was not confirmed.  |
|-------|--|
| Expl. | When an object should be deleted in Predict, the system needs<br>an additional confirmation.<br>In the present case, the user abends the PURGE function and<br>the object still remains in the dictionary. |

## NAT2782: Object purged successfully.

| Text     | Object purged successfully.  |
|----------|--|
| <b>^</b> | The object description was deleted from the dictionary. All other<br>entries belonging to the object remain in the dictionary. |

#### NAT2783: Object scratched successfully.

| Text  | Object scratched successfully.   |
|-------|--|
| Expl. | The object and all objects belonging to that object have been deleted from the dictionary. |

#### NAT2784: Enter "DELETE" or "SCRATCH" or ".".

| Text  | Enter "DELETE" or "SCRATCH" or ".".  |
|-------|--|
| Expl. | The user has been prompted for an confirmation: if "DELETE" is<br>entered, only the specified object will be deleted; if "SCRATCH" is<br>entered, the object and all its dependent objects will be deleted;<br>if input is ".", no object will be deleted. |
| Actn. | Enter the desired option.  |

#### NAT2785: Alternate index not on that offset.

| Text  | Alternate index not on that offset.                 |
|-------|---|
| Expl. | The defined offset of the alternate index is wrong. |
| Actn. | Check offset.                                       |

### NAT2786: Invalid length of alternate index.

| Text  | Invalid length of alternate index.                  |
|-------|---|
| Expl. | The defined length of the alternate index is wrong. |
| Actn. | Check length of the alternate index.                |

## NAT2787: No generation for conceptual or standard file allowed.

| Text  | No generation for conceptual or standard file allowed.  |
|-------|---|
| Expl. | The generation of copy code is not allowed for conceptual and<br>standard files. You must copy the file definition to another<br>file, which is not of type standard or conceptual, then you<br>can start the generation. |
| Actn. | Check file type or use another file.  |

#### NAT2788: No file number available, file not loaded.

| Text  | No file number available, file not loaded.   |
|-------|--|
| Expl. | All file numbers with the same last 3 digits of the specified file<br>number are used. For example the file numbers<br>0001, 1001, 2001, 3001,, 9001 all used. |
| Actn. | Use another file number.   |

#### NAT2789: Invalid Adabas file number, not loaded.

| Text  | Invalid Adabas file number, not loaded.           |
|-------|---|
| Expl. | The last 3 digits of the file number greater 255. |
| Actn. | Check file-number and correct error.              |

## NAT2790: Enter "DELETE" or ".".

| Text  | Enter "DELETE" or ".".  |
|-------|---|
| Expl. | The user has been prompted for an confirmation:<br>if "delete" is entered, the specified object will be deleted;<br>if "." is entered, no object will be deleted. |
| Actn. | Enter the desired option.   |

## NAT2791: All keywords have relations.

| Text  | All keywords have relations.                    |
|-------|---|
| Expl. | Every keyword defined in Predict has relations. |

## NAT2792: No object was selected.

| Text     | No object was selected.  |
|----------|--|
| <b>^</b> | A menu for selecting an object from a list was displayed, and the user was prompted to select one of the objects. None was marked. |

## NAT2793: An object was selected.

| Text | An object was selected.   |
|------|---|
|      | The user was prompted to select an object from a list. An object<br>was marked by the user. This message indicates that Predict has<br>carried out the selection. |

# NAT2794: The RENAME function was not performed.

| Text  | The RENAME function was not performed.   |
|-------|--|
| Expl. | After the RENAME function has been invoked, the user did not enter<br>the new name for the object. Therefore, the RENAME function did not<br>take place. |

# NAT2795: For copy a user view file number cannot change.

| Text  | For copy a user view file number cannot change.  |
|-------|--|
| Expl. | If you copy a user view from an Adabas master file, the file number cannot be changed. |
| Actn. | Enter the file number of the master file.  |

#### NAT2796: Indicator not "+" OR "-".

| Text  | Indicator not "+" OR "-".   |
|-------|---|
| Expl. | The indicator tells the editor whether the entered line command<br>should be performed after the line ("+") or before the line ("-")<br>where the command was entered. For example, the line command<br>".W" will open a window after the line where this command<br>has been entered if the value of the indicator is "+" and will<br>open the window before the mentioned line if the value of the<br>indicator is "-". |
| Actn. | Enter "+" or "-" for the indicator.   |

## NAT2797: Target file does not exist.

| Text  | Target file does not exist.                                 |
|-------|---|
| Expl. | An attempt was made to copy a field to a non-existant file. |
| Actn. | Enter a valid File ID.                                      |

## NAT2798: File tested successfully.

| Text | File tested successfully.  |
|------|--|
| -    | The file was tested against the FDT: no differences between the FDT and the file were found. |

#### NAT2799: File tested with error.

| Text  | File tested with error.   |
|-------|---|
| Expl. | During a test of a file against the FDT, differences were found (for example, a field name in the file was not found in the FDT). |
| Actn. | Check file and correct error.   |

#### NAT2800: The file entered is not accessible.

| Text  | The file entered is not accessible.   |
|-------|---|
| Expl. | Adabas was unable to gain access to a file. Probable reasons are:<br>- file not in data base; or<br>- authorization level too low to gain access; or<br>- file is locked. |
| Actn. | Correct error and retry.  |