

Natural System Error Messages 5701-5750

NAT5701: DSNAME missing.

| | |
|-------|-------------------------|
| Text | ESY5701 DSNAME missing. |
| Expl. | The DSNAME was missing. |
| Actn. | Specify a valid DSNAME. |

NAT5702: OUTADD error-code :1: reason-code :2: key :3:.

| | |
|------|--|
| Text | ESY5702 OUTADD error-code :1: reason-code :2: key :3:. |
|------|--|

NAT5703: Copying of empty files not permitted.

| | |
|------|---|
| Text | ESY5703 Copying of empty files not permitted. |
|------|---|

NAT5710: Allocation failed with code :1:.

| | |
|-------|---|
| Text | ESY5710 Allocation failed with code :1:. |
| Expl. | The allocation failed. The code is the DYNALLOC return code. Note: A more detailed message is returned when field ERROR-TEXT is specified. |
| Actn. | Check the DYNALLOC return code. |

NAT5711: Logical Error occurred in Common JES Interface.

| | |
|-------|--|
| Text | ESY5711 Logical Error occurred in Common JES Interface. |
| Expl. | A logical error has occurred in the Common JES Interface. Additional messages describing the type of error may have been issued to the console. |
| Actn. | Check the system log for additional messages. Contact Software AG technical support. |

NAT5712: Request to Common JES Interface failed.

| | |
|-------|---|
| Text | ESY5712 Request to Common JES Interface failed. |
| Expl. | A request failed to access spool data. |
| Actn. | Contact Software AG technical support. |

NAT5713: Jobname and Job ID missing. One of them required.

| | |
|-------|---|
| Text | ESY5713 Jobname and Job ID missing. One of them required. |
| Expl. | Neither JOB-NAME nor JOB-ID / JOB-NUMBER have been specified. At least one of them is required to process the request. |
| Actn. | Specify JOB-NAME, JOB-ID or JOB-NUMBER with the request. |

NAT5714: Unable to read :1: type SYSOUT datasets.

| | |
|-------|---|
| Text | ESY5714 Unable to read :1: type SYSOUT datasets. |
| Expl. | The specified spool file TYPE is invalid or can not be processed. |
| Actn. | Specify a valid spool file type (CC, JL, SI, SM or SO). |

NAT5715: Duplicate jobnames found. Please specify job id.

| | |
|-------|--|
| Text | ESY5715 Duplicate jobnames found. Please specify job id. |
| Expl. | Multiple jobs were found for the specified job name. |
| Actn. | Additionally specify job id / job number. |

NAT5717: GENCB for ACB or RPL failed with RC:1:and RSN:2:

| | |
|-------|---|
| Text | ESY5717 GENCB for ACB or RPL failed with RC:1:and RSN:2:. |
| Expl. | An ACB or RPL could not be generated to access a SYSOUT dataset. |
| Actn. | Check with systems programmer. Contact Software AG technical support. |

NAT5719: Unable to :1: SYSOUT dataset.

| | |
|-------|---|
| Text | ESY5719 Unable to :1: SYSOUT dataset. |
| Expl. | An error occurred during open or close of a SYSOUT dataset. |
| Actn. | Check with systems programmer. Contact Software AG technical support. |

NAT5720: Invalid TYPE.

| | |
|-------|---|
| Text | ESY5720 Invalid TYPE. |
| Expl. | An invalid TYPE was given in the READ-SPOOL view. |
| Actn. | Check source program. Valid values for TYPE are: in MVS: JL, SI, SO, SM and CC. in VSE: LS, PU, RD, XM, CC. |

NAT5721: Job found, but not for specified spool ID.

| | |
|-------|--|
| Text | ESY5721 Job found, but not for specified spool ID. |
| Expl. | The job was found on a different spool than the one specified. |
| Actn. | No action is required. |

NAT5722: Requested data set not found.

| | |
|-------|---|
| Text | ESY5722 Requested data set not found. |
| Expl. | The requested dataset could not be found. |
| Actn. | No action is required. |

NAT5723: Job not in output service.

| | |
|-------|---|
| Text | ESY5723 Job not in output service. |
| Expl. | The requested job is not in output service. |
| Actn. | No action is required. |

NAT5724: Requested job not found.

| | |
|-------|--|
| Text | ESY5724 Requested Job not found. |
| Expl. | The requested job could not be found on the JES spool. |
| Actn. | No action is required. |

NAT5725: I/O error on JES3 spool.

| | |
|-------|--|
| Text | ESY5725 I/O error on JES3 spool. |
| Expl. | A READ request to the JES spool failed. |
| Actn. | Retry. If the error persists, this is probably a hardware error. |

NAT5726: Logical error on JES3 spool.

| | |
|-------|--|
| Text | ESY5726 Logical error on JES3 spool. |
| Expl. | A logical error occurred while reading the JES3 spool dataset. |
| Actn. | Notify systems programmer. Software AG technical support should be notified as well. |

NAT5727: Spanned record is too large.

| | |
|-------|--------------------------------------|
| Text | ESY5727 Spanned record is too large. |
| Expl. | A spanned record is too large. |
| Actn. | No action is required. |

NAT5728: You are not allowed to see this job.

| | |
|-------|--|
| Text | ESY5728 You are not allowed to see this job. |
| Expl. | The user attempted to access a job for which he has not been authorized. This error is issued by the security system with which Entire System Server interfaces. |
| Actn. | No action is required. |

NAT5729: Invalid job TYPE, specify JOB, STC or TSU.

| | |
|-------|--|
| Text | ESY5729 Invalid job TYPE, specify JOB, STC or TSU. |
| Expl. | The specified job TYPE is invalid. |
| Actn. | Specify a valid job type (JOB, STC, or TSU). |

NAT5730: Unknown error during spool open.

| | |
|-------|--|
| Text | ESY5730 Unknown error during spool open. |
| Expl. | An unknown error occurred during spool open. |
| Actn. | Notify systems programmer and Software AG technical support. |

NAT5731: Error occurred during spool GET.

| | |
|-------|--|
| Text | ESY5731 Error occurred during spool GET. |
| Expl. | An error occurred during spool GET. |
| Actn. | Notify systems programmer and Software AG technical support. |

NAT5732: Account number missing.

| | |
|-------|----------------------------------|
| Text | ESY5732 Account number missing. |
| Expl. | Account number was not supplied. |
| Actn. | Check program and correct error. |

NAT5733: User ID does not exist.

| | |
|-------|--|
| Text | ESY5733 No JOIN entry found for user. |
| Expl. | The user is not defined in the system. |
| Actn. | No action is required. |

NAT5734: ARCHIVE run with errors.

| | |
|-------|---|
| Text | ESY5734 ARCHIVE run with errors. |
| Expl. | An error occurred during ARCHIVE execution. |
| Actn. | Check with systems programmer. |

NAT5735: Logical error using I-T-C.

| | |
|-------|--|
| Text | ESY5735 Logical error using I-T-C. |
| Expl. | The inter-task-communication was not used correctly. |
| Actn. | No action is required. |

NAT5736: MESSAGE-ID missing.

| | |
|-------|-------------------------------|
| Text | ESY5736 MESSAGE-ID missing. |
| Expl. | No MESSAGE-ID value supplied. |
| Actn. | Specify a MESSAGE-ID. |

NAT5737: No more index space for inserting record.

| | |
|-------|--|
| Text | ESY5737 No more index space for inserting record. |
| Expl. | The number of records exceeds the available index range. |
| Actn. | No action required. |

NAT5738: Error when using memory-pools.

| | |
|-------|---|
| Text | ESY5738 Error when using memory-pools. |
| Expl. | Incorrect use of the MAIN-STORAGE view. |
| Actn. | No action is required. |

NAT5739: Error when using Job Variables.

| | |
|-------|---|
| Text | ESY5739 Error when using Job Variables. |
| Expl. | Incorrect use of JOB-VARIABLES view. More details are available in SYSTEM-MESSAGE-CODE. |
| Actn. | Please analyze the SYSTEM-MESSAGE-CODE. |

NAT5740: Error when using BTAM file.

| | |
|-------|--|
| Text | ESY5740 Error when using BTAM file. |
| Expl. | An error occurred while allocating a file. |
| Actn. | No action is required. |

NAT5741: Error when using SAM file.

| | |
|-------|--|
| Text | ESY5741 Error when using SAM file. |
| Expl. | An error occurred while allocating a file. |
| Actn. | No action is required. |

NAT5742: Error when using PAM file.

| | |
|-------|--|
| Text | ESY5742 Error when using PAM file. |
| Expl. | An error occurred while allocating a file. |
| Actn. | No action is required. |

NAT5743: Error when using ISAM file.

| | |
|-------|--|
| Text | ESY5743 Error when using ISAM file. |
| Expl. | An error occurred while allocating a file. |
| Actn. | No action is required. |

NAT5744: Invalid Eventing name given.

| | |
|-------|---|
| Text | ESY5744 Invalid eventing name given. |
| Expl. | An invalid eventing name was specified. |
| Actn. | No action is required. |

NAT5745: Error occurred when executing Eventing.

| | |
|-------|---|
| Text | ESY5745 Error occurred when executing Eventing. |
| Expl. | Logical error using P1-Eventing. |
| Actn. | Contact your systems programmer. |

NAT5746: Serialisation running in error.

| | |
|-------|--|
| Text | ESY5746 Serialisation running in error. |
| Expl. | A serialization request has failed. Detailed information available in SYSTEM-MESSAGE-CODE. |
| Actn. | Repeat the request later. |

NAT5747: LENGTH or SUBSTRING-LENGTH invalid.

| | |
|-------|--|
| Text | ESY5747 LENGTH or SUBSTRING-LENGTH invalid. |
| Expl. | Invalid value specification for view JOB-VARIABLES. Possible reasons: - position greater than length of JV - substring length greater than JV length minus position - position greater than JV length |
| Actn. | Correct values and try again. |

NAT5748: Internal LMS error has occurred.

| | |
|-------|--|
| Text | ESY5748 Internal LMS error has occurred. |
| Expl. | An internal LMS error has been returned from LMS subprogram interface. Check SYSTEM-MESSAGE-CODE for details. |
| Actn. | Please check SYSTEM-MESSAGE-CODE. |

NAT5749: PVS (CATID) not available.

| | |
|-------|---|
| Text | ESY5749 PVS (CATID) not available. |
| Expl. | The requested CATID is not available for the User ID of caller. |
| Actn. | No action possible. |

NAT5750: Invalid operand within operand list.

| | |
|-------|--|
| Text | ESY5750 Invalid operand within operand list. |
| Expl. | Incorrect usage of an Entire System Server view. |
| Actn. | No action is required. |