

List View Control Attributes Window

▶ Accessible Using

1. Double-click on the list view control; or
 2. if selected: "Control > Attributes" or by selecting "Attributes..." from the control's context menu or from the control's context menu.
 3. if selected: ENTER.
-

Entries

Note:

For context-sensitive help on attribute entries, select the entry so it has the focus, and press F1.

Entry in Attributes Window	Represents
Name	Handle name of the list view control (may be overwritten with another name).
Attributes...	Subordinate window for editing the list view control's attribute values. For more information, see <i>List View Control Attributes Subwindow</i> .
Columns:	Displays the titles of the list view columns already created. If you select an item in this list, its attributes are displayed for editing. You can also select several items for cutting and pasting.
New	Creates a new column.
Cut	Cuts a selected item and copies it to the clipboard. You can also cut and paste several items at once.
Paste	Pastes one or more columns from the clipboard. Note: The "New" and "Paste" entries insert columns behind the currently selected item, or, if no items are selected, at the top of the list. You deselect items by holding down CTRL while selecting the selected items.
Selected column	In this group frame, you assign attribute values to the column selected in the "Columns" list box on the left.
Name	Handle name of the column (may be overwritten with another name).
String	STRING attribute value. Specifies the column's title.
...	Dialog box for determining sources of STRING attribute values.
Format	FORMAT attribute value. Specifies the column's data format type and length.
Edit Mask	EDIT-MASK attribute value. Specifies the edit mask (if any) used to display values within the column.

Entry in Attributes Window	Represents
Width	RECTANGLE-W attribute value. Specifies the column width (in pixels).
Alignment:	
Left	STYLE attribute value. Column title is left aligned.
Center	STYLE attribute value. Column title is centered. Note: This option has no effect on the primary column, which is always left aligned.
Right	STYLE attribute value. Column title is right aligned. Note: This option has no effect on the primary column, which is always left aligned.
Sorting:	
Case insensitive	STYLE attribute value. Alphanumeric columns are sorted case-insensitively.
Word compare	STYLE attribute value. Alphanumeric columns are sorted using a lexical compare that treats hyphens and apostrophes differently such that words such as "coordinate" and "co-ordinate" stay together in a sorted list.
State:	
Visible	VISIBLE attribute value. If checked, the column will be shown.
Events	Dialog box for editing the column's event handlers.
OK	Save settings and exit the window.
Cancel	Exit the window without saving the settings.
Help	Provides online help on the attributes window.