

\*\*\*\*\* READ\_NSC.TXT \*\*\*\*\*

\*

\* Product: Natural Security  
\* Platform: WINDOWS  
\* Version: 9.1.1 PL 0  
\* Date of creation: 2018-10-12

\*

\* Software AG  
\* Uhlandstrasse 12  
\* D-64297 Darmstadt  
\* Germany

\*

\* Telephone: +49-6151-92-0  
\* Fax: +49-6151-92-1191

\*

\*\*\*\*\*

Table of Contents

- 1. Installation
  - 1.1. FSEC Database Definition
  - 1.3. Completing the Installation
  - 1.4. Setting Up Natural Security
  - 1.4. Uninstall
- 2. Changes and Enhancements
- 3. Known Issues
- 4. Restrictions
- 5. Documentation Changes

1. Installation  
=====

Natural Security 9.1.1 is available as a

- runtime-only environment for use with Natural Runtime 9.1.1,
- full version including runtime and security administration for use with Natural 9.1.1 development environment.

Natural Security 9.1.1 is based on the functionality of the related Mainframe (8.2.6) Version.

The installation of Natural Security Version 9.1.1 PL 0 requires Natural Version 9.1.1 PL 0.

Before you begin to install Natural Security using the Software AG Installer, read the sections below which are included in the Natural Installation documentation.

1.1. FSEC Database Definition  
=====

The Natural Security FSEC must be an Adabas database. This is defined in

the Global Configuration File, DBMS Assignments, with TYPE=ADA for the FSEC DBID. With the Natural Configuration Utility you may manually make this entry for your FSEC DBID, or it will be entered automatically during the configuration of Natural Security. For further details, see section 'Setting Up the FSEC System File for Natural Security'.

## 1.2. Completing the Installation

=====

After you have installed Natural or Natural Security, you need to set up a number of parameters and individual settings depending on your environment. To do so, you invoke the SYSPCI (Product Configuration and Initialization) utility. For further details, see section 'Configuring the Installed Products with the SYSPCI Utility'.

## 1.3. Setting Up Natural Security

=====

If you have completed the Natural Security installation and if you have installed the full version of Natural Security for the very first time some further steps are required, read section 'Setting Up Natural Security'.

If you have completed the Natural Security runtime installation, no further steps are required.

## 1.4. Uninstall

=====

Once it has been set up, Natural Security cannot be removed from a Natural installation. In order to remove Natural Security, you must uninstall Natural completely. For further details, see section 'Uninstalling Natural'.

## 2. Changes and Enhancements

=====

The LOGON message "NAT1691 Your password will expire on .." is enabled again.

The Natural utilities SYSMAIN and MAINUSER support the Natural Security option 'Library FDIC Assignment Enabled'.

See 'Release Information for Natural Version 9.1.1' section 'Natural Security'.

## 3. Known Issues

=====

For the list of solved problems see the READ\_NSC.FIX.

## 4. Restrictions

=====

5. Documentation Changes

=====

See 'Release Information for Natural Version 9.1.1' section 'Natural Security'.

(c) Copyright 1992 - 2018 Software AG, Darmstadt, Germany and/or Software AG USA Inc., Reston, VA, USA, and/or its subsidiaries and or/its affiliates and/or their licensors.