

webMethods EntireX

Installing Broker Stubs under OpenVMS

Version 9.7

October 2014

This document applies to webMethods EntireX Version 9.7.

Specifications contained herein are subject to change and these changes will be reported in subsequent release notes or new editions.

Copyright © 1997-2014 Software AG, Darmstadt, Germany and/or Software AG USA, Inc., Reston, VA, USA, and/or its subsidiaries and/or its affiliates and/or their licensors.

The name Software AG and all Software AG product names are either trademarks or registered trademarks of Software AG and/or Software AG USA, Inc. and/or its subsidiaries and/or its affiliates and/or their licensors. Other company and product names mentioned herein may be trademarks of their respective owners.

Detailed information on trademarks and patents owned by Software AG and/or its subsidiaries is located at <http://softwareag.com/licenses>.

Use of this software is subject to adherence to Software AG's licensing conditions and terms. These terms are part of the product documentation, located at <http://softwareag.com/licenses/> and/or in the root installation directory of the licensed product(s).

This software may include portions of third-party products. For third-party copyright notices, license terms, additional rights or restrictions, please refer to "License Texts, Copyright Notices and Disclaimers of Third-Party Products". For certain specific third-party license restrictions, please refer to section E of the Legal Notices available under "License Terms and Conditions for Use of Software AG Products / Copyright and Trademark Notices of Software AG Products". These documents are part of the product documentation, located at <http://softwareag.com/licenses> and/or in the root installation directory of the licensed product(s).

Use, reproduction, transfer, publication or disclosure is prohibited except as specifically provided for in your License Agreement with Software AG.

Document ID: EXX-INSTALL-97-20160805OVMS

Table of Contents

1 Installing Broker Stubs under OpenVMS 1

 Prerequisites 2

 Installation Steps 2

 Installation Verification 3

1 Installing Broker Stubs under OpenVMS

■ Prerequisites	2
■ Installation Steps	2
■ Installation Verification	3

See also *Administration of Broker Stubs under OpenVMS*.

Prerequisites

The following prerequisites apply to the EntireX package on OpenVMS:

- HP Integrity Server
- OpenVMS 8.3-1H1, Update V8.0
- OpenVMS 8.4, Update V6.0
- HP TCP/IP Services for OpenVMS
- HP SSL V1.4-334

Installation Steps

➤ To install EntireX under OpenVMS

- 1 Mount the CD-ROM.
- 2 Check whether the logical sag\$root is set. If not, define sag\$root as concealed device to the directory used for installing Software AG products. Example:

```
DEFINE/TRANSLATION_ATTRIBUTES=CONCEALED SAG$ROOT SAG$DEVICE:[SAG.]
```

- 3 Restore the delivered EntireX backup saveset to sag\$root directory. The backup saveset can be found in the VMS subdirectory of the CD-ROM. Example:

```
BACKUP/LOG CD-DEVICE:[VMS]EXX_V8020.BCK/SAVE SAG$DEVICE:[SAG...]*.*
```

- 4 Change the default directory to "sag\$root:[exx.v802.install]".
- 5 Run the installation script `install.com`.
 - The file `SAG$ROOT:[EXX]login.com` is created.
 - Environment files are created in `SAG$ROOT:[EXX.V802.INSTALL]`.
- 6 To set the environment, execute either `SAG$ROOT:[EXX]LOGIN.COM` or `SAG$ROOT:[EXX.V802.INSTALL]EXXENV.COM`.

Installation Verification

This section assumes you have installed EntireX Broker on the target node and it is up and running.

➤ **To verify the installation of the EntireX package on OpenVMS**

- 1 Start up two user sessions.
- 2 To ensure that the environment has been setup, enter the commands:

```
SHOW LOGICAL ETBLNK
SHOW LOGICAL EXX$LIBRARY
SHOW LOGICAL EXX$EXAMPLES
SHOW LOGICAL EXXDIR
SHOW SYMBOL EXXVERS
```

- 3 Run the setup procedure `@EXX$EXAMPLES:SETUP_EXAMPLES.COM` on both user sessions.
- 4 Run the following two example programs, one on each of the user sessions.

```
bcos -i<REPEATS> -b<BROKER-ID> -2
bcoc -i<REPEATS> -b<BROKER-ID> -2
```

Verification Example

In the following example, both programs are run on the local node, using two user sessions. The `BROKER-ID` is a combination of the hostname (where the EntireX broker is running) and the port number. The `REPEATS` value is 100. The value "-2" indicates that the Broker is Version 2.1.1 or above.

```
bcos -i100 -bhost1:1971 -2
bcoc -i100 -bhost1:1971 -2
```

The `BROKER-ID` should be set up as a TCP/IP service. For an example of how to set up this service, see `EXXDIR:[v802.bin]set_service.com`.

