

ADAMTR Utility Error Messages

Overview of Messages

ERROR-121	ERROR-122	ERROR-123	ERROR-124	ERROR-125	ERROR-126
ERROR-127	ERROR-128	ERROR-129	ERROR-130	ERROR-131	ERROR-132
ERROR-133	ERROR-134				

ERROR-121 **Parameter MTYPE must be set to ETBROKER or MQSERIES**

Explanation An invalid value was specified for the MTYPE parameter of the ADAMTR utility.

Action Check the parameter input, correct the error, and rerun the job.

ERROR-122 **Parameter ETBROKERID must be specified when MTYPE=ETBROKER** **Parameter ETBSERVICE must be specified when MTYPE=ETBROKER** **Parameter ETBSERVICENAME must be specified when MTYPE=ETBROKER** **Parameter ETBSERVICECLASS must be specified when MTYPE=ETBROKER** **Parameter MQQNAME must be specified when MTYPE=MQSERIES** **Parameter MQQMGRNAME must be specified when MTYPE=MQSERIES**

Explanation The listed, required parameters are missing for the selected MTYPE.

Action Check the parameter input, correct the error, and rerun the job.

ERROR-123 **ETBROKER parameters may not be specified when MTYPE=MQSERIES** **MQSeries parameters may not be specified when MTYPE=ETBROKER**

Explanation Improper parameters have been specified for the selected MTYPE.

Action Check the parameter input, correct the error, and rerun the job.

ERROR-124 **Load failed for {ADAETB|ADAMQS}**

Explanation The module listed could not be loaded by the job.

Action Check the job output or JCL, correct the error, and rerun the job.

ERROR-125 **INIT call failed. Return code *rcrc*, Reason code *reason***

Explanation The INIT call failed for the selected MTYPE.

Action Check the job output or JCL, correct the error, and rerun the job.

ERROR-126 **CONNECT call failed**
“Return-code” “reason-code” “messaging-system-return-code”
“messaging-system-reason-code”

Explanation The CONNECT call failed for the selected MTYPE.

Action Check the job output or JCL, correct the error, and rerun the job.

ERROR-127 **OPEN call failed.**
“Return-code” “reason-code” “messaging-system-return-code”
“messaging-system-reason-code”

Explanation The OPEN call failed for the selected MTYPE.

Action Check the job output or JCL, correct the error, and rerun the job.

ERROR-128 **RECEIVE call failed.**
“Return-code” “reason-code” “messaging-system-return-code”
“messaging-system-reason-code”

Explanation The RECEIVE call failed for the selected MTYPE.

Action Check the job output or JCL, correct the error, and rerun the job.

ERROR-129 **BACKOUT call failed.**
“Return-code” “reason-code” “messaging-system-return-code”
“messaging-system-reason-code”

Explanation The BACKOUT call failed for the selected MTYPE.

Action Check the job output or JCL, correct the error, and rerun the job.

ERROR-130 **COMMIT call failed.**
“Return-code” “reason-code” “messaging-system-return-code”
“messaging-system-reason-code”

Explanation The COMMIT call failed for the selected MTYPE.

Action Check the job output or JCL, correct the error, and rerun the job.

ERROR-131 **CLOSE call failed.**
 “Return-code” “reason-code” “messaging-system-return-code”
 “messaging-system-reason-code”

Explanation The CLOSE call failed for the selected MTYPE.

Action Check the job output or JCL, correct the error, and rerun the job.

ERROR-132 **DISCONNECT call failed.**
 “Return-code” “reason-code” “messaging-system-return-code”
 “messaging-system-reason-code”

Explanation The DISCONNECT call failed for the selected MTYPE.

Action Check the job output or JCL, correct the error, and rerun the job.

ERROR-133 **TERM call failed. Return code xxxxxxxx Reason code xxxxxxxx**

Explanation The TERM call failed for the selected MTYPE.

Action Check the job output or JCL, correct the error, and rerun the job.

ERROR-134 **Parameter PRINT must be set to YES or NO**

Explanation An invalid value was specified for the PRINT parameter of the ADAMTR utility.

Action Check the parameter input, correct the error, and rerun the job.