

# Invoking and Terminating the DDM Editor

The DDM editor is used to edit the source of a DDM.

This section describes how to invoke and terminate the DDM editor for an existing DDM by using either the **DDM Maintenance** menu of DDM Services, or the Natural system command EDIT.

- Invoking the Editor with DDM Maintenance
  - Invoking the Editor with EDIT
  - Terminating the Editor
- 

## Invoking the Editor with DDM Maintenance

### ► To invoke the DDM editor from DDM Maintenance

- In the DDM maintenance window, next to the DDM to be edited, enter the function code E.

The source code of the specified DDM is read into the editing area of the DDM editor.

If the Adabas or SQL database referenced by the specified DDM is available and a database file with the specified file number exists, a screen similar to the example below appears; if not, an empty screen is displayed instead.

```

17/09/2004          DDM Services
12:44:43          V 6.1.1 Pl 9 Software AG 2004      Line: 1
DBID: 20    FNR: 14    DDM: EMPLOYEES      DEF. SEQ.:
C   T      L Name          F  Length  S  D
      1 PERSONNEL-ID        A     8      D
*
*      CNNNNNNN
G      1 FULL-NAME
      2 FIRST-NAME        A     20      N
      2 MIDDLE-I           A      1      N
      2 NAME               A     20      D
      1 MIDDLE-NAM          A     20      N
      1 MAR-STAT            A      1      F
*
*      M=MARRIED
      1 SEX                A      1      F
      1 BIRTH              N   06.0      D
      1 N@BIRTH             I      2      D
G      1 FULL-ADDRESS
M      2 ADDRESS-LINE       A     20      N
      2 CITY                A     20      N  D
      2 ZIP                 A     10      N
      2 POST-CODE            A     10      N
      2 COUNTRY              A      3      N
F1 HELP  F2 CHOICE F3 STOW+EXIT      F10 STOW      F11 CHECK
F12 DB-SHORT-NAMES  F13 MODIFY HEADER  F14 SHOW EXT FIELD  F15

```

If the Tamino database referenced by the specified DDM is available and a database file with the specified file number exists, a screen similar to the example below appears; if not, an empty screen is displayed instead:

01/10/2004	DDM Services	
11:05:45	V 6.1.1 Pl 9	Software AG 2004
DBID: 175	FNR: 1	DDM: DDM_TEST
		Line: 1
C T L Name	F	Length D
G 1 EMPLOYEE		
G 2 GROUP\$1		
3 PERSONNEL-ID	A	8 D
G 2 GROUP\$2		
G 3 FULL-NAME		
G 4 GROUP\$3		
5 FIRST-NAME	A	20 D
5 MIDDLE-NAME	A	20 D
5 MIDDLE-I	A	20 D
5 NAME	A	20 D
3 MAR-STAT	A	1 D
3 SEX	A	1 D
3 BIRTH	A	10 D
G 3 FULL-ADDRESS		
G 4 GROUP\$4		
5 ADDRESS-LINE	A	20
5 CITY	A	20 D
5 ZIP	A	20 D
F1 HELP F2 CHOICE F3 STOW+EXIT	F10 STOW	F11 CHECK
F12 DOCTYPE INFO	F13 MODIFY HEADER	F14 SHOW EXT FIELD
		F15

For information on the fields and commands provided in the DDM editor, see the section *Using the DDM Editor Screen*.

## Invoking the Editor with EDIT

As an alternative to using DDM Services functions, you can invoke the DDM editor with the Natural system command EDIT.

### ► To invoke the DDM editor with EDIT

- From the Natural main menu, choose **Direct** and, in the **Direct Command** window, enter the following:

```
EDIT VIEW object-name
```

where *object-name* denotes the name of the DDM to be edited.

The DDM editor is invoked for the DDM specified and the DDM source is read into the editing area.

For information on all options available with EDIT, see the relevant section in the *System Commands* documentation.

## Terminating the Editor

This section describes how to terminate an editor session and return to the DDM maintenance window.

## ► To terminate the DDM editor

- After editing, saving and cataloging the DDM source (see *Using the DDM Editor Screen* and *Saving and Cataloging a DDM*), on the DDM editor screen, press ESC.

The DDM editor menus **COMMANDS**, **MISC** and **QUIT** (see also the section *Commands*) appear at the top of the DDM editor screen as shown in the example below:

COMMANDS		MISC		QUIT		
14:22:37		V 6.1.1 Pl 7	Software AG 2004			Line: 1
DBID: 20	FNR: 14	DDM: EMPLOYEES				DEF. SEQ.:
C T	L Name			F Length	S D	
	1 PERSONNEL-ID			A 8		D
*	CNNNNNNN					
G	1 FULL-NAME					
	2 FIRST-NAME			A 20	N	
	2 MIDDLE-I			A 1	N	
	2 NAME			A 20		D
	1 MIDDLE-NOME			A 20	N	
	1 MAR-STAT			A 1	F	
*	M=MARRIED					
	1 SEX			A 1	F	
	1 BIRTH			N 06.0		D
	1 N@BIRTH			I 2		D
G	1 FULL-ADDRESS					
M	2 ADDRESS-LINE			A 20	N	
	2 CITY			A 20	N	D
	2 ZIP			A 10	N	
	2 POST-CODE			A 10	N	
	2 COUNTRY			A 3	N	
F1 HELP F2 CHOICE F3 STOW+EXIT			F10 STOW			F11 CHECK
Select a Command						

- Select the **QUIT** menu and choose **EXIT (with STOW)** or **QUIT (without STOW)** to leave the DDM source as described in *QUIT Menu*.

The DDM maintenance window appears.