

# Display General Database Layout

Option "G" displays general database information on the Display General DB-Layout screen:

```

15:43:07          ***** A D A B A S  BASIC  SERVICES  *****          2005-11-22
DBID 105          - Display General DB-Layout -          PDRG002

Isolated
Database Name ..... RD-105
Database Number ..... 105
Database Version ..... 7.1
Database Load Date ..... 2005-11-22 14:40:47
System Files ..... 19 , 0 , 0 , 0 , 0 , 0 , 0 , 0 , 0
Maximum Number of Files .. 100
Number of Files Loaded ... 5
Highest File Loaded ..... 75
Trigger File Number ..... 14
Size of RABN ..... 4 Bytes
Current Log Tape Number .. 5
Delta Save Facility ..... Inactive
Recovery Aid Facility .... Inactive
Universal Encoding Sup. .. Yes

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit          Menu

```

You can display additional information about UES codes, coupling, and space allocations by pressing ENTER.

The equivalent direct command is

```
DISPLAY DBLAYOUT
```

The Display General DB Layout screen displays the following information for the file:

- the name and number of the database;
- the version level of the Adabas database software;
- the date and time the database was loaded;
- the numbers of Adabas system files allocated to the database;
- the maximum number of files permitted for the database; the total number of files currently loaded; and the highest file number currently in use;
- whether 3- or 4-byte RABNs are being used for the file;

- the number of the most recent data protection log tape for the database;
- whether the Adabas Delta Save Facility and/or the Adabas Recovery Aid (ADARAI) are active or inactive for the database.
- whether universal encoding support (UES) is being used.

When universal encoding support (UES) is being used, pressing ENTER from the initial Display File Layout screen lists the current code values:

```

15:51:22          ***** A D A B A S  BASIC  SERVICES  *****      2005-11-22
DBID 105          - Display General DB-Layout -                          PDRG002

Universal Encoding Support Enabled

UES Encoding Keys:
Alpha File Encoding ..... 37
Wide File Encoding ..... 4095
Alpha ASCII Encoding ..... 437
Wide User Encoding ..... 4095
    
```

In any case, pressing ENTER from the initial Display File Layout screen displays the following space allocation and usage information:

```

15:52:01          ***** A D A B A S  BASIC  SERVICES  *****      2005-11-22
DBID 105          - Display General DB-Layout -                          PDRG002

      IDeviceI      Total Number of I      Extents  in Block  I DD-Names I
      I Type I      Blocks / Cyls. I      From      To      I      I
-----I-----I-----I-----I-----I-----I-----I-----I
      I      I      I      I      I      I      I      I      I
ASSO I 3380 I      14231      50 I      1      14231 I DDASSOR1 I
      I      I      I      I      I      I      I      I      I
DATA I 3380 I      6741      50 I      1      6741 I DDDATAR1 I
      I      I      I      I      I      I      I      I      I
WORK I 3380 I      3592      30 I      1      3592 I DDWORKR1 I

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit          Menu
    
```