

Display or Modify Parameters

▶ To view Adabas nucleus (ADARUN) parameters

1. Choose option "D" from the Session Monitoring menu and press ENTER.

The equivalent direct command is

```

DISPLAY PARAMETERS

11:13:03          ***** A D A B A S  BASIC SERVICES  *****          2005-11-14
DBID 1955                - Display Parameters -                          PACP002

Modify parameters below, as required:
----- Miscellaneous -----
ReadOnly session (READONLY) .. NO
UTI only session (UTIONLY) .. NO
OPEN required (OPENRQ) .. NO
Ignore DIB Entry (IGNDIB) .. NO
Local nucleus (LOCAL) .. NO
Number of Threads (NT) .. 5
Non DE Search (NONDES) .. YES
Log AOS/DBS Update (AOSLOG) .. NO
Batch Support (BATCH) .. NO
Data Protection Area (LP) .. 1000
Ignore Work Part 4 (IGNTPC) .. NO
WORK-Part-4 Area (LDTP) .. 0
WORK-Part-2 Area (LWKP2) .. 104
SVC (SVC) .. 249
----- User Specific Limits -----
Hold Queue Limit (NISNHQ) .. 2000
CIDs per User (NQCID) .. 40
ISNs / TBI Element (NSISN) .. 1000
----- Buffer Pool -----
Bufferflush Dur. (TFLUSH) .. 1
Parallel LFIOP I/O (FMXIO) .. 1
Async. by Vol-Ser (ASYTVS) .. YES
----- Replication -----
Replication (REPLICATION) ... YES

Page 1 of 3
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help                Exit                +                Menu

```

▶ To modify Adabas nucleus (ADARUN) parameters

1. Choose option "P" from the Session Monitoring menu and press ENTER.

Modifiable values are highlighted (intensified) on the displays.

The equivalent direct command is

```

MODIFY PARAMETERS

```

Three screens are used for displaying and modifying parameters:

