

Entire Net-Work Abend Codes

The abend (abnormal end) codes described in this chapter are issued primarily by Adabas modules operating with Entire Net-Work. Entire Net-Work itself issues only the abend code 253 to indicate an abnormal termination occurred. The specific termination information is given in the messages written to the print data set.

The following abend codes are identical to the Adabas Abend Codes listed in the *Adabas Messages and Codes* manual:

Code	Module	Explanation
214	MPMGCS	UNSUCCESSFUL STATE
215	MPMGCS	INVALID OPERATING SYSTEM
216	MPMGCS	INVALID FUNCTION
221	MPMDOS	INVALID OPERATING SYSTEM
222	MPMDOS	INVALID FUNCTION
227	MPMBS2	WRONG ADARER MODULE FOUND
228	MPMBS2	STXIT NOT SUCCESSFULLY INSTALLED
229	MPMBS2	INVALID FUNCTION
230	MPMBS2	INVALID ROUTER 40-CALLER
231	MPMBS2	CALLER NOT CORRECT TARGET
232	MPMBS2	INVALID IDT
247	MPMMVS	UNSUCCESSFUL STAE
248	MPMMVS	INVALID OPERATING SYSTEM OR RMODE
	MPMF4	INVALID OPERATING SYSTEM, RMODE, OR CID GETMAIN FAILED
249	MPMMVS	INVALID FUNCTION
252	IORSUB	ADABAS SUBTASK ABEND. See the ADAM90 message
253	MPMIND	NONRECOVERABLE ABEND (caused by STAE/STXIT processing program check or nucleus ABEND)
254	MPMIND	INVALID FUNCTION IN ABNORMAL TERMINATION RECOVERY EXIT
255	MPMIND	INVALID FUNCTION
443	RTRGCS	INVALID 40-CALLER
444	RTRGCS	CALLER NOT CORRECT TARGET
445	RTRGCS	NO IDT
446	RTRGCS	CALLER NOT AUTHORIZED
447	RTRGCS	INVALID 48-CALL PARAMETERS

Code	Module	Explanation
448	RTRGCS	INVALID 00-CALL PARAMETERS
449	RTRGCS	INVALID OPERATING SYSTEM
450	RTRGCS	INVALID FUNCTION
451	LNKGCS	UNSUPPORTED FUNCTION
452	LNKGCS	INVALID UB
453	LNKGCS	LENGTH OF USER INFO LT (less than) 0
454	LNKGCS	ERROR IN LINK INITIALIZATION ROUTINE
455	LNKGCS	INCORRECT ROUTER VERSION
456	LNKGCS	USER EXIT BEFORE CALL INCREASED LENGTH OF USER INFO
485	LNKBTO	UNSUPPORTED FUNCTION
486	SVCMVS	INVALID PCR04 CALL
487	SVCMVS	CALLER NOT CORRECT TARGET
488	SVCMVS	INVALID PCR16 CALL
489	SVCMVS	INVALID 48-CALL PARAMETERS
490	SVCMVS	INVALID 40-CALLER
491	SVCMVS	SVC 12-CALL WITHOUT 16-CALL REQUIRED
492	SVCMVS	ACTIVE DORMANT LX
493	SVCMVS	INVALID 00-CALL PARAMETERS
494	SVCMVS	CALLER NOT AUTHORIZED
495	SVCMVS	INVALID OPERATING SYSTEM
496	SVCMVS	NO IDT
497	SVCMVS	INVALID FUNCTION
498	LNKBTO	INVALID UB
499	LNKBTO	LENGTH OF USER INFO LESS THAN ZERO
500	LNKBTO	ERROR IN LINK INITIALIZATION ROUTINE
501	LNKBTO	INCORRECT ROUTER VERSION
502	LNKBTO	USER EXIT BEFORE CALL INCREASED LENGTH OF USER INFO
510	SSFENV	SSF INITIALIZATION ERROR
547	IOROS	NOT MVS/ESA OR z/OS SYSTEM; RMOD IS NOT 24; OR AMODE 31 IS NOT ALLOWED
549	IOROS/ IORGCS	DLECB ERROR

Code	Module	Explanation
550	IOROS	QEDIT (BLOCK) ERROR
559	IOROS	INCORRECT SVC VERSION
560	IOROS	MAXIMUM BLOCKS/TRACK > MINIMUM, I/O ERROR, GLOBAL SEQUENTIAL BLKSIZE TOO BIG, OR INVALID NUMBER (ECBS)
561	IOROS/ IORGCS	EVENTS ERROR
562	IOROS	PROGRAM LOADED ABOVE 16MEG
563	IORBS2	INVALID TDCE FOUND DURING ADAIOR INIT
564	IORBS2	FAILURE TO LOAD ADAIOI OR AT (when trying to) ENABLE CONTROL EVENT NAME
565	IORBS2	ECB LIST OVERFLOW
566	IORBS2	INVALID SOLSIG RETURN CODE
567	IORBS2	DDSCAN ERROR
570	IORBS2	CHKIO ERROR
571	IORBS2	INVALID ECB TYPE
575	IORBS2	ADARUN NUCLEUS EXTENSION NOT FOUND
576	IORBS2	INSUFFICIENT STORAGE FOR DATA AREA
583	IOROS	QEDIT (CIBCTR) ERROR
585	SVCMVS	PRB CANNOT BE FOUND
587	MGABTO	LOAD ERROR
588	MGABTO	ADAMAI ERROR
590	IORCMS	MAXIMUM BLOCKS/TRACK > MINIMUM, I/O ERROR
591	IODOS	EVENTS ERROR
592	IODOS	GETDVS ERROR
593	IODOS	IVST ERROR
595	IODOS	EXTRACT ERROR
596	IODOS	GETLBL ERROR
597	IODOS	TOPMSG ERROR
598	IOROS/ IORGCS	ADECB ERROR
599	IODOS	ADECB ERROR
600	IODOS	DLECB ERROR
601	IODOS	SUBSID ERROR, INVALID VERSION, OR ADAIOI COULD NOT BE LOADED

Code	Module	Explanation
602	IODOS	CKTDC ERROR
603	IODOS	GLOBAL SEQUENTIAL BLOCKSIZE TOO BIG OR INVALID NUMBER (ECBS)
604	IODOS	GETTVS ERROR
605	IODOS	INVALID PRINTER DEVICE
606	LNKBS2	UNSUPPORTED FUNCTION
607	LNKBS2	INVALID UB
608	LNKBS2	LENGTH OF USER INFO (LESS THAN) 0
609	LNKBS2	INCORRECT ROUTER VERSION
610	LNKBS2	USER EXIT BEFORE CALL INCREASED LENGTH OF USER INFO
611	LNKBS2	WAIT ERROR
612	RERBS2	NO IDT (identification table)
613	RERBS2	INVALID FUNCTION
614	SVCDOS	INVALID FUNCTION VIA CALLER
615	SVCDOS	NO IDT (identification table)
616	SVCDOS	INVALID 00-CALL PARAMETERS
617	SVCDOS	INVALID 40-CALLER
618	SVCDOS	CALLER NOT CORRECT TARGET
620	IORIND	IOR FATAL ERROR
621	IORIND	PLOG SIZE ALTERATION ERROR
622	LNKxx	INVALID SAVE AREA IN UB (UEXITB) SAVE area (USERSAV) in the Adabas link routine was less than 72 bytes and User Exit A/B was invoked.
627	IORGCS	NO VIRTUAL CONSOLE
800	NETSIP/OS	INVALID OPERATING SYSTEM DETECTED - NOT MVS
801	NETSIP/OS	PARAMETER ERROR DETECTED
802	NETSIP/OS	ADDRESSING OR RESIDENCY MODE, AUTHORIZATION ERROR OR OPERATING SYSTEM IS NOT A VIRTUAL MACHINE GUEST
803	NETSIP/OS	ERROR DETECTED DURING PROGRAM LOADING OR VALIDATION
804	NETSIP/OS	SPACE ALLOCATION FAILURE
806	NETSIP/OS	NETSIR INITIALIZATION FAILED