

Preparing for the Installation

This section of the documentation provides installation preparation information for Adabas Review 4.4 or above under BS2000 operating system environments.

The installation of Software AG products is performed by installation *jobs*, which are either created *manually* or generated by System Maintenance Aid (SMA).

For each step of the installation procedure described below, the job number of a job performing the respective task is indicated. This job number refers to an installation job generated by SMA. If you are not using SMA, a sample installation job of the same number is provided in the job library on the Natural installation tape; you must adapt this example job to your requirements.

For information about using Software AG's System Maintenance Aid (SMA) for the installation process, refer to the *System Maintenance Aid* documentation.

For installation with SMA please read #READ-ME.REV.

This chapter covers the following topics:

- Prerequisites
 - The Adabas Review Installation Tape
 - Installation Overview
-

Prerequisites

Operating System Level

Before installing this version of Adabas Review, ensure that you are running a currently-supported version of BS2000 OSD. For information on the BS2000 OSD versions supported by this release of Adabas Review, access Software AG's ServLine24 web site at <http://servline24.softwareag.com/public/>. In the left menu of this web page, expand My ServLine24 and log into Secured Services. Once you have logged in, you can expand Products in the left menu of the web page and select Product Roadmaps to access the Product Version Roadmaps application. This application allows you to review platform support information for specific Software AG products and releases.

Adabas Version Requirements

There are specific version requirements for Review 4.4 in both local and hub mode. See section *Review 4.4 Version Compatibility* in the *Review 4.4 Release Notes* for a detailed matrix of these version requirements.

Natural Version Requirements

Adabas Review version 4.4 supports Natural version 4.1.4 and above.

TP Monitor Support

Adabas Review version 4.4 requires one of the following TP monitors:

- TIAM
- UTM

The Adabas Review Installation Tape

The Adabas Review installation tape is a standard label tape with the volume serial number REV vrs , where the notation vrs represents the version, revision, and SM level of the product.

The installation tape contains the files listed below. The sequence of the files is shown in the "Report of Tape Creation" delivered with the installation tape.

File Name	Contents
REV vrs .INPL	Adabas Review Natural objects
REV vrs .MOD	Adabas Review module library
REV vrs .JOBS	Adabas Review installation jobs
REV vrs .SRC	Adabas Review source modules and more installation jobs
REV vrs .SYSF	Empty Adabas Review system file
REV vrs .ZAPS	Zaps required for Adabas Review on this platform

Note:

Throughout this documentation, the notation vrs stands for the version, revision, and system maintenance level of the Adabas Review being installed.

Installation Overview

Adabas Review is installed in two phases:

1. Phase 1: Install non-TP-specific components. All steps in this phase are identical regardless of the TP monitor in use:
 - Install Adabas Review under Natural;
 - Install the Adabas Review repository;
 - Install Adabas Review under Adabas;
 - Install the Adabas Review hub (hub mode only);
 - Optional installation procedures.

2. Phase 2: Install TP-specific components. Separate procedures are used to install Adabas Review under each of the supported TP monitors: TIAM, batch, and UTM.

Phase one procedures are described in *Installation: Phase 1*; phase two procedures in *Installation: Phase 2*.