

ADAMTR Error Messages

Overview of Messages

ERROR-121	ERROR-122	ERROR-123	ERROR-124	ERROR-125	ERROR-126
ERROR-127	ERROR-128	ERROR-129	ERROR-130	ERROR-131	ERROR-132
ERROR-133	ERROR-134				

ERROR-121 Parameter MTYPE must be set to ETBROKER or MQSERIES

Explanation An invalid value was specified for the MTYPE parameter of the ADAMTR utility.

Action Check the parameter input, correct the error, and rerun the job.

ERROR-122 Parameter ETBROKERID must be specified when MTYPE=ETBROKER
Parameter ETBSERVICE must be specified when MTYPE=ETBROKER
Parameter ETBSERVICENAME must be specified when TYPE=ETBROKER
Parameter ETBSERVICECLASS must be specified when MTYPE=ETBROKER
Parameter MQQNAME must be specified when MTYPE=MQSERIES
Parameter MQQMGRNAME must be specified when MTYPE=MQSERIES

Explanation The listed, required parameters are missing for the selected MTYPE.

Action Check the parameter input, correct the error, and rerun the job.

ERROR-123 ETBROKER parameters may not be specified when MTYPE=MQSERIES
MQSeries parameters may not be specified when MTYPE=ETBROKER

Explanation Improper parameters have been specified for the selected MTYPE.

Action Check the parameter input, correct the error, and rerun the job.

ERROR-124 Load failed for {ADAETB|ADAMQS}

Explanation The module listed could not be loaded by the job.

Action Check the job output or JCL, correct the error, and rerun the job.

ERROR-125 INIT call failed. Return code *rcrc*, Reason code *reason*

Explanation The INIT call failed for the selected MTYPE.

Action Check the job output or JCL, correct the error, and rerun the job.

ERROR-126 CONNECT call failed.

***“Return-code” “reason-code” “messaging-system-return-code”
“messaging-system-reason-code”***

Explanation The CONNECT call failed for the selected MTYPE.

Action Check the job output or JCL, correct the error, and rerun the job.

ERROR-127 OPEN call failed.

***“Return-code” “reason-code” “messaging-system-return-code”
“messaging-system-reason-code”***

Explanation The OPEN call failed for the selected MTYPE.

Action Check the job output or JCL, correct the error, and rerun the job.

ERROR-128 RECEIVE call failed.

***“Return-code” “reason-code” “messaging-system-return-code”
“messaging-system-reason-code”***

Explanation The RECEIVE call failed for the selected MTYPE.

Action Check the job output or JCL, correct the error, and rerun the job.

ERROR-129 BACKOUT call failed.

***“Return-code” “reason-code” “messaging-system-return-code”
“messaging-system-reason-code”***

Explanation The BACKOUT call failed for the selected MTYPE.

Action Check the job output or JCL, correct the error, and rerun the job.

ERROR-130 COMMIT call failed.

***“Return-code” “reason-code” “messaging-system-return-code”
“messaging-system-reason-code”***

Explanation The COMMIT call failed for the selected MTYPE.

Action Check the job output or JCL, correct the error, and rerun the job.

ERROR-131 CLOSE call failed.
“*Return-code*” “*reason-code*” “*messaging-system-return-code*”
“*messaging-system-reason-code*”

Explanation The CLOSE call failed for the selected MTYPE.

Action Check the job output or JCL, correct the error, and rerun the job.

ERROR-132 DISCONNECT call failed.
“*Return-code*” “*reason-code*” “*messaging-system-return-code*”
“*messaging-system-reason-code*”

Explanation The DISCONNECT call failed for the selected MTYPE.

Action Check the job output or JCL, correct the error, and rerun the job.

ERROR-133 TERM call failed. Return code xxxxxxxx Reason code xxxxxxxx

Explanation The TERM call failed for the selected MTYPE.

Action Check the job output or JCL, correct the error, and rerun the job.

ERROR-134 Parameter PRINT must be set to YES or NO

Explanation An invalid value was specified for the PRINT parameter of the ADAMTR utility.

Action Check the parameter input, correct the error, and rerun the job.