

ADAMTS Error Messages

Overview of Messages

ERROR-121	ERROR-122	ERROR-123	ERROR-124	ERROR-125	ERROR-126
ERROR-127	ERROR-128	ERROR-129	ERROR-130	ERROR-131	ERROR-132
ERROR-133					

ERROR-121 Parameter MTYPE must be set to ETBROKER or MQSERIES

Explanation An invalid value was specified for the MTYPE parameter of the ADAMTS utility.

Action Check the parameter input, correct the error, and rerun the job.

**ERROR-122 Parameter ETBROKERID must be specified when MTYPE=ETBROKER
 Parameter ETBSERVICE must be specified when MTYPE=ETBROKER
 Parameter ETBSERVICENAME must be specified when MTYPE=ETBROKER
 Parameter ETBSERVICECLASS must be specified when MTYPE=ETBROKER
 Parameter MQQNAME must be specified when MTYPE=MQSERIES
 Parameter MQQMGRNAME must be specified when MTYPE=MQSERIES**

Explanation The listed, required parameters are missing for the selected MTYPE.

Action Check the parameter input, correct the error, and rerun the job.

**ERROR-123 ETBROKER parameters may not be specified when MTYPE=MQSERIES
 MQSeries parameters may not be specified when MTYPE=ETBROKER**

Explanation Improper parameters have been specified for the selected MTYPE.

Action Check the parameter input, correct the error, and rerun the job.

ERROR-124 Open failed for file MTSIN

Explanation The file allocated by the MTSIN DD statement could not be opened.

Action Check the job output or JCL, correct the error, and rerun the job.

ERROR-125 Load failed for {ADAETB|ADAMQS}

Explanation The module listed could not be loaded by the job.

Action Check the job output or JCL, correct the error, and rerun the job.

ERROR-126	INIT call failed. Return code <i>rcrc</i>, Reason code <i>reason</i>
Explanation	The INIT call failed for the selected MTYPE.
Action	Check the job output or JCL, correct the error, and rerun the job.
ERROR-127	CONNECT call failed <i>“Return-code” “reason-code” “messaging-system-return-code”</i> <i>“messaging-system-reason-code”</i>
Explanation	The CONNECT call failed for the selected MTYPE.
Action	Check the job output or JCL, correct the error, and rerun the job.
ERROR-128	OPEN call failed. <i>“Return-code” “reason-code” “messaging-system-return-code”</i> <i>“messaging-system-reason-code”</i>
Explanation	The OPEN call failed for the selected MTYPE.
Action	Check the job output or JCL, correct the error, and rerun the job.
ERROR-129	SEND call failed. <i>“Return-code” “reason-code” “messaging-system-return-code”</i> <i>“messaging-system-reason-code”</i>
Explanation	The SEND call failed for the selected MTYPE.
Action	Check the job output or JCL, correct the error, and rerun the job.
ERROR-130	CLOSE call failed. <i>“Return-code” “reason-code” “messaging-system-return-code”</i> <i>“messaging-system-reason-code”</i>
Explanation	The CLOSE call failed for the selected MTYPE.
Action	Check the job output or JCL, correct the error, and rerun the job.
ERROR-131	DISCONNECT call failed. <i>“Return-code” “reason-code” “messaging-system-return-code”</i> <i>“messaging-system-reason-code”</i>
Explanation	The DISCONNECT call failed for the selected MTYPE.
Action	Check the job output or JCL, correct the error, and rerun the job.

ERROR-132 **TERM call failed. Return code xxxxxxxx Reason code xxxxxxxx**

Explanation The TERM call failed for the selected MTYPE.

Action Check the job output or JCL, correct the error, and rerun the job.

ERROR-133 **Read of MTSIN failed**

Explanation A problem occurred while attempting to read MTSIN. The cause is probably a JCL error.

Action Check the job output or JCL, correct the error, and rerun the job.