

# Adabas Manager Configuration

The Adabas Manager **Configuration** panel allows you to enter your license key for the Adabas Manager Enterprise Edition on mainframes and deactivate/activate the license for your version of Adabas on Open Systems; you also have to define the location for large output files of Adabas Manager's *Long Running Utilities*.

## ▶ To view the Adabas Manager Configuration panel:

1. Select **Adabas Manager** in tree-view and right-click it.
2. Select **Configuration** in the menu.

The Adabas Manager **Configuration** panel is displayed.

## ▶ To enter your Adabas Manager mainframe license key file:

1. Display the Adabas Manager **Configuration** panel.

The current license file name is displayed. If the license key field is empty, no license file is active and Adabas Manager is running in Standard Edition mode.

### **Note:**

Click **Display** in the **Configuration** panel to view a current license file text.

2. Click **Modify** to browse to the new license file and to activate it.
3. After selecting the new license key file click **OK** to activate it or **Cancel** to return to the **Configuration** panel.

## ▶ To deactivate your Adabas for Open Systems license:

1. Display the Adabas Manager **Configuration** panel.
2. Press **Deactivate** for the version you wish to deactivate.

The **Deactivate License** panel is displayed.

### **Caution:**

If you proceed with the deactivation, the license key will be deleted; before you confirm the deactivation, ensure that you have a copy of the license key in a safe location or you will not be able to activate your version of Adabas for Open Systems again.

3. Click **OK** or **Cancel** to return to the **Configuration** panel.

## ▶ To activate your Adabas for Open Systems license:

1. Display the Adabas Manager **Configuration** panel.
2. Press **Activate** for the version you wish to activate.

The **Activate License** panel is displayed.

3. Browse to the location where your license is stored.
4. Click **OK** or **Cancel** to return to the **Configuration** panel.

The System Management Hub job monitor receives the output of Adabas Manager's *Long Running Utilities*. In case of very large reports, Adabas Manager only sends the first and last lines to the job monitor; the complete output is written to the location defined in this panel. You can also modify the number of lines that should be displayed by the job monitor.

 **To modify the Job Monitor parameters:**

1. Display the Adabas Manager **Configuration** panel.
2. Press **Modify** and browse to a location where you want the output of the long running utilities to be written.
3. Enter the number of lines to be displayed by the job monitor (500 is the maximum value).
4. Click **OK** or **Cancel** to return to the **Configuration** panel.