

# ADAMTS Utility Error Messages

## Overview of Messages

|           |           |           |           |           |           |
|-----------|-----------|-----------|-----------|-----------|-----------|
| ERROR-121 | ERROR-122 | ERROR-123 | ERROR-124 | ERROR-125 | ERROR-126 |
| ERROR-127 | ERROR-128 | ERROR-129 | ERROR-130 | ERROR-131 | ERROR-132 |
| ERROR-133 |           |           |           |           |           |

---

### **ERROR-121    Parameter MTYPE must be set to ETBROKER or MQSERIES**

**Explanation**    An invalid value was specified for the MTYPE parameter of the ADAMTS utility.

**Action**            Check the parameter input, correct the error, and rerun the job.

### **ERROR-122    Parameter ETBROKERID must be specified when MTYPE=ETBROKER Parameter ETBSERVICE must be specified when MTYPE=ETBROKER Parameter ETBSERVICENAME must be specified when TYPE=ETBROKER Parameter ETBSERVICECLASS must be specified when MTYPE=ETBROKER Parameter MQQNAME must be specified when MTYPE=MQSERIES Parameter MQQMGRNAME must be specified when MTYPE=MQSERIES**

**Explanation**    The listed, required parameters are missing for the selected MTYPE.

**Action**            Check the parameter input, correct the error, and rerun the job.

### **ERROR-123    ETBROKER parameters may not be specified when MTYPE=MQSERIES MQSeries parameters may not be specified when MTYPE=ETBROKER**

**Explanation**    Improper parameters have been specified for the selected MTYPE.

**Action**            Check the parameter input, correct the error, and rerun the job.

### **ERROR-124    Open failed for file MTSIN**

**Explanation**    The file allocated by the MTSIN DD statement could not be opened.

**Action**            Check the job output or JCL, correct the error, and rerun the job.

### **ERROR-125    Load failed for {ADAETB|ADAMQS}**

**Explanation**    The module listed could not be loaded by the job.

**Action**            Check the job output or JCL, correct the error, and rerun the job.

|                    |  |
|--------------------|--|
| <b>ERROR-126</b>   | <b>INIT call failed. Return code <i>rcrc</i>, Reason code <i>reason</i></b>  |
| <b>Explanation</b> | The INIT call failed for the selected MTYPE.   |
| <b>Action</b>      | Check the job output or JCL, correct the error, and rerun the job.   |
| <b>ERROR-127</b>   | <b>CONNECT call failed</b><br><b><i>“Return-code” “reason-code” “messaging-system-return-code”</i></b><br><b><i>“messaging-system-reason-code”</i></b>     |
| <b>Explanation</b> | The CONNECT call failed for the selected MTYPE.  |
| <b>Action</b>      | Check the job output or JCL, correct the error, and rerun the job.   |
| <b>ERROR-128</b>   | <b>OPEN call failed.</b><br><b><i>“Return-code” “reason-code” “messaging-system-return-code”</i></b><br><b><i>“messaging-system-reason-code”</i></b>       |
| <b>Explanation</b> | The OPEN call failed for the selected MTYPE.   |
| <b>Action</b>      | Check the job output or JCL, correct the error, and rerun the job.   |
| <b>ERROR-129</b>   | <b>SEND call failed.</b><br><b><i>“Return-code” “reason-code” “messaging-system-return-code”</i></b><br><b><i>“messaging-system-reason-code”</i></b>       |
| <b>Explanation</b> | The SEND call failed for the selected MTYPE.   |
| <b>Action</b>      | Check the job output or JCL, correct the error, and rerun the job.   |
| <b>ERROR-130</b>   | <b>CLOSE call failed.</b><br><b><i>“Return-code” “reason-code” “messaging-system-return-code”</i></b><br><b><i>“messaging-system-reason-code”</i></b>      |
| <b>Explanation</b> | The CLOSE call failed for the selected MTYPE.  |
| <b>Action</b>      | Check the job output or JCL, correct the error, and rerun the job.   |
| <b>ERROR-131</b>   | <b>DISCONNECT call failed.</b><br><b><i>“Return-code” “reason-code” “messaging-system-return-code”</i></b><br><b><i>“messaging-system-reason-code”</i></b> |
| <b>Explanation</b> | The DISCONNECT call failed for the selected MTYPE.   |
| <b>Action</b>      | Check the job output or JCL, correct the error, and rerun the job.   |

**ERROR-132**      **TERM call failed. Return code xxxxxxxx Reason code xxxxxxxx**

**Explanation**      The TERM call failed for the selected MTYPE.

**Action**              Check the job output or JCL, correct the error, and rerun the job.

**ERROR-133**      **Read of MTSIN failed**

**Explanation**      A problem occurred while attempting to read MTSIN. The cause is probably a JCL error.

**Action**              Check the job output or JCL, correct the error, and rerun the job.