

Maintaining Directory Server Links

To maintain your Directory Servers, they must be linked to SMH. Once linked, any of the Directory Server's parameters, targets, partitions, and other settings can be modified using the SMH screens.

To maintain your Entire Net-Work target entries, you must have an Directory Server linked to SMH. A default link, called *sag-adi*, automatically set up during Entire Net-Work installation.

Ordinarily, Directory Servers are installed as part of another Software AG product (for example, Entire Net-Work). When this type of installation occurs, the Directory Server is automatically linked to SMH. However, there may be instances in your environment where a Directory Server is already installed in a location unknown to SMH. In these cases, you must manually create a link for the Directory Server if you want to maintain it.

Note:

Directory Servers linked to SMH can be maintained by any user with SMH access.

Using SMH, you can add, modify, and delete SMH links to installed Directory Servers.

This chapter covers the following topics:

- Listing Linked Directory Servers
- Adding a Link to a Directory Server
- Modifying a Directory Server Link Definition
- Listing Directory Server Parameters
- Deleting a Link to a Directory Server

Listing Linked Directory Servers

 **To list the installed Directory Servers that are linked to SMH:**

1. Access the Directory Server administration area, as described in *The Directory Server Administration Area*.
2. Select **Directory Servers** in the tree-view frame.

Note:

The "No Directories have been defined!" error message displays in the detail-view frame and is expected if no directory servers have been defined.

The list of directory servers linked to this System Management Hub appears in the detail-view frame.

5. Specify the **Directory Server Listen Port** as appropriate for your site.

You can no longer specify the port number as "0". If you are using an older Directory Server installation, it may have inherited a port number of "0". While this setting for older Directory Server versions is still supported, a setting of "0" will default to "4952". If this default is not satisfactory for your installation (if any applications you are running expect a port number other than 4952), specify the non-zero port number that should be used. In fact, Software AG recommends that you change all Directory Server port numbers that have been set to "0" to valid non-zero numbers to avoid any confusion. If you do this, however, be sure that you have also changed the values of the `XTSDSURL` and `SAGXTSDSport` environment variables and the `SAGXTSDSport` DNS entry, wherever they might be set.

For more information about setting the Directory Server port number, read *The Directory Server Port Number*. If you have problems accessing the Directory Server once it is defined, contact your system administrator for the correct port setting to use.

6. Click OK.

A link to the Directory Server is added and should appear in the listing of Directory Servers in both the tree-view and detail-view frames.

Modifying a Directory Server Link Definition

 **To modify the link definition in SMH for an installed Directory Server:**

1. Access the Directory Server administration area, as described in *The Directory Server Administration Area*.
2. Right-click on the name of the Directory Server whose link definition you wish to modify in the tree-view frame of SMH and select **Modify Directory Server Settings** from the resulting drop-down menu.

The **Modify Directory Server Settings** panel appears in the detail-view frame.

Modify Directory Server Settings

Directory Name:
test-D5 *

Directory Server Host Name:
localhost

Enter the Directory Server Listen Port:
4952 *

OK Cancel

3. Change the name for the Directory Server in the **Directory Name** field.
4. Change the host name where the Directory Server is running in the **Directory Server Host Name** field. It can be a fully qualified name.

Note:

Host names are case-sensitive in SMH.

Or:

Change the IP address for the Directory Server. We do not recommend using IP addresses instead of host names because the IP address may change

5. Change the **Directory Server Listen Port** as needed.

You can no longer specify the port number as "0". If you are using an older Directory Server installation, it may have inherited a port number of "0". While this setting for older Directory Server versions is still supported, a setting of "0" will default to "4952". If this default is not satisfactory for your installation (if any applications you are running expect a port number other than 4952), specify the non-zero port number that should be used. In fact, Software AG recommends that you change all Directory Server port numbers that have been set to "0" to valid non-zero numbers to avoid any confusion. If you do this, however, be sure that you have also changed the values of the `XTSDSURL` and `SAGXTSDSport` environment variables and the `SAGXTSDSport` DNS entry, wherever they might be set.

For more information about setting the Directory Server port number, read *The Directory Server Port Number*. If you have problems accessing the Directory Server once it is defined, contact your system administrator for the correct port setting to use.

6. Click OK.

The Directory Server link definition is modified.

Listing Directory Server Parameters

► To display the parameters for a Directory Server:

1. Access the Directory Server administration area, as described in *The Directory Server Administration Area*.
2. Right-click on the name of the Directory Server whose parameters you wish to review in the tree-view frame of SMH and select **Display Directory Server Parms** from the resulting drop-down menu.

The **Display Directory Server Parms** panel appears in the detail-view frame.

Display Directory Server Parms

Version:

Listen Port:

Trace Settings:

Debug Settings:

Log Directory:

Directory Type:

Directory Parms:

The following table describes the parameters that are listed. These parameters are set automatically when Directory Server starts up. If you wish to change these values, contact Software AG Customer Support.

Parameter	Description
Version	A version number for internal use only.
Listen Port	The listen port used by this Directory Server. The Directory Server uses this port to listen for target access and connection requests.
Trace Settings	The trace setting for this Directory Server.
Debug Settings	The debug setting for this Directory Server.
Log Directory	The full path of the directory in which trace logs are written for this Directory Server.
Directory Type	The type of Directory Server.
Directory Parms	The full path name of the URL configuration file for this Directory Server.

Deleting a Link to a Directory Server

To delete the link to an Directory Server in SMH:

1. Access the Directory Server administration area, as described in *The Directory Server Administration Area*.
2. Click on the name of the Directory Server whose definition you wish to delete in the tree-view frame of SMH.

The targets for that Directory Server are listed in the detail-view frame.

3. Right-click on the name of the Directory Server whose definition you wish to delete and select **Delete Directory Server Entry** on the resulting drop-down menu.

The **Delete Directory Server Entry** panel appears in the detail-view frame.

4. Click OK.

The Directory Server definition is deleted.