

# Maintaining Partitions

This chapter covers the following topics:


- Listing the Partitions
- Adding a Partition
- Changing a Partition Name
- Deleting a Partition


## Listing the Partitions

You can list the partitions defined for a Directory Server using the System Management Hub.

▶ **To list the partitions defined in a Directory Server:**

1. Access the Directory Server administration area, as described in *The Directory Server Administration Area*.
2. Click and expand the name of the Directory Server whose partitions you wish to review in the tree-view frame of SMH.

The targets and partitions for that Directory Server are listed in the detail-view frame and under the Directory Server name in the tree-view frame. Partitions are identified by the red square icon (  ).



The screenshot shows the System Management Hub interface. On the left is a tree view under 'System Management' showing 'Managed Hosts' > 'host address 1' > 'Directory Server' > 'LOCAL'. Under 'LOCAL', several partitions are listed, including 'WCVMP01' and 'wcvmp02'. On the right is a detail view titled 'LOCAL' showing a table of partitions with columns for Partition, Target, Qualifier, and URL.

Partition	Target	Qualifier	URL
WCVMP01	140	access	TCPIP://WCVMP01:9010
WCVMP01	157	access	TCPIP://WCVMP01:9010
WCVMP01	158	access	TCPIP://WCVMP01:9010?DBID=LOCAL
WCVMP01	159	access	TCPIP://WCVMP01:9010
WCVMP01	5	access	TCPIP://WCVMP01:9010
WCVMP01	59	access	TCPIP://WCVMP01:9010
WCVMP01	87	access	TCPIP://WCVMP01:9010
WCVMP01	89	access	TCPIP://WCVMP01:9010
wcvmp02	140	access	TCPIP://WCVMP02:9010?KERNEL=WCVMP02
wcvmp02	157	access	TCPIP://WCVMP02:9010?KERNEL=WCVMP02
wcvmp02	158	access	TCPIP://WCVMP02:9010?KERNEL=WCVMP02
wcvmp02	159	access	TCPIP://WCVMP02:9010?DBID=LOCAL&KERNEL=WCVMP02

Targets are initially listed by partition, in the order they appear in the Directory Server. You can change the sort order of the list by clicking on the arrows in the column headings of the table in the detail-view frame. If you click on an up arrow in the column heading, the display is sorted alphabetically by the contents in that column. If you click on a down arrow in the column heading, the display is sorted in reverse alphabetic order by the contents in that column.


## Adding a Partition

You can add a partition to a Directory Server using the System Management Hub.

### ▶ To add a partition in the Directory Server:

1. Access the Directory Server administration area, as described in *The Directory Server Administration Area*.
2. In the tree-view frame of SMH, right-click on the name of the Directory Server to which you want to define partitions and select **Add Partition** from the resulting drop-down menu.

The Add Partition panel appears in the detail-view frame.



3. Specify a name for the partition in the **Enter the Partition Name:** field.
4. Click OK.

The partition is added for the Directory Server and the added partition displays in the System Management Hub tree-view frame.

#### **Note:**

No targets are defined initially for a partition. You must define them now.

## Changing a Partition Name

You can change the name of a partition defined for a Directory Server using the System Management Hub.



#### **Warning:**


**When you rename a partition, all of the target definitions defined for that partition remain with the partition under its new name.**

### ▶ To change the name of a partition:

1. Access the Directory Server administration area, as described in *The Directory Server Administration Area*.

2. In the tree-view frame of SMH, right-click on the name of the Directory Server containing the partition you want to rename and select **Change Partition Name** from the resulting drop-down menu.

The **Change Partition Name** panel appears in the detail-view frame.

A dialog box titled "Change Partition Name" with a light blue header. Below the title is a label "Change Partition Name To:" in blue text. Underneath is a white text input field with a red asterisk on the right side. At the bottom of the dialog are two blue buttons: "OK" and "Cancel".

3. Specify a new name for the partition in the **Change Partition Name To** field.
4. Click OK.

The partition is renamed displays in the System Management Hub tree-view frame with its new name. All of its target definitions remain with the partition under its new name.

## Deleting a Partition

You can delete a partition defined for a Directory Server using the System Management Hub.



### Warning:

**When you delete a partition, all of the target definitions defined for that partition are also deleted.**



### To delete a partition in a Directory Server:

1. Access the Directory Server administration area, as described in *The Directory Server Administration Area*.
2. In the tree-view frame of SMH, click on the name of the Directory Server containing the the partition you wish to delete.

The partitions and targets for that Directory Server are listed in the detail-view frame.

3. Right-click on the partition you wish to delete and select **Delete Partition** from the resulting drop-down menu.

The Delete Partition panel appears in the detail-view frame.

4. Click OK.

The partition and all of its associated target definitions are deleted.