Natural Global Buffer Pool Manager Messages

This section contains the informational and error messages issued by the Natural Global buffer pool manager in z/OS and z/VSE.

All messages have the format:

GBPnnnn xxxxxxxx: message text

where *nnnn* is the message number and *xxxxxxxxx* is the job name, under which the Natural global buffer pool is running. For ease of use, the job name message portion has been omitted in the following list of messages. Notation in italics indicates a variable message portion.

The following topics are covered below:

- Natural Global Buffer Pool Manager Syntax Error Messages
- Natural Global Buffer Pool Manager Run-Time Messages
- Natural Global Buffer Pool Manager Driver Messages

Natural Global Buffer Pool Manager Syntax Error Messages

The Natural global buffer pool manager syntax error messages are self-explanatory with *xxxx* being the invalid command or parameter. For appropriate command and parameter syntax, refer to the Natural Operations documentation.

Message Number	Message Text
GBP0001	Invalid command: xxxx
GBP0002	More than one command specified
GBP0003	Invalid parameter keyword: xxxx
GBP0004	Buffer pool name parameter missing
GBP0005	Invalid buffer pool name: xxxx
GBP0006	Leading parenthesis missing in NATBUFFER
GBP0007	Ending parenthesis missing in NATBUFFER
GBP0008	Buffer pool size not numeric: xxxx
GBP0009	Buffer pool size less than 100K: xxxx
GBP0010	Buffer pool size too large: xxxx
GBP0011	Invalid MODE specified: xxxx
GBP0012	Text block size not numeric: xxxx
GBP0013	Text block size must be 1,2,4,8,12 or 16, not xxxx
GBP0014	Invalid buffer pool type: xxxx
GBP0015	Invalid preload list name: xxxx
GBP0016	Invalid sub-system ID: xxxx
GBP0017	IDLE time not numeric: xxxx
GBP0018	IDLE time out of valid range: xxxx
GBP0019	Buffer pool cache size not numeric: xxxx
GBP0020	Buffer pool cache size out of valid range: xxxx
GBP0021	RESIDENT must be Y or N or A, not xxxx
GBP0022	METHOD must be S or N, not xxxx
GBP0023	CONFIRM must be Y or N, not xxxx
GBP0024	PLUGIN must be BP or NOBP, not xxxx
GBP0025	REGISTER must be Y or N, not xxxx
GBP0029	NAT buffer pool size less than 256K: xxxx

Natural Global Buffer Pool Manager Run-Time Messages

Message Number	Message Text	
GBP0000	xxxx (dummy message consisting only of a variable message part)	
GBP0098	Parameter module missing or invalid: pgm-name	
GBP0099	Message text module missing or invalid: pgm-name	

GBP0100	No parameters specified
GBP0101	Specified parms: xxxx
GBP0102	Operator input: xxxx
GBP0103	Input from file: xxxx
GBP0104	Mandatory module missing or invalid: pgm-name
GBP0105	Storage could not be obtained: xxxx
GBP0106	FREEMAIN not successful
GBP0107	NAME/TOKEN service failure: error-info
GBP0108	Buffer pool manager module incompatible: pgm-name
GBP0109	Pool (de)allocation failure: error-info
GBP0110	GBP not active: gbp-name/subsid
GBP0111	GBP active: gbp-name/subsid - DIR=dir-addr ADDR=gbp-addr
GBP0112	GBP refreshed: gbp-name/subsid - DIR=dir-addr ADDR=gbp-addr
GBP0113	GBP stopped: gbp-name/subsid - DIR=dir-addr ADDR=gbp-addr
GBP0114	GBP already active: gbp-name/subsid - DIR=dir-addr ADDR=gbp-addr
GBP0115	GBP still in use: gbp-name/subsid - DIR=dir-addr ADDR=gbp-addr
GBP0116	Associated GBP has been lost gbp-name/subsid
GBP0117	Shutdown forced for GBP gbp-name/subsid
GBP0118	Reply Y to force shutdown of GBP gbp-name/subsid
GBP0119	Shutdown aborted, reply was x
GBP0120	Creating cache for GBP: gbp-name/subsid
GBP0121	Deleting cache for GBP: gbp-name/subsid
GBP0122	GBP cache creation failure: error-info
GBP0123	GBP cache deletion failure: error-info
GBP0124	GBP cache created: cache-name,cache-token,cache-ALET
GBP0125	GBP cache deleted: cache-name,cache-token,cache-ALET
GBP0126	ALET stack overflow. Cannot create GBP cache
GBP0127	Cache already exists for GBP: gbp-name/subsid
GBP0128	No cache available for GBP: gbp-name/subsid
GBP0129	GBP cache not owned by job job-name
GBP0130	No global buffer pool available for SUBSID: subsid
GBP0131	List of all global buffer pools with SUBSID: subsid
GBP0132	BP-Name/SUBSID Size(KB) A(GBP) A(DIR) ALET Cache Size Cache Owner
GBP0133	About to shutdown the following global buffer pools
I	

GBP0134	Reply Y to continue shutdown of global buffer pools	
GBP0135	No global buffer pool matching selection criteria	
GBP0136	Job does not own GBP cache(s)	
GBP0137	GBP cache(s) owned by job job-name	
GBP0138	Data space cache not supported in non-ESA environment	
GBP0139	GBP(s) owned by job: <i>job-name</i>	
GBP0140	RESIDENT=N ignored due to owning GBP cache(s):	
GBP0141	TERMINATE aborted due to owning GBP cache(s):	
GBP0142	RESIDENT=N ignored due to owning GBP(s):	
GBP0143	TERMINATE aborted due to owning GBP(s):	
GBP0144	GBP not allocated due to user key pool not possible	
GBP0145	Global parameter settings: xxxx	
GBP0149	Service request failure: service, error-info	
GBP0150	Formatted dump	
GBP0151	Formatted dump for GBP gbp-name/subsid	
GBP0154	Global buffer pool manager not operational	
GBP0158	Bad retcode from NATBPMG4, function REINIT: rtc	
GBP0159	Bad retcode from NATBPMG4, function INIT: rtc	
GBP0197	No Zaps applied	
GBP0198	Applied Zaps:	
GBP0199	Natural Global Buffer Pool Manager Version: xxxx	

 $\it Error-info$ format is: failing function (macro), sub-function, request return (RC) or cancel code (CC), request failure reason code

Please see the relevant IBM documentation for an explanation of the return or abend codes of the relevant IBM request macro.

Natural Global Buffer Pool Manager Driver Messages

The following messages are issued by the Natural global buffer pool manager operating system dependent driver modules:

Message Number	Message Text
GBP0200	Specified file does not exist: file-name
GBP0201	Reading parm input from file file-name
GBP0202	EOF encountered reading file <i>file-name</i>
GBP0203	Error reading file file-name
GBP0204	Subsystem storage protection feature is required
GBP0205	Insufficient authorization: error-info
GBP0206	Job cancelled by operator
GBP0207	Job cancelled due to unrecoverable abend abend-code

The following messages are issued by the Natural global buffer pool manager z/OS driver module:

Message Number	Message Text
GBP0300	Sorry, z/OS is required
GBP0301	Only MODIFY or STOP commands allowed
GBP0302	STOP command received from operator

The following messages are issued by the Natural global buffer pool manager z/VSE driver module:

Message Number	Message Text
GBP0400	Sorry, VSE/ESA 2.4 or higher is required
GBP0401	Ready for communications
GBP0402	No input received from operator
GBP0403	Job cancelled due to JCL overrun