

NAF - Look at Spool File - Function 22

With this function, all reports on the spool file can be displayed in hexadecimal format, including pointer information.

When you invoke this function, the **Display Spool File** window appears.

```

Time 15:03:39          *** Natural Spool Administration ***          Date 2002-10-23
User SAG              M e n u                                       File 7/411
+----- Display Spool File 7/411 -----+
!                                     !                               Information
!   1   by Job Number                !
!   2   by Destination/Form           !   20 Cross-Reference
!   3   Records with status In Use    !   21 Statistics
!   4   All records                   !   22 Look at Spool File
!   5   Records of a Report           !   23 CALLNAT Handling
!   6   by Job Number                !
!       (output to printer 1)        !
!                                     !
!                                     !   Control Functions
!                                     !
!                                     !   40 Check Spool File
!                                     !   41 Logging Data
!   .   Exit                          !   42 Create Test Reports
!                                     !   43 Delete Reports by Date
!   Command / _ /                    !
+-----+
Enter values.
Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help  Menu  Exit  JobNo De/Fo Used  All   Point                               Canc

```

This chapter covers the following topics:

- By Job Number - Function 22.1
- By Destination/Form - Function 22.2
- Records with Status In Use - Function 22.3
- All Records - Output to Screen - Function 22.4
- Records of a Report - Function 22.5
- All Records - Output to Printer 1 - Function 22.6

By Job Number - Function 22.1

When you invoke this function, you can specify a job number or press Enter to select a job number from a list.

The specified job is then shown, for example:

By Destination/Form - Function 22.2

When you invoke this function, you can specify a Destination/Form, or press Enter to select a Destination/Form from a list.

The specified Destination/Form is then shown. See *Function 22.1* for information on the contents of the resulting screen.

Records with Status In Use - Function 22.3

When you invoke this function, all records that are currently used are shown. See *Function 22.1* for information on the contents of the resulting screen.

All Records - Output to Screen - Function 22.4

When you invoke this function, you can specify a start value, or press Enter to start with the first record.

The spool file records are then shown. See *Function 22.1* for information on the contents of the resulting screen.

Records of a Report - Function 22.5

When you invoke this function, you can specify a job number, or press Enter to select a job number from a list.

The report pointers for the specified job are then shown.

| Job No. | F | Pointer | Prev. Gr | Next Gr. | La. | R/Gr | Prev.Re. | Next Re. | Pag/Gr | Pag/Re |
|---|---|------------------|----------|----------------|----------|----------|------------------|----------|--------|--------|
| 88 | S | 00000058 | 00000000 | 0000005B | 0000005A | 00000000 | 00000059 | | 2 | 1 |
| | | 00000059 | 00000000 | 0000005B | 0000005A | 00000058 | 0000005A | | 2 | 1 |
| | | 0000005A | 00000000 | 0000005B | 0000005A | 00000059 | 00000000 | | 2 | 2 |
| | * | 0000005B | 00000058 | 0000005E | 0000005D | 00000000 | 0000005C | | 3 | 2 |
| | | 0000005C | 00000058 | 0000005E | 0000005D | 0000005B | 0000005D | | 3 | 2 |
| | | 0000005D | 00000058 | 0000005E | 0000005D | 0000005C | 00000000 | | 3 | 3 |
| | * | 0000005E | 0000005B | 00000000 | 00000060 | 00000000 | 0000005F | | 4 | 3 |
| | | 0000005F | 0000005B | 00000000 | 00000060 | 0000005E | 00000060 | | 4 | 4 |
| | E | 00000060 | 0000005B | 00000000 | 00000060 | 0000005F | 00000000 | | 4 | 4 |
| | | 00000000 | 00000000 | 00000000 | 00000000 | 00000000 | 00000000 | | | |
| | | 00000000 | 00000000 | 00000000 | 00000000 | 00000000 | 00000000 | | | |
| | | 00000000 | 00000000 | 00000000 | 00000000 | 00000000 | 00000000 | | | |
| | | 00000000 | 00000000 | 00000000 | 00000000 | 00000000 | 00000000 | | | |
| | | 3 used Groups | | 9 used Records | | | 0 unused Records | | | |
| | | 18.000 allocated | | 18.000 used | | | 0 unused Bytes | | | |
| End of Report. Enter function, mark with cursor or press PF key | | | | | | | | | | |
| Command ==> | | | | | | | | | | |
| Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12--- | | | | | | | | | | |
| Help Menu Exit + Bot - Top Canc | | | | | | | | | | |

For each pointer, information concerning next group, next record, previous group, previous record and the last record in a group is shown.

The flag in front of a line indicates the following:

| Flag | Description |
|-------------|--------------------|
| S | Start of report. |
| * | Start of group. |
| E | End of report. |

At the end of the report, information on the used space is given.

To display information on a specific pointer of the report, mark the corresponding value and press Enter. See *Function 22.1* for information on the contents of the resulting screen.

All Records - Output to Printer 1 - Function 22.6

When you invoke this function, you can specify a job number, or press Enter to select a job number from a list.

The job specified is printed to the assigned Printer 1 by using the format described for Function 22.1.