

Object Specification - Natural System Error Messages

This section describes the options provided on the object-specification screens for processing Natural system error messages from the specified system file.

For descriptions of keywords and valid input values, see also *select-clause* in the section *Direct Commands*.

This section covers the following topics:

- Natural System Error Messages
 - Natural System Error Message Details
 - Natural System Error Message Exceptions
-

Natural System Error Messages

The screen **Unload/Load/Scan Natural System Error Messages** provides the following fields and PF keys:

Field	PF Key	Explanation
Error number from/to		A range of Natural system error messages delimited by the first and the last message number. Select Select system error messages for a list of all system error messages available.
Details	PF6	Invokes the screen Unload/Load/Scan Natural Library Objects, Details where you can enter more detailed object specifications: see <i>Natural System Error Message Details</i> .
Settings	PF7	Invokes the screen Unload/Load/Scan Settings where you can specify option and parameter settings. See <i>Settings</i> .

Natural System Error Message Details

The screen **Unload/Load/Scan System Error Messages, Details** is used to specify further selection criteria for Natural system error messages.

For descriptions of keywords and valid input values, see also *select-clause* in the section *Direct Commands*.

The screen **Unload/Load/Scan System Error Messages, Details** provides the following fields and PF keys:

Field	PF Key	Explanation
DBID/FNR		Only applies to the unload function. The database ID (DBID) and the number of the Adabas (FNR) file where the Natural error messages are stored.
Password/Cipher		Only applies to the unload function. The password and cipher code for the Adabas file where the Natural error message sources are stored.
Error number from/to		See Error number in <i>Natural System Error Messages</i> above.
Language codes		See Language codes in <i>Natural Library Object Details</i> .
S/L-Kind		See S/L-Kind in <i>Natural Library Object Details</i> .
Exceptions	PF8	Invokes an extra screen where you can specify exceptions to the selection of Natural system error messages: see <i>Natural System Error Message Exceptions</i> .

Natural System Error Message Exceptions

The screen **Unload/Load/Scan System Error Messages, Exceptions** is used to specify exceptions to the selection of Natural system error messages.

All Natural system error messages that match the selection criteria specified in *Natural System Error Messages* and *Natural System Error Message Details* are checked against the specifications made on the screen **Unload/Load/Scan System Error Messages, Exceptions**. Error messages that match *all* specifications defined as exceptions, are exempted from processing.

For explanations of the fields provided on the exceptions screen, see *Natural System Error Message Details* above.

For descriptions of keywords and valid input values, see also *select-clause* in the section *Direct Commands*.