

Master File Task Screens

This chapter covers the following topics:

- Master File Task Selection Menu
- Add Master File Definition
- Modify Master File Definition
- Display Master File Definition
- Delete Master File Definition

Master File Task Selection Menu

By either entering the MM direct command or selecting the MM option on the ETP Maintenance Utility Main Menu, the Master File Definition Maintenance screen appears.

The Master File Task Selection Menu

```

23:59:59          ***** ENTIRE TRANSACTION PROPAGATOR *****          2000-12-24
                    Master File Definition Maintenance

                AD  Add      master file definition
                MO  Modify   master file definition
                DI  Display  master file definition
                DE  Delete   master file definition

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help  Menu  Exit  Last          Flip          Tech          Canc

```

The master file tasks you select from this menu cause the screens described in the following section to appear.

Add Master File Definition

By either entering the Add Master direct command or selecting the AD option on the Master File Definition Maintenance menu, the following screen appears.

The Add Master File Definition Screen

```

23:59:59          ***** ENTIRE TRANSACTION PROPAGATOR *****          2000-12-24
                    Add master file definition

Master file ..  _____  _____  Verify FDT
Log   file ..  _____  _____  Y (Y/N)
                                         Y (Y/N)

ADABAS field name of distribution key ..... ___
NATURAL data format of distribution key ... _____

Call user exit before replication ..... N (Y/N)
Start program after ET ..... N (Y/N)

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help Menu Exit Last Save Flip                      Tech          Canc

```

To define an ETP master file, enter the information in the fields, as described below.

Screen Field Description

Master File DBID/FNR	Enter the database ID and file number of the Adabas file that becomes a master file. Specify Y (yes) under "Verify FDT" to verify the file's Field Definition Table (FDT); otherwise, enter N (no). You must make all entries; there are no defaults.
Log File FNR	Enter the file number of the Adabas file that is or will be the ETP log file. The log file must be on the same database as the master file. A single log file can be used for more than one master file. Specify Y (yes) under "Verify FDT" to verify the log file's Field Definition Table (FDT); otherwise, enter N (no). To ensure data consistency, the log file must be empty; otherwise, adding a master file is not allowed.
Adabas Field Name of Distribution Key	When any of the replicate files for this master file contain only a subset of master file records, one field must contain values or ranges of values that uniquely identify each replicate file's subset, and therefore the replicate file itself. Specify the two-letter Adabas field name of that identifying field here. The distribution key field cannot be a multiple-value (MU), a periodic group (PE) or field within a PE group, or a phonetic descriptor field; otherwise, an error occurs either during FDT verification, or when writing to the log file during operation.
Natural Data Format of Distribution Key	When you specify a field name for the Distribution Key field above, you must specify the field's Natural data type here (for example, A15 for a 15-byte alphanumeric field). Specifying the number of digits after the decimal point is not possible for numeric data types.
Call User Exit?	Specify Y (yes) if you want the WADUSER2 subprogram called <i>after</i> ETP checks the current transaction record's distribution key field, if any. ETP checks any distribution key to determine if a change to the master file must also be made to a specific replicate file. The default is N (no).
Start Program after ET?	Specify Y (yes) if you want to execute the program defined in the Modify System Profile task screen. The default is N (no).

Modify Master File Definition

By either entering the Modify Master direct command or selecting the MO option on the Master File Definition Maintenance menu, the Modify Master File Definition screen appears.

The Modify Master File Definition Screen

```
23:59:59          ***** ENTIRE TRANSACTION PROPAGATOR *****          2000-12-24
                          Modify master file definition

Master file ..*  _____  _____  Y (Y/N)
Log file ...    _____  _____  Y (Y/N)

ADABAS field name of distribution key ..... _
NATURAL data format of distribution key ... ____

Call user exit before replication? ..... _ (Y/N)
Start program after ET ..... _ (Y/N)

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help  Menu  Exit  Last  Save  Flip                      Tech          Canc
```

To change an existing master file's definition, enter the information in the fields as described below.

Screen Field Description

When the "Modify Master File Definition" screen is first displayed, you must either enter (or have already selected) a master file; otherwise, you cannot make entries in the rest of the fields. Once you have selected a master file and pressed Enter, you cannot change your selection unless you either exit and then re-enter the screen, or enter the SAVE command.

Master File DBID/FNR	Enter the database ID and file number of the existing master file. If you enter a wild card in either the database ID or file number field, a window appears from which you can select a single master file definition for modification.
Log File FNR	Enter a new log file file number here. The log file must be on the same database as the master file. Note that if the current log file is not empty, a new log file cannot be defined.
Adabas Field Name of Distribution Key	When any of the replicate files for this master file contain only a subset of master file records, one field must contain values or ranges of values that uniquely identify each replicate file's subset, and therefore the replicate file itself. If the distribution key field is being changed, specify the two-letter Adabas field name of that field here. The distribution key field cannot be a multiple-value (MU), a periodic group (PE) or field within a PE group, or a phonetic descriptor field; otherwise, an error occurs either during FDT verification, or when writing to the log file during operation. Note that if any of the replicate files are still using the distribution key, it cannot be changed.
Natural Data Format of Distribution Key	When you specify a new field name for the Distribution Key field, you must specify the field's Natural data type here (for example, A15 for an alphanumeric field of 15 bytes). Specifying the number of digits after the decimal point is not possible for numeric data types.
Call User Exit?	Specify Y(yes) if you want the WADUSER2 subprogram called <i>after</i> ETP checks the current transaction record's distribution key field, if any. ETP checks any distribution key to determine if a change to the master file must also be made to a specific replicate file. The default is N (no).
Start Program after ET?	Specify Y (yes) if you want to execute the program defined in the Modify System Profile task screen. The default is N (no).

Display Master File Definition

By either entering the Display Master direct command or selecting the DI option on the Master File Definition Maintenance menu, the Display Master File Definition screen appears.

The Display Master File Definition Screen

```

23:59:59          ***** ENTIRE TRANSACTION PROPAGATOR *****          2000-12-24
                    Display master file definition

Master file ..*   DBID   FNR
                  _____

Printer name .. _____ (' ' = terminal)

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help  Menu  Exit  Last           Flip           Tech           Canc

```

To display a master file's definition, enter the information in the fields as described below. To make changes to a master file's definition, enter the `MODify MASTER` direct command on the command line at the bottom of the screen.

Screen Field Description

Master File DBID/FNR	Enter the database ID and file number of the master file you want displayed. If you enter a wild card in either the database ID or file number field, a window appears from which you can select one or more master file definitions for display.
Printer Name	To print out the selected master file definitions, enter a valid printer ID here. Leave this field empty to display the master file definition on your terminal.

Delete Master File Definition

By either entering the `DElete MASTER` direct command or selecting the `DE` option on the Master File Definition Maintenance menu, the Delete Master File Definition screen appears.

The Delete Master File Definition Screen

```

23:59:59          ***** ENTIRE TRANSACTION PROPAGATOR *****          2000-12-24
                        Delete master file definition

Delete master file ..*  _____  _____

                                DBID      FNR

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help  Menu  Exit  Last          Flip          Tech          Canc

```

Before you delete a master file definition, you must delete all related replicate files; the related log file must be empty.



Warning:

Deleting a master file only removes the master file definition from the ETP administration file. The file and its contents still exist as a normal Adabas file in its original database and with its original file number.

To delete a master file's definition, enter the information in the fields as described below. To make changes to a master file's definition, enter the MODIFY MASTER direct command on the command line at the bottom of the current screen.

Screen Field Description

Delete Master File DBID/FNR	Enter the database ID and file number of the master file you want to delete. If you enter a wild card in either the database ID or file number field, a window appears from which you can select one or more master file definitions for deletion.
--------------------------------	--

If you have requested the confirmation window using the Modify User Profile function, the confirmation window appears, asking you to confirm the deletion. If either of the following conditions exist:

- The log file has entries for the master file;

- A master file has one or more replicate files still defined.
- then a warning occurs, and the deletion request will be rejected.