

# RPC Server Front-End Messages

This section explains the messages that are issued by the RPC server front-end.

When a message of type "error message" appears, the RPC server environment is terminated abnormally.

---

## RPC0001 PARM string missing

Type	Error message.
Expl.	The PARM string with the RPC server front-end parameters is not specified on the EXEC card.

## RPC0002 Natural driver name too long: *name*

Type	Error message.
Expl.	The name of the Natural z/OS batch nucleus in the PARM string is longer than eight characters. The invalid name is shown in the message.

## RPC0004 Thread size not numeric or too large: *value*

Type	Error message.
Expl.	The value for the thread size in the PARM string is invalid. The invalid value is shown in the message.

## RPC0006 Thread number not numeric or too large: *value*

Type	Error message.
Expl.	The value for the number of threads in the PARM string is invalid. The invalid value is shown in the message.

## RPC0007 Natural driver not found: *name*

Type	Error message.
Expl.	The Natural z/OS batch nucleus could not be loaded. Check your STEPLIB concatenation.

## RPC0010 Authorized environment for impersonation established

Type	Informational message.
Expl.	Indicates that impersonation is possible in z/OS mode. This message is issued if the Natural RPC server front-end has been linked with AC=1 and is loaded from an APF authorized library.

## RPC0011 Starting Natural RPC server

Type	Informational message.
Expl.	Normal startup message.

## RPC0012 Restarting Natural RPC server

Type	Informational message.
Expl.	Indicates a problem with the Roll Server. This message is typically issued if an active Natural session has been deleted from the Roll Server.

## RPC0013 Terminating Natural RPC server

Type	Informational message.
Expl.	The Natural RPC server environment is terminated normally.

## RPC0014 Natural Security logon failed or missing on Natural STACK

Type	Error message.
Expl.	If Natural profile parameter AUTO=OFF is specified, a Natural Security logon must be provided with the profile parameter STACK.

## RPC0015 Impersonation failed with SAF RC/reason *xxxx/yyyy*

Type	Informational message.
Expl.	Informational message in the RPC server trace.

## RPC0016 Impersonation failed with CICS RC/reason *xxxx/yyyy*

Type	Informational message.
Expl.	Informational message in the RPC server trace.

## **RPC0017 Initializing Natural RPC server environment**

Type	Informational message.
Expl.	Normal startup message to indicate the initialization of the Natural RPC server environment.

## **RPC0018 Creating Natural RPC server session template**

Type	Informational message.
Expl.	Normal startup message to indicate the creation of a Natural template session that is used by all subsequently started Natural RPC servers.

## **RPC0019 Terminating Natural RPC server environment**

Type	Informational message.
Expl.	The Natural RPC server environment is terminated normally.

## **RPC0020 Disconnecting Natural RPC server from transport**

Type	Informational message.
Expl.	This message is issued during abnormal termination of a Natural RPC server.