

# NAF - Look at Spool File - Function 22

With this function, all reports on the spool file can be displayed in hexadecimal format, including pointer information.

When you invoke this function, the **Display Spool File** window appears.

```

Time 15:03:39          *** Natural Spool Administration ***          Date 2002-10-23
User SAG              M e n u                                       File 7/411
+----- Display Spool File 7/411 -----+
!                                     !                               Information
!   1   by Job Number                !                               !
!   2   by Destination/Form          !   20 Cross-Reference
!   3   Records with status In Use   !   21 Statistics
!   4   All records                  !   22 Look at Spool File
!   5   Records of a Report          !   23 CALLNAT Handling
!   6   by Job Number                !                               !
!       (output to printer 1)        !                               !
!                                     !                               Control Functions
!                                     !                               !
!                                     !   40 Check Spool File
!                                     !   41 Logging Data
!   .   Exit                          !   42 Create Test Reports
!                                     !   43 Delete Reports by Date
!   Command / _ /                    !                               !
+-----+
Enter values.
Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help  Menu  Exit  JobNo De/Fo Used  All   Point                               Canc

```

This chapter covers the following topics:

- By Job Number - Function 22.1
- By Destination/Form - Function 22.2
- Records with Status In Use - Function 22.3
- All Records - Output to Screen - Function 22.4
- Records of a Report - Function 22.5
- All Records - Output to Printer 1 - Function 22.6

---

## By Job Number - Function 22.1

When you invoke this function, you can specify a job number or press Enter to select a job number from a list.

The specified job is then shown, for example:





## By Destination/Form - Function 22.2

When you invoke this function, you can specify a Destination/Form, or press Enter to select a Destination/Form from a list.

The specified Destination/Form is then shown. See *Function 22.1* for information on the contents of the resulting screen.

## Records with Status In Use - Function 22.3

When you invoke this function, all records that are currently used are shown. See *Function 22.1* for information on the contents of the resulting screen.

## All Records - Output to Screen - Function 22.4

When you invoke this function, you can specify a start value, or press Enter to start with the first record.

The spool file records are then shown. See *Function 22.1* for information on the contents of the resulting screen.

## Records of a Report - Function 22.5

When you invoke this function, you can specify a job number, or press Enter to select a job number from a list.

The report pointers for the specified job are then shown.

Job No.	F	Pointer	Prev. Gr	Next Gr.	La.	R/Gr	Prev.Re.	Next Re.	Pag/Gr	Pag/Re
88	S	00000058	00000000	0000005B	0000005A	00000000	00000059		2	1
		00000059	00000000	0000005B	0000005A	00000058	0000005A		2	1
		0000005A	00000000	0000005B	0000005A	00000059	00000000		2	2
	*	0000005B	00000058	0000005E	0000005D	00000000	0000005C		3	2
		0000005C	00000058	0000005E	0000005D	0000005B	0000005D		3	2
		0000005D	00000058	0000005E	0000005D	0000005C	00000000		3	3
	*	0000005E	0000005B	00000000	00000060	00000000	0000005F		4	3
		0000005F	0000005B	00000000	00000060	0000005E	00000060		4	4
	E	00000060	0000005B	00000000	00000060	0000005F	00000000		4	4
		00000000	00000000	00000000	00000000	00000000	00000000			
		00000000	00000000	00000000	00000000	00000000	00000000			
		00000000	00000000	00000000	00000000	00000000	00000000			
		00000000	00000000	00000000	00000000	00000000	00000000			
		3 used Groups		9 used Records			0 unused Records			
		18.000 allocated		18.000 used			0 unused Bytes			
End of Report. Enter function, mark with cursor or press PF key										
Command ==>										
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---										
Help Menu Exit + Bot - Top Canc										

For each pointer, information concerning next group, next record, previous group, previous record and the last record in a group is shown.

The flag in front of a line indicates the following:

<b>Flag</b>	<b>Description</b>
S	Start of report.
*	Start of group.
E	End of report.

At the end of the report, information on the used space is given.

To display information on a specific pointer of the report, mark the corresponding value and press Enter. See *Function 22.1* for information on the contents of the resulting screen.

## **All Records - Output to Printer 1 - Function 22.6**

When you invoke this function, you can specify a job number, or press Enter to select a job number from a list.

The job specified is printed to the assigned Printer 1 by using the format described for Function 22.1.