

# Progress Bar Control Attributes Window

## ▶ Accessible Using

1. Double-click on the progress bar control; or
  2. if selected: "Control > Attributes" or by selecting 'Attributes...' from the control's context menu.
  3. if selected: ENTER.
- 

## Entries

### Note:

For context-sensitive help on attribute entries, select the entry so it has the focus, and press F1.

Entry in Attributes Window	Represents
<b>Name</b>	Handle name of the progress bar control (may be overwritten with another name).
<b>Context Menu</b>	CONTEXT-MENU attribute value. Specifies the context menu (if any) associated with the control.
<b>Background color:</b>	Defines the color of the progress bar background.  <b>Note:</b> The specified color is ignored if Windows XP styles are active.
<b>Selection box</b>	BACKGROUND-COLOUR-NAME attribute value.
...	Invokes dialog box for editing BACKGROUND-COLOUR-VALUE attribute value.
<b>Foreground color:</b>	Defines the color of the progress bar itself.  <b>Note:</b> The specified color is ignored if Windows XP styles are active.
<b>Selection box</b>	FOREGROUND-COLOUR-NAME attribute value.
...	Invokes dialog box for editing FOREGROUND-COLOUR-VALUE attribute value.
<b>Range:</b>	
<b>Min</b>	MIN attribute value. Lower limit of control's range.
<b>Max</b>	MAX attribute value. Upper limit of control's range.
<b>Pos.</b>	POSITION attribute value. Current progress bar position within control's numeric range.
<b>Style:</b>	

<b>Entry in Attributes Window</b>	<b>Represents</b>
<b>Smooth</b>	STYLE attribute value. Progress bar is smooth rather than segmented.  <b>Note:</b> The progress bar is always segmented if Windows XP styles are active.
<b>Vertical</b>	STYLE attribute value. The control is oriented vertically, rather than horizontally.
<b>State:</b>	
<b>Visible</b>	VISIBLE attribute value. Control will be shown.
<b>Rectangle:</b>	The following four attributes decide the input field control's x and y axis position, its height and its width on the screen.  <b>X</b> - RECTANGLE-X attribute value. <b>Y</b> - RECTANGLE-Y attribute value. <b>W</b> - RECTANGLE-W attribute value. <b>H</b> - RECTANGLE-H attribute value.
<b>OK</b>	Save settings and exit the window.
<b>Cancel</b>	Exit the window without saving the settings.
<b>Help</b>	Provides online help on the attributes window.