

# Scrollbar Control Attributes Window

## ▶ Accessible Using

1. Double-click on the scroll-bar control; or
  2. if selected: "Control > Attributes" or by selecting 'Attributes...' from the control's context menu or
  3. if selected: ENTER
- 

## Entries

### Note:

For context-sensitive help on attribute entries, select the entry so it has the focus, and press F1.

Entry in Attributes Window	Represents
<b>Name</b>	Handle name of the scroll-bar control (may be overwritten with another name starting with the # sign).
<b>Array...</b>	Dialog box for defining an array of scroll-bar controls.
<b>DIL text</b>	DIL-TEXT attribute value (string).
<b>...</b>	Dialog box for determining sources of DIL-TEXT attribute values.
<b>Help ID</b>	HELP-ID attribute value. You must use the help topic's .h file to map the numerical ID that you enter here to the corresponding help topic ID (created by a markup in the .hlp file).
<b>Context Menu</b>	CONTEXT-MENU attribute value. Specifies the context menu (if any) associated with the control.
<b>State:</b>	
<b>Visible</b>	VISIBLE attribute value.
<b>Enabled</b>	ENABLED attribute value.
<b>Values:</b>	
<b>Minimum</b>	MIN attribute value (minimum numerical value on the scale).
<b>Maximum</b>	MAX attribute value (maximum numerical value on the scale).
<b>Line</b>	LINE attribute value (number of logical units by which the slider moves if the end user presses the up and down arrow buttons).
<b>Page</b>	PAGE attribute value (number of logical units by which the slider moves if the end user clicks on the scroll-bar control's shaft).
<b>Slider</b>	SLIDER attribute value (position of the slider in between the MIN and MAX values).

Entry in Attributes Window	Represents
<b>Rectangle:</b>	<p>The following four attributes decide the scroll-bar control's x and y axis position, its height and its width on the screen.</p> <p><b>X</b> - RECTANGLE-X attribute value.  <b>Y</b> - RECTANGLE-Y attribute value.  <b>W</b> - RECTANGLE-W attribute value.  <b>H</b> - RECTANGLE-H attribute value.</p>
<b>Horizontal / Vertical</b>	<p>Mutually exclusive STYLE attribute values: slider will scroll horizontally or vertically.</p> <p><b>Note:</b>  When you edit the STYLE attribute value in the scroll-bar control attributes window, setting "h" instead of "v" and vice versa, the RECTANGLE-H and RECTANGLE-W attribute values are exchanged. The dialog editor thus ensures that the scroll-bar control will not provide for vertical scrolling in a horizontal shape and vice versa.</p>
<b>Foreground color:</b>	
<b>Selection box</b>	FOREGROUND-COLOUR-NAME attribute value.
...	Dialog box for editing FOREGROUND-COLOUR-VALUE attribute value.
<b>Background color:</b>	
<b>Selection box</b>	BACKGROUND-COLOUR-NAME attribute value.
...	Dialog box for editing BACKGROUND-COLOUR-VALUE attribute value.
<b>OK</b>	Save settings and exit the window.
<b>Cancel</b>	Exit the window without saving the settings.
<b>Help</b>	Provides online help on the attributes window.