

# Spin Control Attributes Window

## ▶ Accessible Using

1. Double-click on the spin control (not on its buddy, if any); or
  2. if selected: "Control > Attributes" or by selecting 'Attributes...' from the control's context menu.
  3. if selected: ENTER.
- 

## Entries

### Note:

For context-sensitive help on attribute entries, select the entry so it has the focus, and press F1.

Entry in Attributes Window	Represents
<b>Name</b>	Handle name of the spin control control (may be overwritten with another name).
<b>Context Menu</b>	CONTEXT-MENU attribute value. Specifies the context menu (if any) associated with the control.
<b>Array...</b>	Dialog box for defining an array of input field controls.
<b>String</b>	STRING attribute value.
<b>...</b>	"Source" dialog box for determining sources of STRING attribute values.
<b>Font</b>	Output field where the font currently selected is displayed.
<b>...</b>	Dialog box for selecting fonts.
<b>DIL text</b>	DIL-TEXT attribute value (string).
<b>...</b>	Dialog box for determining sources of DIL-TEXT attribute values.
<b>Context Menu</b>	CONTEXT-MENU attribute value. Specifies the context menu (if any) associated with the control.
<b>Help ID</b>	HELP-ID attribute value. You must use the help topic's .h file to map the numerical ID that you enter here to the corresponding help topic ID (created by a markup in the .hlp file).
<b>Range:</b>	
<b>Min</b>	MIN attribute value. Lower limit of control's numeric range.
<b>Max</b>	MAX attribute value. Upper limit of control's numeric range.
<b>Pos.</b>	POSITION attribute value. Current position within control's numeric range.
<b>Style:</b>	
<b>Horizontal</b>	STYLE attribute value. Control is oriented horizontally, rather than vertically.

Entry in Attributes Window	Represents
<b>Left align</b>	STYLE attribute value. The control has an implicit buddy input field. The spin control's buttons are aligned to the left of the buddy.
<b>Right align</b>	STYLE attribute value. The control has an implicit buddy input field. The spin control's buttons are aligned to the right of the buddy.
<b>Set buddy</b>	STYLE attribute value. Buddy control (if any) is automatically set to indicate the spin control's position when the latter changes.
<b>Wrap</b>	STYLE attribute value. Control value wraps from maximum to minimum value, and vice versa, if scrolled past the corresponding limit.
<b>Arrow keys</b>	STYLE attribute value. The control's value can be scrolled via use of the arrow keys.
<b>No thousands</b>	STYLE attribute value. No thousands separators are displayed in the buddy control (if any). For example, "1234" instead of "1,234".
<b>Hot tracking</b>	<p>STYLE attribute value. Buttons are highlighted when traversed by the mouse cursor.</p> <p><b>Note:</b> This option is implicitly set if Windows XP styles are in use.</p>
<b>Hexadecimal</b>	<p>STYLE attribute value. Values are displayed in buddy control (if any) in hexadecimal format (e.g. "0x0032" instead of "50").</p> <p><b>Note:</b> This option is only effective if the "set buddy" style is also set.</p>
<b>State:</b>	
<b>Visible</b>	VISIBLE attribute value. Control will be shown.
<b>Enabled</b>	ENABLED attribute value. Control can accept user input.
<b>Rectangle:</b>	<p>The following four attributes decide the input field control's x and y axis position, its height and its width on the screen.</p> <p><b>X</b> - RECTANGLE-X attribute value.  <b>Y</b> - RECTANGLE-Y attribute value.  <b>W</b> - RECTANGLE-W attribute value.  <b>H</b> - RECTANGLE-H attribute value.</p>
<b>OK</b>	Save settings and exit the window.
<b>Cancel</b>	Exit the window without saving the settings.
<b>Help</b>	Provides online help on the attributes window.