

# Status Bar Control Attributes Subwindow

## ▶ Accessible Using

- Select the "Attributes..." button in the status bar control attributes window
- 

## Entries

### Note:

For context-sensitive help on attribute entries, select the entry so it has the focus, and press F1.

Entry in Attrib. Subwindow	Represents
<b>Control ID</b>	CLIENT-KEY attribute value (used in this context for associating a user-defined ID).
<b>Context Menu</b>	CONTEXT-MENU attribute value. Specifies the context menu (if any) associated with the control.
<b>Location</b>	LOCATION attribute value. Determines the side of the dialog on which the status bar control is initially positioned.
<b>Internal Metrics:</b>	
<b>Minimum height</b>	ITEM-H attribute value. Specifies the <i>minimum</i> height of the status bar panes (in pixels). This is particularly useful for status bar controls which display icons. By default, the minimum height of a status bar control depends on the font used to draw the text.
<b>Margin-X</b>	MARGIN-X attribute value. Specifies the margin (in pixels) to the left and right of the status bar panes.
<b>Margin-Y</b>	MARGIN-Y attribute value. Specifies the margin (in pixels) above and below the status bar panes.
<b>Borders:</b>	
<b>Top</b>	STYLE attribute value. Species whether a border should be displayed at the top of the control.
<b>Bottom</b>	STYLE attribute value. Species whether a border should be displayed at the bottom of the control.
<b>3-D</b>	STYLE attribute value. If set, the status bar control borders (if any) are drawn with a 3-D appearance.
<b>Style:</b>	
<b>Gripper</b>	STYLE attribute value. Determines whether a sizing gripper is displayed within the status bar control.
<b>State:</b>	
<b>Visible</b>	VISIBLE attribute value.

<b>Entry in Attrib. Subwindow</b>	<b>Represents</b>
<b>Enabled</b>	ENABLED attribute value.
<b>Tooltips</b>	HAS-TOOLTIP attribute value. If not set, display of the tool tip text (if any) for the status bar panes will be suppressed.
<b>OK</b>	Save settings and exit the window.
<b>Cancel</b>	Exit the window without saving the settings.
<b>Help</b>	Provides online help on the attributes window.