

Table Attributes Subwindow

▶ Accessible Using

- Select the "Attributes..." button in the table attributes window.
-

Entries

Note:

For context-sensitive help on attribute entries, select the entry so it has the focus, and press F1.

Entry in Attrib. Subwindow	Represents
Name	Handle name of the table (may be overwritten with another name).
Font	Output field where the font currently selected is displayed.
...	Dialog box for selecting fonts.
Header font	Output field where the font currently selected for the table header is displayed.
...	Dialog box for selecting fonts.
DIL text	DIL-TEXT attribute value (string).
...	Dialog box for determining sources of DIL-TEXT attribute values.
Context Menu	CONTEXT-MENU attribute value. Specifies the context menu (if any) associated with the control.
Rectangle:	The following four attributes decide the table's x and y axis position, its height and its width on the screen. X - RECTANGLE-X attribute value. Y - RECTANGLE-Y attribute value. W - RECTANGLE-W attribute value. H - RECTANGLE-H attribute value.
Row count	ROW-COUNT attribute value.
Row height	ROW-HEIGHT attribute value.
Header height	HEADER-HEIGHT attribute value.
Width 1st col.	FIRST-COLUMN-WIDTH attribute value.
Frozen cols.	FIRST-COLUMN-WIDTH attribute value.
Help ID	HELP-ID attribute value. You must use the help topic's .h file to map the numerical ID that you enter here to the corresponding help topic ID (created by a markup in the .hlp file).
First visible col.	FIRST-VISIBLE-COLUMN attribute value.
First visible row	FIRST-VISIBLE-ROW attribute value.

Entry in Attrib. Subwindow	Represents
Columns header	STYLE attribute value: buttons with field names are displayed at the top of each column.
Extendable	STYLE attribute value: end users can delete and insert rows using DEL and INS.
No lines	STYLE attribute value: the table control is displayed without the lines that normally separate the cells.
Resize columns	STYLE attribute value: end users may resize the columns horizontally.
Single cell selection	STYLE attribute value: if set, end users may only select single cells. If not set, end users may select ranges of cells.
Resize rows	STYLE attribute value: end users may resize the rows vertically.
Whole row selection	STYLE attribute value: selecting an individual cell sets the selection to the entire row.
Draggable columns	STYLE attribute value: if set, end users may drag the columns.
Integral height	STYLE attribute value: partial rows are not displayed.
Foreground color:	
Selection box	FOREGROUND-COLOUR-NAME attribute value.
...	Dialog box for editing FOREGROUND-COLOUR-VALUE attribute value.
Background color:	
Selection box	BACKGROUND-COLOUR-NAME attribute value.
...	Dialog box for editing BACKGROUND-COLOUR-VALUE attribute value.
State:	
Visible	VISIBLE attribute value.
Enabled	ENABLED attribute value.
Modifiable	MODIFIABLE attribute value.
RTL	RTL attribute value. If this entry is checked, the dialog element direction is right-to-left.
Has first column	HAS-FIRST-COLUMN attribute value.
Horizontal scroll bar	HORIZ-SCROLLABLE attribute value.
Vertical scroll bar	VERT-SCROLLABLE attribute value.
OK	Save settings and exit the window.
Cancel	Exit the window without saving the settings.
Help	Provides online help on the attributes window.