

Natural System Error Messages 5601-5650

NAT5601: DSNAME missing.

| | |
|-------|--|
| Text | DSNAME missing |
| Expl. | Dataset Name is required, to catalog a Dataset |

NAT5602: Device is invalid.

| | |
|-------|--|
| Text | ESY5602 Device is invalid. |
| Expl. | An invalid DEVICE value was specified. |
| Actn. | Specify valid DEVICE value. |

NAT5603: INDEX / ALIAS missing.

| | |
|-------|--------------------------------|
| Text | ESY5603 INDEX / ALIAS missing. |
| Actn. | Specify INDEX / ALIAS. |

NAT5604: No volumes specified.

| | |
|-------|--|
| Text | ESY5604 No volumes specified. |
| Expl. | No VOLUMES were specified for CATLG / RECATLG. |
| Actn. | Specify VOLUMES. |

NAT5605: IGWASMS returned with RC :1: and reason :2:.

| | |
|-------|--|
| Text | ESY5605 IGWASMS returned with RC :1: and reason :2:. |
| Expl. | A request failed to retrieve attributes for a dataset. |
| Actn. | Contact your systems programmer. |

NAT5606: Managed data sets cannot be uncataloged.

| | |
|-------|---|
| Text | ESY5606 Managed data sets cannot be uncataloged. |
| Expl. | A request was issued to uncatalog an SMS-managed dataset. |
| Actn. | Do no request to uncatalog an SMS-managed dataset. |

NAT5610: QNAME is missing.

| | |
|-------|--|
| Text | ESY5610 QNAME is missing. |
| Expl. | No value was specified in the QNAME field. |
| Actn. | Specify valid QNAME value. |

NAT5611: QNAME cannot start with SYS.

| | |
|-------|---|
| Text | ESY5611 QNAME cannot start with SYS. |
| Expl. | Major names beginning with SYS are not allowed. |
| Actn. | Specify valid QNAME value. |

NAT5612: RNAME is missing.

| | |
|-------|--|
| Text | ESY5612 RNAME is missing. |
| Expl. | No value was specified in the RNAME field. |
| Actn. | Specify RNAME value. |

NAT5613: RNAME length is missing or invalid.

| | |
|-------|---|
| Text | ESY5613 RNAME length is missing or invalid. |
| Expl. | No value was specified in the RNAME-LENGTH field. |
| Actn. | Specify valid RNAME-LENGTH value. |

NAT5614: Resource is in use.

| | |
|-------|--|
| Text | ESY5614 Resource is in use. |
| Expl. | Resource is already allocated as sharable by another task, and exclusive access was requested. |
| Actn. | Retry at a later time. |

NAT5615: Resource held by another task.

| | |
|-------|--|
| Text | ESY5615 Resource held by another task. |
| Expl. | Resource is already allocated exclusively by another task. |
| Actn. | Retry at a later time. |

NAT5616: Error in CQSCAN routine.

| | |
|-------|--|
| Text | ESY5616 Error in GQSCAN routine. |
| Expl. | An internal error occurred as a result of the GQSCAN macro request. |
| Actn. | Notify systems programmer. (Software AG technical support should be notified as well). |

NAT5621: Identifier missing/duplicate/not found.

| | |
|-------|--|
| Text | ESY5621 Identifier missing/duplicate/not found. |
| Expl. | The identifier associated with the area was missing/duplicate/not found. |
| Actn. | Specify correct identifier. |

NAT5622: NUMBER-OF-ENTRIES missing or invalid.

| | |
|-------|---|
| Text | ESY5622 NUMBER-OF-ENTRIES missing or invalid. |
| Expl. | The specification of the maximum number of entries was missing/invalid. |
| Actn. | Specify a valid NUMBER-OF-ENTRIES value. |

NAT5623: ENTRY-LENGTH missing or invalid.

| | |
|-------|--|
| Text | ESY5623 ENTRY-LENGTH missing or invalid. |
| Expl. | The specification of the entry length was missing/invalid. |
| Actn. | Specify a valid ENTRY-LENGTH value. |

NAT5624: ENTRY-NUMBER missing or invalid.

| | |
|-------|--|
| Text | ESY5624 ENTRY-NUMBER missing or invalid. |
| Expl. | The specification of the entry number was missing/invalid. |
| Actn. | Specify correct entry number. |

NAT5625: Cannot allocate area.

| | |
|-------|--|
| Text | ESY5625 Cannot allocate area. |
| Expl. | Insufficient storage was available to allocate the area. |
| Actn. | Decrease amount of requested storage or notify systems programmer. |

NAT5626: DATA missing.

| | |
|-------|-------------------------|
| Text | ESY5626 DATA missing. |
| Expl. | No data was specified. |
| Actn. | Specify the DATA field. |

NAT5627: Field position + length > 250.

| | |
|-------|--|
| Text | ESY5627 Field position + length > 250. |
| Expl. | The field extends the maximum area length (250). |
| Actn. | Specify valid field position/length. |

NAT5628: Error in editor.

| | |
|-------|------------------------------------|
| Text | ESY5628 Error in editor. |
| Expl. | An internal editor error occurred. |
| Actn. | Notify system programmer. |

NAT5629: Area is protected.

| | |
|-------|----------------------------|
| Text | ESY5629 Area is protected. |
| Expl. | Area is protected. |
| Actn. | No action required. |

NAT5630: Console not defined or not active.

| | |
|-------|--|
| Text | ESY5630 Console not defined or not active. |
| Expl. | The specified console ID was not found. |
| Actn. | Specify valid console ID. |

NAT5631: Console table not found.

| | |
|-------|-----------------------------------|
| Text | ESY5631 Console table not found. |
| Expl. | Console table could not be found. |
| Actn. | Contact your systems programmer. |

NAT5632: General or Control object not found.

| | |
|-------|---|
| Text | ESY5632 General or Control object not found. |
| Expl. | General or Control object returned by Multi Console Support (MCS) could not be found. |
| Actn. | Contact your systems programmer. |

NAT5633: Cannot lock Console table.

| | |
|-------|---|
| Text | ESY5633 Cannot lock Console table. |
| Expl. | Console table could not be locked for exclusive use. |
| Actn. | Retry operation. If problem persists, please contact your systems programmer. |

NAT5634: Invalid record number.

| | |
|-------|---|
| Text | ESY5634 Invalid record number. |
| Expl. | Requested record number is invalid. |
| Actn. | Retry operation. If problem persists, please contact your systems programmer. |

NAT5635: Attempt to alter key in KSDS file.

| | |
|-------|--|
| Text | ESY5635 Attempt to alter key in KSDS file. |
| Expl. | It is not allowed to alter keys in KSDS files. |
| Actn. | Check program and correct error. |

NAT5636: Too many active requests on this ACB.

| | |
|-------|---|
| Text | ESY5636 Too many active requests on this ACB. |
| Expl. | There may be a nested loop while accessing VSAM files or there are too many parallel requests open. |
| Actn. | Check your program and check also with your ESY-DBA. |

NAT5637: VSAM subtask is not active.

| | |
|-------|---|
| Text | ESY5637 VSAM subtask is not active. |
| Expl. | The ESY subtask for VSAM access may be abended. Check with your ESY-DBA to restart ESY. |
| Actn. | Contact your ESY-DBA or contact Software AG technical support. |

NAT5638: Key not found.

| | |
|-------|--|
| Text | ESY5638 Key not found. |
| Expl. | Key to access the requested record in your file not found. |
| Actn. | Check program and correct error. |

NAT5639: Cannot delete record in ESDS file.

| | |
|-------|--|
| Text | ESY5639 Cannot delete record in ESDS file. |
| Expl. | It is not allowed to delete records from ESDS-files. |
| Actn. | Check program and correct error. |

NAT5640: Error generating VSAM control blocks.

| | |
|-------|---|
| Text | ESY5640 Error generating VSAM control blocks. |
| Expl. | An error occurred generating VSAM control blocks. |
| Actn. | Notify systems programmer. |

NAT5641: Error :1: while opening SMF or VSAM file.

| | |
|-------|---|
| Text | ESY5641 Error :1: while opening SMF or VSAM file. |
| Expl. | A VSAM error occurred while opening an SMF file. |
| Actn. | Notify systems programmer. |

NAT5642: Error :1: while reading SMF or VSAM file.

| | |
|-------|---|
| Text | ESY5642 Error :1: while reading SMF or VSAM file. |
| Expl. | A VSAM error occurred while reading an SMF file. |
| Actn. | Notify systems programmer. |

NAT5643: SMF not active / not recording.

| | |
|-------|---|
| Text | ESY5643 SMF not active / not recording. |
| Expl. | At time of the request SMF is not active / not recording. |
| Actn. | Notify systems programmer. |

NAT5644: :1:.

| | |
|-------|---|
| Text | ESY5644 xxxxxxxx error in POWER interface aabb. |
| Expl. | Error aabb returned by POWER interface function xxxxxxxx. |
| Actn. | Contact systems programmer. |

NAT5645: Invalid RBA was specified.

| | |
|-------|------------------------------------|
| Text | ESY5645 Invalid RBA was specified. |
| Expl. | The requested RBA was not found. |
| Actn. | Specify valid RBA value. |

NAT5646: Write to VSAM only allowed on base cluster.

| | |
|-------|--|
| Text | ESY5646 Write to VSAM only allowed on base cluster. |
| Expl. | An attempt was made to write to a none base cluster. |
| Actn. | Check program and correct error. |

NAT5647: VSAM cluster is not defined as reusable.

| | |
|-------|--|
| Text | ESY5647 VSAM cluster is not defined as reusable. |
| Expl. | Access to VSAM cluster only allowed if reusable. |
| Actn. | Define your VSAM cluster reusable. |

NAT5648: Record not in ascending key sequence.

| | |
|-------|---|
| Text | ESY5648 Record not in ascending key sequence. |
| Expl. | An attempt was made to write a record with a wrong key. |
| Actn. | Check program and correct error. |

NAT5649: ESY User not found or cannot be cancelled.

| | |
|-------|--|
| Text | ESY5649 ESY User not found or cannot be cancelled. |
| Expl. | The ESY user could not be found for various functions. |
| Actn. | Correct input data. |

NAT5650: Invalid sequential file.

| | |
|-------|---|
| Text | ESY5650 Invalid sequential file. |
| Expl. | The requested sequential file does not exist. |
| Actn. | Check file name, and re-run program. |