INatAutoDialogs INatAutoDialogs

# **INatAutoDialogs**

This chapter covers the following topics:

- Purpose
- Properties
- Methods

## **Purpose**

Collection of the dialogs currently open in a dialog editor window.

## **Properties**

The following properties are available:

- Parent
- Studio
- Count

#### **Parent**

Used to navigate to the parent interface of this interface.

Natural Data Format	Variant Type	Remark
HANDLE OF OBJECT	VT_DISPATCH (INatAutoObjects)	Get only

### **Studio**

Used to navigate to the root interface.

Natural Data Format Variant Type		Remark
HANDLE OF OBJECT	VT_DISPATCH (INatAutoStudio)	Get only

## Count

The number of dialogs currently open in a data area editor window.

Natural Data Format	Variant Type	Remark
I4	VT_I4	Get only

INatAutoDialogs Methods

## **Methods**

The following methods are available:

- Item
- Add
- Open

### **Item**

Returns a specific dialog from the collection.

#### **Parameters**

Name	Natural Data Format	Variant Type	Remark
Return value	HANDLE OF OBJECT	VT_DISPATCH (INatAutoDialog)	
Index	I4	VT_I4	
	A	VT_BSTR	
Library	A	VT_BSTR	Optional

#### **Return value**

The dialog identified by the value specified in Index.

#### **Index**

Identifies a specific dialog in the collection. This can be either the index of the dialog in the collection (a value between 1 and Count) or the name of the dialog.

### Library

Used to identify a specific dialog by name (specified in Index) and library (specified in Library).

### Add

Creates a new (untitled) dialog and opens it in a dialog editor window.

#### **Parameters**

Name	Natural Data Format	Variant Type	Remark
Return value	HANDLE OF OBJECT	VT_DISPATCH (INatAutoDialog)	
Visible	L	VT_BOOL	Optional

#### Return value

Open INatAutoDialogs

The newly created dialog.

#### Visible

Decides if the editor is opened visibly or not. By default, the editor is opened visibly.

## **Open**

Opens an existing dialog in a dialog editor window.

#### **Parameters**

Name	Natural Data Format	Variant Type	Remark
Return value	HANDLE OF OBJECT	VT_DISPATCH (INatAutoDialog)	
Name	A	VT_BSTR	
Library	A	VT_BSTR	Optional
Visible	L	VT_BOOL	Optional

### Return value

The newly opened dialog.

#### Name

The name of the dialog to open.

## Library

The library of the dialog to open.

#### Visible

Decides if the editor is opened visibly or not. By default, the editor is opened visibly.