

Natural System Error Messages 5601-5650

NAT5601: DSNAME missing.

Text	DSNAME missing
Expl.	Dataset Name is required, to catalog a Dataset

NAT5602: Device is invalid.

Text	ESY5602 Device is invalid.
Expl.	An invalid DEVICE value was specified.
Actn.	Specify valid DEVICE value.

NAT5603: INDEX / ALIAS missing.

Text	ESY5603 INDEX / ALIAS missing.
Actn.	Specify INDEX / ALIAS.

NAT5604: No volumes specified.

Text	ESY5604 No volumes specified.
Expl.	No VOLUMES were specified for CATLG / RECATLG.
Actn.	Specify VOLUMES.

NAT5605: IGWASMS returned with RC :1: and reason :2:.

Text	ESY5605 IGWASMS returned with RC :1: and reason :2:.
Expl.	A request failed to retrieve attributes for a dataset.
Actn.	Contact your systems programmer.

NAT5606: Managed data sets cannot be uncataloged.

Text	ESY5606 Managed data sets cannot be uncataloged.
Expl.	A request was issued to uncatalog an SMS-managed dataset.
Actn.	Do no request to uncatalog an SMS-managed dataset.

NAT5610: QNAME is missing.

Text	ESY5610 QNAME is missing.
Expl.	No value was specified in the QNAME field.
Actn.	Specify valid QNAME value.

NAT5611: QNAME cannot start with SYS.

Text	ESY5611 QNAME cannot start with SYS.
Expl.	Major names beginning with SYS are not allowed.
Actn.	Specify valid QNAME value.

NAT5612: RNAME is missing.

Text	ESY5612 RNAME is missing.
Expl.	No value was specified in the RNAME field.
Actn.	Specify RNAME value.

NAT5613: RNAME length is missing or invalid.

Text	ESY5613 RNAME length is missing or invalid.
Expl.	No value was specified in the RNAME-LENGTH field.
Actn.	Specify valid RNAME-LENGTH value.

NAT5614: Resource is in use.

Text	ESY5614 Resource is in use.
Expl.	Resource is already allocated as sharable by another task, and exclusive access was requested.
Actn.	Retry at a later time.

NAT5615: Resource held by another task.

Text	ESY5615 Resource held by another task.
Expl.	Resource is already allocated exclusively by another task.
Actn.	Retry at a later time.

NAT5616: Error in CQSCAN routine.

Text	ESY5616 Error in GQSCAN routine.
Expl.	An internal error occurred as a result of the GQSCAN macro request.
Actn.	Notify systems programmer. (Software AG technical support should be notified as well).

NAT5621: Identifier missing/duplicate/not found.

Text	ESY5621 Identifier missing/duplicate/not found.
Expl.	The identifier associated with the area was missing/duplicate/not found.
Actn.	Specify correct identifier.

NAT5622: NUMBER-OF-ENTRIES missing or invalid.

Text	ESY5622 NUMBER-OF-ENTRIES missing or invalid.
Expl.	The specification of the maximum number of entries was missing/invalid.
Actn.	Specify a valid NUMBER-OF-ENTRIES value.

NAT5623: ENTRY-LENGTH missing or invalid.

Text	ESY5623 ENTRY-LENGTH missing or invalid.
Expl.	The specification of the entry length was missing/invalid.
Actn.	Specify a valid ENTRY-LENGTH value.

NAT5624: ENTRY-NUMBER missing or invalid.

Text	ESY5624 ENTRY-NUMBER missing or invalid.
Expl.	The specification of the entry number was missing/invalid.
Actn.	Specify correct entry number.

NAT5625: Cannot allocate area.

Text	ESY5625 Cannot allocate area.
Expl.	Insufficient storage was available to allocate the area.
Actn.	Decrease amount of requested storage or notify systems programmer.

NAT5626: DATA missing.

Text	ESY5626 DATA missing.
Expl.	No data was specified.
Actn.	Specify the DATA field.

NAT5627: Field position + length > 250.

Text	ESY5627 Field position + length > 250.
Expl.	The field extends the maximum area length (250).
Actn.	Specify valid field position/length.

NAT5628: Error in editor.

Text	ESY5628 Error in editor.
Expl.	An internal editor error occurred.
Actn.	Notify system programmer.

NAT5629: Area is protected.

Text	ESY5629 Area is protected.
Expl.	Area is protected.
Actn.	No action required.

NAT5630: Console not defined or not active.

Text	ESY5630 Console not defined or not active.
Expl.	The specified console ID was not found.
Actn.	Specify valid console ID.

NAT5631: Console table not found.

Text	ESY5631 Console table not found.
Expl.	Console table could not be found.
Actn.	Contact your systems programmer.

NAT5632: General or Control object not found.

Text	ESY5632 General or Control object not found.
Expl.	General or Control object returned by Multi Console Support (MCS) could not be found.
Actn.	Contact your systems programmer.

NAT5633: Cannot lock Console table.

Text	ESY5633 Cannot lock Console table.
Expl.	Console table could not be locked for exclusive use.
Actn.	Retry operation. If problem persists, please contact your systems programmer.

NAT5634: Invalid record number.

Text	ESY5634 Invalid record number.
Expl.	Requested record number is invalid.
Actn.	Retry operation. If problem persists, please contact your systems programmer.

NAT5635: Attempt to alter key in KSDS file.

Text	ESY5635 Attempt to alter key in KSDS file.
Expl.	It is not allowed to alter keys in KSDS files.
Actn.	Check program and correct error.

NAT5636: Too many active requests on this ACB.

Text	ESY5636 Too many active requests on this ACB.
Expl.	There may be a nested loop while accessing VSAM files or there are too many parallel requests open.
Actn.	Check your program and check also with your ESY-DBA.

NAT5637: VSAM subtask is not active.

Text	ESY5637 VSAM subtask is not active.
Expl.	The ESY subtask for VSAM access may be abended. Check with your ESY-DBA to restart ESY.
Actn.	Contact your ESY-DBA or contact Software AG technical support.

NAT5638: Key not found.

Text	ESY5638 Key not found.
Expl.	Key to access the requested record in your file not found.
Actn.	Check program and correct error.

NAT5639: Cannot delete record in ESDS file.

Text	ESY5639 Cannot delete record in ESDS file.
Expl.	It is not allowed to delete records from ESDS-files.
Actn.	Check program and correct error.

NAT5640: Error generating VSAM control blocks.

Text	ESY5640 Error generating VSAM control blocks.
Expl.	An error occurred generating VSAM control blocks.
Actn.	Notify systems programmer.

NAT5641: Error :1: while opening SMF or VSAM file.

Text	ESY5641 Error :1: while opening SMF or VSAM file.
Expl.	A VSAM error occurred while opening an SMF file.
Actn.	Notify systems programmer.

NAT5642: Error :1: while reading SMF or VSAM file.

Text	ESY5642 Error :1: while reading SMF or VSAM file.
Expl.	A VSAM error occurred while reading an SMF file.
Actn.	Notify systems programmer.

NAT5643: SMF not active / not recording.

Text	ESY5643 SMF not active / not recording.
Expl.	At time of the request SMF is not active / not recording.
Actn.	Notify systems programmer.

NAT5644: :1:.

Text	ESY5644 xxxxxxxx error in POWER interface aabb.
Expl.	Error aabb returned by POWER interface function xxxxxxxx.
Actn.	Contact systems programmer.

NAT5645: Invalid RBA was specified.

Text	ESY5645 Invalid RBA was specified.
Expl.	The requested RBA was not found.
Actn.	Specify valid RBA value.

NAT5646: Write to VSAM only allowed on base cluster.

Text	ESY5646 Write to VSAM only allowed on base cluster.
Expl.	An attempt was made to write to a none base cluster.
Actn.	Check program and correct error.

NAT5647: VSAM cluster is not defined as reusable.

Text	ESY5647 VSAM cluster is not defined as reusable.
Expl.	Access to VSAM cluster only allowed if reusable.
Actn.	Define your VSAM cluster reusable.

NAT5648: Record not in ascending key sequence.

Text	ESY5648 Record not in ascending key sequence.
Expl.	An attempt was made to write a record with a wrong key.
Actn.	Check program and correct error.

NAT5649: ESY User not found or cannot be cancelled.

Text	ESY5649 ESY User not found or cannot be cancelled.
Expl.	The ESY user could not be found for various functions.
Actn.	Correct input data.

NAT5650: Invalid sequential file.

Text	ESY5650 Invalid sequential file.
Expl.	The requested sequential file does not exist.
Actn.	Check file name, and re-run program.