

# Natural System Error Messages 5651-5700

## NAT5651: Requested catalog does not exist.

Text	ESY5651 Requested catalog does not exist.
Expl.	The requested CVOL does not exist.
Actn.	Specify valid CVOL.

## NAT5652: Catalog structure inconsistent.

Text	ESY5652 Catalog structure inconsistent.
Expl.	The catalog structure is inconsistent.
Actn.	Notify the systems programmer.

## NAT5653: Cannot delete index.

Text	ESY5653 Cannot delete index.
Expl.	The index cannot be deleted.
Actn.	No action is required.

## NAT5654: Index structure does not exist.

Text	ESY5654 Index structure does not exist.
Actn.	No action is required.

## NAT5655: Insufficient space on catalog data set.

Text	ESY5655 Insufficient space on catalog data set.
Expl.	The catalog dataset is full.
Actn.	Notify the systems programmer.

## NAT5656: Error cataloging generation data set.

Text	ESY5656 Error cataloging generation data set.
Expl.	An error occurred while cataloging a generation dataset.
Actn.	Check specified values. If valid, contact the systems programmer.

**NAT5657: I/O error on catalog.**

Text	ESY5657 I/O error on catalog.
Expl.	An I/O error occurred while accessing the catalog.
Actn.	This is probably a hardware error. Contact the systems programmer.

**NAT5658: Data set is not catalogued.**

Text	ESY5658 Data set is not catalogued.
Expl.	The specified dataset is not catalogued.
Actn.	No action is required.

**NAT5659: Data set is already catalogued.**

Text	ESY5659 Data set is already catalogued.
Expl.	The specified dataset is already catalogued.
Actn.	No action is required.

**NAT5660: :1: - :2: module not available.**

Text	ESY5660 ... - ... module not available.
Expl.	The specified Natural module was not found.
Actn.	Specify the name of an existing Natural module.

**NAT5661: :1: - NATURAL sub-task already active.**

Text	ESY5661 :1: - NATURAL sub-task already active.
Expl.	A Natural subtask is already active for this user.
Actn.	Make sure that subtask is closed prior restarting it.

**NAT5662: :1: - NATURAL sub-task not allowed.**

Text	ESY5662 :1: - NATURAL sub-task not allowed.
Expl.	The Natural subtask system has not been initialized.
Actn.	Notify systems programmer.

**NAT5663: :1: - NATURAL sub-task not active.**

Text	ESY5663 :1: - NATURAL sub-task not active.
Expl.	The Natural subtask does not exist.
Actn.	No action is required.

**NAT5664: :1: - NATURAL sub-task table full.**

Text	ESY5664 :1: - NATURAL sub-task table full.
Expl.	The maximum number of Natural subtasks is reached.
Actn.	Notify systems programmer.

**NAT5665: :1: - invalid action requested.**

Text	ESY5665 :1: - invalid action requested.
Expl.	An invalid action was requested.
Actn.	Specify valid action.

**NAT5666: :1: - NATURAL sub-task must have parameters.**

Text	ESY5666 :1: - NATURAL sub-task must have parameters.
Expl.	An attempt was made to start a Natural subtask without parameters.
Actn.	Specify parameter for Natural subtask.

**NAT5669: Invalid specification for keyword.**

Text	ESY5669 Queue or job name invalid.
Expl.	Submit JCL contains error.
Actn.	Correct JCL error and rerun program.

**NAT5670: View not supported.**

Text	ESY5670 View not supported.
Expl.	This view is not supported on the local operating system.

**NAT5671: Class missing or is invalid.**

Text	ESY5671 Class missing or is invalid.
Expl.	The function CHANGE requires a valid NEW-CLASS, NEW-DESTINATION or NEW-USERID value.

**NAT5672: Segment option requires JOBNAME/JOBNUMBER.**

Text	ESY5672 Segment option requires JOBNAME/JOBNUMBER.
Expl.	Specifying the SEGMENT option (SEGMENT-NUMBER > 0) requires that the job is identified with JOB-NAME and JOB-NUMBER.

**NAT5673: Access error due to FILETABLE=STATIC.**

Text	ESY5673 Access error due to FILETABLE=STATIC.
Expl.	The requested file could not be accessed because the Entire System Server startup parameter FILETABLE was specified as STATIC. Only those files available at ESY initialization time (STD,PARSTD & TEMP labels) can therefore be accessed.
Actn.	To allow dynamic access of files NOT specified at ESY initialization time, change the FILETABLE parameter to DYNAMIC and restart Entire System Server.

**NAT5674: VTOC error reading format-3 labels.**

Text	ESY5674 VTOC error reading format-3 labels.
Expl.	VTOC error reading format-3 labels for the requested file.
Actn.	Information message only. No action necessary or possible.

**NAT5675: :1: not supported.**

Text	ESY5675 :1: not supported.
Expl.	Entire System Server has detected that the requested file has attributes which are not supported by this version of ESY e.g. Multi-volume files, Multi-extent output files etc.

**NAT5676: Not first volume of a multi volume file.**

Text	ESY5676 Not first volume of a multi-volume file.
Expl.	Entire System Server has detected that the file on the specified volume is NOT the first volume/extent of a multi-volume file.

**NAT5677: FAMS ERROR, R15=XXXXXXXX, R0=XXXXXXXX**

Expl.	A FAMS error occurred while COPY-FILE was copying one or more program objects.
Actn.	Check the console log for IGW prefixed messages issued by FAMS for further information

**NAT5678: Member already exists.**

Text	ESY5678 Member already exists.
Expl.	In WRITE-FILE or COPY-FILE, REPLACE = "NO" was specified, however the member exists.
Actn.	No action required.

**NAT5679: Input and output files are incompatible.**

Text	ESY5679 Input and output files are incompatible.
Expl.	COPY-FILE has determined that the record formats of the input and output files are not compatible (RECFM does not match, block size incompatibilities, etc.).
Actn.	Verify dataset attributes and reissue request with correct parameters.

**NAT5680: Job/output is protected.**

Text	ESY5680 Job/output is protected.
Expl.	The user is not authorized to access the specified job/output.
Actn.	Notify systems programmer.

**NAT5681: Job/output is active.**

Text	ESY5681 Job/output is active.
Expl.	The specified job/output is currently active.
Actn.	There is no action required.

**NAT5682: Job/output is not dispatchable.**

Text	ESY5682 Job/output is not dispatchable.
Expl.	The job/output is not dispatchable.
Actn.	There is no action required.

**NAT5683: FAMS error, R15=:1:, R0=:2:.**

Text	ESY5683 FAMS error, R15=:1:, R0=:2:.
Expl.	A FAMS error occurred while COPY-FILE was copying one or more program objects.
Actn.	Check the console log for IGW prefixed messages issued by FAMS for further information.

**NAT5684: Remote program object copy currently unsupported.**

Text	ESY5684 Remote program object copy currently unsupported.
Expl.	In this release of Entire System Server, use of COPY-FILE on OS/390 for copying program objects between different nodes is not supported. This message is also issued if a program object copy request is issued to a VSE/ESA node.
Actn.	A workaround is to first copy the program object to a PDS on the local node, then copy to a PDS on the remote node, then copy to the target PDSE.

**NAT5685: FAMS subtask abended.**

Text	FAMS subtask abended.
Expl.	One of the subtasks used by remote program object copy has abnormally terminated. The ERROR-NODE and ERROR-VIEW fields will show which node had the ABEND. Information regarding the ABEND will be in the JES log.
Actn.	Contact Software AG support.

**NAT5687: Bad variable record.**

Text	ESY5687 Bad variable record.
Expl.	Bad variable record.
Actn.	No action is required.

**NAT5688: Return code :1: HCF function :2:.**

Text	ESY5688 Return code :1: HCF function :2:.
Expl.	The HCF function failed. The return code is the HCF return code.
Actn.	Notify systems programmer.

**NAT5690: :1: error :2: during :3:.**

Text	ESY5690 1: error :2: during :3:.
Expl.	An error occurred accessing PANVALET or LIBRARIAN data.
Actn.	Notify systems programmer.

**NAT5691: Error while accessing librarian member.**

Text	ESY5691 Error while accessing librarian member.
Expl.	An error occurred accessing a LIBRARIAN member.
Actn.	There is no action required.

**NAT5692: You are not permitted to access member.**

Text	ESY5692 You are not permitted to access member.
Expl.	This user is not authorized to access the specified member.
Actn.	Check with systems programmer.

**NAT5693: :1:.**

Text	ESY5693 :1:.
Expl.	A PANVALET error occurred.
Actn.	See message text.

**NAT5694: Strange error opening VTOC.**

Text	ESY5694 Strange error opening VTOC.
Expl.	A strange internal error occurred reading the VTOC.
Actn.	Notify systems programmer.

**NAT5695: VTOC is in use.**

Text	ESY5695 VTOC is in use.
Expl.	The VTOC is currently in use.
Actn.	Retry.

**NAT5696: Cannot assign logical unit.**

Text	ESY5696 Cannot assign logical unit.
Expl.	A logical unit could not be assigned.
Actn.	Notify systems programmer.

**NAT5697: Library/sublibrary not found.**

Text	ESY5697 Library/sublibrary not found.
Expl.	The specified library/sublibrary was not found.
Actn.	Specify valid library/sublibrary name.

**NAT5698: Internal LIBRARIAN error has occurred.**

Text	ESY5698 Internal LIBRARIAN error has occurred.
Expl.	An internal LIBRARIAN error occurred.
Actn.	Notify systems programmer.

**NAT5699: Not enough main storage available.**

Text	ESY5699 Not enough main storage available.
Expl.	Not enough main storage was available to process the request.
Actn.	Notify systems programmer.

**NAT5700: Invalid value specified (DSORG / RECFM / TYPE).**

Text	ESY5700 Invalid value specified (DSORG / RECFM / TYPE).
Expl.	An invalid value was specified for view FILE-ALLOCATE. Note: A more detailed message is returned when field ERROR-TEXT is specified.
Actn.	Specify valid value for DSORG / RECFM / TYPE.